



acdsee™ Photo Studio

Home 2026



Contents

CHAPTER 1: GETTING STARTED	19
Welcome to ACDSee Photo Studio Home 2026	19
The Benefits of ACDSee	19
Using the User Guide	19
Automatically Imported Settings	20
About the ACDSee User Interface	21
Manage Mode	21
Media Mode	22
View Mode	22
Edit Mode	22
People Mode	22
365 Mode	22
Dashboard Mode	22
Switching Modes in ACDSee	23
Using Manage Mode	23
About the Manage Mode Panes	23
Manage Mode Drop-Down Menus	25
Working with Manage Mode Panes	25
Moving Panes	26
Docking Panes	26
Stacking Panes	26
Resizing Panes	27
Resetting the Layout	27
Using Media Mode	27
Header Button Bar	28
My Folders	29
Display Area	29
Toggle Between Grid and Full Screen View	29
Filter By	29
Sort and Group	30
Group By and Properties Panes	30

Navigation Buttons in Media Mode	30
Deleting Images in Media Mode	30
Using View Mode	30
Viewing Images in Full Screen Mode	31
Using the View Mode Panes	32
Using the Bottom Toolbar	32
Using Windows Touch Gestures™ with View Mode	35
Switching to Manage Mode	35
Using Edit Mode	35
Using 365 Mode	36
Uploading Images	36
Using Dashboard Mode	37
Cataloging Files	37
Dashboard Mode Tabs	37
<hr/>	
CHAPTER 2: GETTING HELP	39
Using the Quick Start Guide	39
Finding Other Resources and Support	39
Using the Help Menu	39
Online Help and ACDSee Connect	40
<hr/>	
CHAPTER 3: MANAGE MODE	41
ACDSee Home Page	41
Quick Search Bar	42
Search Buttons	42
Action Buttons	43
Importing Files with ACDSee Home	43
Import Status	43
Importing Files Using the Windows AutoPlay Dialog Box	44
Importing Files from Specific Types of Devices	44
RAW + JPEG Options	44
About Removable Devices	45
Importing Photos from a Device	45
Importing Photos From a Scanner	50

Importing Photos From a CD or DVD	51
Importing Photos From a Disk	51
Creating a Renaming Template	52
Importing a Lightroom® Database	54
Working with Images on Mobile	54
Sending Images to ACDSee from Your Mobile Device Using ACDSee Mobile Sync	55
Getting Started	56
Sending Images and Videos	57
Troubleshooting for Mobile Sync	58
Browsing Files in the File List Pane	58
Using the File List Pane	58
Changing Overlay Icon Visibility	62
Maximizing the File List Pane	62
Browsing Using the Folders Pane	63
Selecting Multiple Folders	63
Creating and Managing Folders	64
Browsing Using ACDSee Tabs	64
Startup Behavior	64
Managing ACDSee Tabs	64
Closing Tabs	65
Tab Navigation	66
Transferring Files Between Tabs	66
Managing Panes and Options in ACDSee Tabs	66
Performing Searches Using ACDSee Tabs	66
Using Microsoft OneDrive™	66
Browsing Files By Date or Event	68
Adding Descriptions and Thumbnails in Events View	70
Browsing Your Favorite Files	71
Accessing the Shortcuts Pane	71
Creating a Shortcut	71
Creating a New Folder	71
Deleting a Shortcut or Folder	72
Detecting Faces in Manage Mode	72

Embedding, Retrieving, and Importing Face Data	73
Changing Views	74
Customizing the Details View	75
Filtering Files	76
Grouping Files	77
Navigating Through Groups in the File List	77
Removing Groups from the File List	78
Selecting Files in One or More Groups	78
Sorting Files	78
Sorting Files Using Column Headers	79
Custom Sorting Files	79
Selecting Files	80
Previewing Images	80
The Information Palette	81
Rotating Images	82
Comparing Images	83
Gathering Images in an Image Basket	86
Using the ACDSee Activity Manager	87
Opening the Activity Manager	87
Queued Activities	87
Notifications	88
Idle Activities	89
History	90
Clearing History	91
Activity Manager Options:	91
Cataloging and Managing Files in ACDSee Home	92
Organizing with the Catalog Pane	92
Categories	92
People	93
Keywords	93
Ratings	93
Color Labels	93
Auto Categories	93

Advanced Searches	94
Special Items	94
The ACDSee Home Database and Embedded Data	95
Easy-Select Bars	95
Match All Match Any	96
Creating Categories	97
Manage Categories	98
Quick Category Sets	99
Assigning and Searching Categories and Ratings	99
Quickly Assign Ratings in Thumbnail View	99
Assign and Search Categories and Ratings in the Catalog Pane	100
Assign Categories and Ratings in the Properties Pane	101
Unassigning Categories or Ratings from Files	102
Assigning Color Labels	103
Create a Color Label Set	103
Assign Color Labels	104
Search Files Assigned to a Label	106
Removing Color Labels and Color Label Sets	106
Creating Collections	107
Collections Sets	109
Smart Collections	110
Using the Properties Pane	111
Properties Pane Areas	112
Metadata Tab	112
Organize Tab	113
File Tab	113
Embedding ACDSee Metadata into Files	113
Browsing and Cataloging with Auto Advance	114
Manage Mode	114
Keywords and Categories	115
Keywords	115
Categories	116
View Mode	116

Using the Map Pane	116
Using the Map Pane to Further Your Workflow	118
Creating and Assigning Hierarchical Keywords	119
Creating Keywords	119
Managing Keywords	120
Creating Quick Keywords	121
Importing and Exporting Keywords	122
Copying and Moving Files	123
Copying Images to the Clipboard	124
Pasting Files and Folders	124
Replacing or Overwriting Files	125
Renaming a File or Folder	125
Storing Files in Private Folders	126
Tagging Images or Files	128
Managing Metadata Views	129
Adding ACDSee Metadata to Multiple Files	132
Embedding and Importing Categories and Keywords between ACDSee and IPTC	133
Removing IPTC Keywords from Auto Categories	134
Changing the Date and Time Properties of Images	135
Backing Up Your Files to Another Computer	136
Updating or Deleting a Synchronization	137
Running a Saved Synchronization	138
Searching with ACDSee Home	138
Using the Quick Search Bar	138
Using the Advanced Search Pane	143
Advanced Search Pane Areas	143
Search Presets	143
Source	144
Criteria	144
History	144
Options	144
Choosing Criteria in the Advanced Search Pane	145
Using Selective Browsing	149

Setting Selective Browsing Criteria	149
Tips for Selective Browsing	150
Hiding the Selective Browsing Panel	150
Searching with Auto Categories	150
Identifying Commonly Used Search Categories	151
Refining Your Auto Categories Search	151
Finding Duplicate Files	152
Deleting and Renaming Files	153
Finding Images Quickly	153
Sharing Files with ACDSee Home	154
Taking a Screen Capture	154
Emailing Images	157
Share/Email Using ACDSee 365	158
Viewing and Configuring a Slideshow	158
Sharing Slideshows and Screensavers	162
Creating a Desktop Slideshow	163
Using the ACDSee Showroom Slideshow Controls	164
Creating a PDF	164
Creating a PowerPoint Presentation	165
Creating an HTML Album	166
Uploading Images to Photo Websites	168
Welcome to the Flickr Uploader Plug-in	168
Authorizing	168
Authorizing ACDSee with Flickr	169
Creating a Flickr Account	170
Uploading Images	170
Tagging Images	172
Editing Default Settings	172
Flickr Uploader Settings	173
Adjusting and Adding Information to Your Photos	175
Batch information and resizing	176
Creating a Contact Sheet	177
Creating Archives of Your Files	178

Extracting Archives	179
Printing Images	180
Setting Printer Options	181
Creating Custom Print Layouts	182
Setting Image Size and Positioning	183
Setting Print Adjustments	184
Adding Text to Pages	184
Setting Contact Sheet Printing Options	185
About Batch Editing	186
Using AI Super-Resolution	187
Converting Multiple Images to Another File Format	190
Conversion Status	190
To Convert Images to Another File Format:	190
Rotating or Flipping Multiple Images	191
Setting Rotated and Flipped File Options	193
Resizing Multiple Images	194
Resize Status	194
To Resize Multiple Images:	195
Setting File Options	200
Adjusting Exposure For Multiple Images	200
Adjusting Batch Exposure Options	201
Renaming Multiple Files	203
About the ACDSee Home Database	208
Embedding ACDSee Metadata in Files	208
Embedding ACDSee Categories and Keywords into IPTC Metadata	210
The Embed Pending Icon	210
Viewing Files That Have Data to Embed	211
Retrieving ACDSee Metadata That is Embedded in Files	211
Excluding Folders From the Database	211
Cataloging Files in the Database	212
About the ACDSee Indexer	217
Cataloging and the Database.	217
Creating and Switching Between Multiple Databases	217

Converting an Older Database	218
Importing Database Information	219
Importing File Information from Other Sources	220
Importing Photo Discs	220
Importing Albums	220
Working with Description Files	221
Exporting Database Information	221
Generating File Lists	222
Backing Up Your Database	222
Database Backup Tips and Strategies	224
Backup Schedule	224
Backup Location	224
Backup Size	224
Restoring Database Information From a Backup	224
Maintaining the Database	225
Optimizing the Database	226
Mapping Drives for an Incoming Database	226
Rebuilding Thumbnails and Metadata	227
Quarantined Files	227
Working with Plug-Ins	227
Types of Plug-Ins	228
Managing Plug-Ins	228
Disabling a Plug-In	228
Changing the Plug-In Order	229
Viewing Plug-In Properties and Getting Help	229
ACDSee SeeDrive™	229
Managing Your ACDSee 365 Files with SeeDrive™	230
Uploading	231
Downloading	231
Making Folders Private or Public	232
Sharing and Downloading with ACDSee SeeDrive™	232
Sharing a Folder with ACDSee SeeDrive™	233
Sharing Your Folders by Copying and Pasting its URL Using ACDSee SeeDrive™	235

CHAPTER 4: MEDIA MODE	236
Using Media Mode	236
Header Button Bar	237
My Folders	237
Display Area	237
Toggle Between Grid and Full Screen View	238
Filter By	238
Sort and Group	238
Group By and Properties Panes	238
Navigation Buttons in Media Mode	239
Deleting Images in Media Mode	239
CHAPTER 5: VIEW MODE	240
Previewing Your Images with Auto Lens	240
Light EQ™	241
Using Face Detection and Recognition in View Mode	241
Suggestions	243
Using ACDSee AI Super-Resolution	243
Rotating Images	247
Using the Histogram	247
Viewing Images with Image Advance	247
Displaying Text on Images in View Mode	248
Hiding Image Text	249
Selecting Part of an Image	249
Viewing File Properties in View Mode	250
Viewing and Using Brush Files	250
Playing Video and Audio Files	251
Automatically Playing Audio and Video Files	251
The Media Toolbar	252
Saving Video Frames as Images	252
Adding or Editing Image Audio	253
Recording Audio to an Image	253
Printing Images in View Mode	254

Setting an Image as the Desktop Wallpaper	256
Synchronizing View Mode to a Folder	256
Viewing Offline Images	257
Rebinding Photo Discs	258
Viewing Images in Another Application	258
Showing Originals	258
Committing Changes	259
Changing Image Color Depth	259
Zooming In and Out	260
Setting the Zoom Level	260
Automatically Shrinking or Enlarging Images	261
Using the Navigator to View Select Areas of an Image	262
Panning a Magnified Image	263
Using Pan Lock	263
Magnifying Specific Areas of an Image	263
CHAPTER 6: EDIT MODE	265
Using Edit Mode	265
Editing an Image	265
Reverting to Original Settings	266
Histogram and Image Viewing Controls	266
Using Color Pickers in Edit Mode	268
Using Presets in Edit Mode	268
Using the Undo/Redo Button	269
Restoring Originals	269
Using the Edit Brush	270
Edit Brush	270
Using the Gradient Tool	272
Gradient Tool	272
Using the Radial Gradient Tool	273
Radial Gradient Tool	273
Using Blend Modes and Opacity	275
Opacity	275

Blend Modes	275
Saving Images in Edit Mode	278
Saving Images	278
Using Selections	279
The Selection Tools	280
Using the Selection Tools	280
Combining the Tools	283
Applying Edits or Effects to Selections	283
Reducing Red Eye	284
Removing Flaws	285
Adjusting Skin Tone	287
Adding Drawings to Your Image	288
Adding Text to an Image	292
Adding a Watermark to an Image	295
Adding Borders	296
Adding Your Own Textures or Edges	301
Textures	302
Edges	302
Adding a Vignette	303
Adding a Tilt-Shift Effect	305
Adding a Grain Effect	306
About Special Effect Filters	307
Applying a Bathroom Window Effect	307
Applying a Blinds Effect	308
Applying a Blue Steel Effect	309
Applying a Bob Ross Effect	310
Applying a Bulge Effect	311
Applying a Cartoon Effect	313
Applying a Childhood Effect	314
Applying a Collage Effect	315
Applying a Colored Edges Effect	316
Applying a Contours Effect	317
Applying a Crayon Drawing Effect	318

Applying a Crosshatch Effect	318
Applying a Dauber Effect	319
Applying a Dramatic Effect	320
Applying an Edge Detect Effect	321
Applying an Emboss Effect	322
Applying a Furry Edges Effect	323
Applying a Glowing Edges Effect	325
Applying a Granite Effect	325
Applying a Lomo Effect	326
Applying a Mirror Effect	327
Applying a Negative Effect	328
Applying an Oil Paint Effect	329
Applying an Old Effect	329
Applying an Orton Effect	330
Applying an Outline Effect	331
Applying a Pencil Drawing Effect	332
Applying a Pixel Explosion Effect	333
Applying a Pixelate Effect	334
Applying a Posterize Effect	335
Applying a Purple Haze Effect	336
Applying a Radial Waves Effect	337
Applying a Rain Effect	338
Applying a Ripple Effect	339
Applying a Scattered Tiles Effect	341
Applying a Sepia Effect	342
Applying a Seventies Effect	342
Applying a Sheet Metal Effect	343
Applying a Shift Effect	344
Applying a Slant Effect	345
Applying a Sobel Effect	346
Applying a Solarize Effect	347
Applying a Sombre Effect	348
Applying a Stained Glass Effect	349

Applying a Sunspot Effect	350
Applying a Swirl Effect	350
Applying a Threshold Effect	351
Applying a Topography Effect	352
Applying a Water Effect	353
Applying a Water Drops Effect	354
Applying a Waves Effect	356
Applying a Weave Effect	357
Applying a Wind Effect	358
Creating a Custom Special Effect Filter (Convolution Effect)	359
Rotating an Image	361
Flipping an Image	362
Cropping an Image	362
Resizing the Crop Window	363
Resizing an Image	364
Pixel Resize Options and Resulting Action	365
Adjusting Image Exposure	368
Adjusting Image Levels	369
Adjusting Levels Automatically	371
Adjusting Tone Curves in Edit Mode	372
Adjusting Lighting	373
Using the 1-Step Tab	374
Using the Basic Tab	374
Adjusting White Balance	375
Adjusting Color with Color EQ	376
Creating a Grayscale Image	381
Color Grading with LUTs	383
Using the Histogram	384
Using the Color Dialog Box	384
The Standard Tab	385
The Custom Tab	385
Selecting and Adjusting Colors	385
Sharpening an Image	386


Blurring an Image	387
About Noise and Noise Reduction	390
Removing Noise	390
Adding Noise	393
Adjusting Clarity	394
Using People Mode	395
Named View	396
Unnamed View	396
Person View	396
Folders Pane	397
The Named View	397
Unnamed View	398
Deleting Images and Faces in the Unnamed View:	399
Person View	400
Assigned Faces Pane	400
Renaming Faces	401
The Suggested Faces Pane	401
CHAPTER 7: 365 MODE	403
Working in 365 Mode	405
Creating an ACDSee 365 Account	405
Uploading Images to ACDSee 365	406
Setting Folders to Sync to Web	407
Creating Folders and Setting Privacy	408
Changing the Rating System	409
Downloading Images	409
Using the Transfer Manager	410
CHAPTER 8: DASHBOARD MODE	411
Using Dashboard Mode	411
Cataloging Files	411
Dashboard Mode Tabs	411
CHAPTER 9: PICAVIEW	413

About ACDSee PicaView	413
Using ACDSee Quick View	414
Using Windows Touch Gestures™ with Quick View	415
CHAPTER 10: OPTIONS AND CONFIGURATION	417
Setting the General Options	417
Setting the Auto Advance Options	418
Setting the Mode Configuration Options	418
Setting the Batch Operation Options	419
Setting the Batch AI Super-Resolution Options	419
Setting the Manage Mode Options	422
Setting the ACDSee Home Page Options	423
Setting the Quick Search Options	425
Setting the Face Detection and Recognition Options	426
Setting the File List Pane Options	429
Setting the Thumbnail Info Options	433
Setting the Thumbnail Style Options	435
Setting the Details View Options	436
Setting the Preview Pane Options	437
Setting the Folders Pane Options	438
Setting the Catalog Pane Options	439
Setting the Calendar Pane Options	440
Setting the CD/DVD Management Options	441
Setting the Properties Pane Options	442
Setting the File Management Options	442
Setting the Database Options	444
Setting the Media Options	446
Setting the Embed ACDSee Metadata Options	446
Setting the View Mode Options	448
Setting the People Mode Options	450
Setting the Display Options	452
Setting the Edit Mode Options	453
Setting the ACDSee 365 Options	454

Setting the ACDSee Showroom Options	455
Setting the ACDSee Quick View Options	457
Setting the Media Options	458
Setting the ACDSee Indexer Options	459
Setting the ACDSee PicaView Options	459
Setting the ACDSee Mobile Sync Options	460
Import Options	461
Auto-hiding Panes and Panels	462
Using the Task Pane	462
Customizing Toolbars	463
Displaying and Hiding Toolbars	463
Customizing Toolbar Contents	463
Resetting Toolbars	464
Customizing Toolbar and Pane Locations	465
Hiding Panes	465
Moving Panes and Toolbars in View and Edit Mode	465
Docking Panes and Toolbars in View and Edit Mode	466
Creating a Custom Menu	466
Configuring External Editors	467
Customizing Keyboard Shortcuts	469
Changing the Display Theme	470
Setting JPEG Options	470
CHAPTER 11: SHORTCUTS	472
Manage Mode Keyboard Shortcuts	472
Manage Mode Mouse Shortcuts	484
Calendar Pane Shortcuts	484
Media Mode Keyboard Shortcuts	485
View Mode Keyboard Shortcuts	486
View Mode Mouse Shortcuts	500
Edit Mode Keyboard Shortcuts	501
Edit Mode Mouse Shortcuts	509
365 Mode Keyboard Shortcuts	510

365 Mode Mouse Shortcuts	512
ACDSee PicaView Keyboard Shortcuts	513
<hr/>	
CHAPTER 12: FILE FORMATS	514
Supported File Formats in ACDSee Home	514
About RAW Files	519
Associating Files	520
<hr/>	
GLOSSARY	521

Chapter 1: Getting Started



Welcome to ACDSee Photo Studio Home 2026

Welcome to ACDSee, the industry-leading digital photo and document management software.

The Benefits of ACDSee

- **Total workflow control.** Build your photography workflow around ACDSee and notice the difference. With flexible cataloging capabilities, unrivaled viewing speed, and a powerful photo editor, ACDSee is the choice of busy professional and advanced amateur photographers worldwide. Add vastly improved RAW processing, a full set of metadata tools, and unparalleled viewing speed, and you have a fully integrated photography editing and management solution.
- **Patented editing features including Light EQ™.** The Patented Light EQ™ technology single-exposure HDR algorithms powering ACDSee's Light EQ™ tool accurately and intelligently stretch the dynamic lighting range of your photos, making them incredibly realistic or atmospheric.
- **Wide variety of editing and processing tools.** Create, edit, and touch-up your digital images. Use tools such as red eye reduction, crop, sharpen, blur, and photo repair to enhance or correct your images. Image editing tools, such as exposure adjustment, convert, resize, rename, and rotate, can be performed on multiple files at the same time.
- **Completely customizable UI.** The user interface is completely customizable, and provides quick access to tools and features. You can customize the screen layout, the order of images, toolbar display, and many other options to suit your preferences.
- **Impressive organizational capabilities.** With ACDSee you can import your photos from your camera to your computer, categorize and rate your files, and manage photo collections of any size—from a few hundred to a few hundred thousand. Choose to view thumbnail previews of any size, or use a detailed list of file properties to sort your files. Can't find a particular photo? No problem. ACDSee includes a variety of powerful searching tools and a Compare Images feature to eliminate duplicates.
- **Context-sensitive help.** ACDSee contains extensive context-sensitive help materials to assist you as you move through the application. Press **F1** when using any feature to open the relevant online help page.

Using the User Guide

This user guide is here to help you get the most out of your ACDSee software. It is categorized by mode and by function. Throughout the guide, you will find icons that help you best use ACDSee.



Notes are things to consider when performing an action.



Tips are ways to optimize your work.



Warnings are things to take into account when making an action.

Thank you for choosing ACDSee, the complete photography management solution for professional photographers.

Automatically Imported Settings

If you have installed a previous version of ACDSee Home, some settings will automatically be imported into your new version when launched for the first time.

ACDSee Photo Studio Home 2026 will import the following settings from your most recently installed version:

- **Import Options:** Automatically imports your saved Options settings. For more information see [Import Options](#).
- **Metadata Views:** Use Metadata Views to save frequently used metadata fields and keep the most relevant information visible. For more information see [Metadata Views](#).
- **Label Presets:** Create label sets so you can quickly select and assign specified labels. For more information see [Assigning Color Labels](#).
- **Quick Category Sets:** Use Quick Categories to keep order by creating categories of different events or areas of interest. For more information see [Creating Categories](#).
- **Quick Keyword Sets:** Use Quick Keywords to keep organized and to streamline your workflow by creating a group of related keywords that hold an association for you. For more information see [Creating and Assigning Hierarchical Keywords](#).
- **Batch Convert File Format Presets:** Save frequently used file format settings as a preset, allowing you to convert multiple images to specific file formats quickly. For more information, see [Converting Multiple Images to Another File Format](#).
- **Batch Rename Presets:** Save frequently used renaming settings as a preset. Use Batch Rename presets to rename multiple files with specific formatting applied. For more information, see [Renaming Multiple Files](#).
- **Batch Resize Presets:** Save frequently used resizing parameters to resize multiple images at once with specific formatting applied. For more information, see [Resizing Multiple Images](#).
- **Advanced Search Pane Search Presets:** Save search results and bring them back with a single click. For more information, see [Using the Advanced Search Pane](#).
- **Advanced Search Pane Search History:** Displays search history when searching by Filename, Text, or Filename > Pattern Match. For more information, see [Choosing Criteria in the Advanced Search Pane](#).

- **Customized Keyboard Shortcuts:** Customizing keyboard shortcuts allows you to modify default key combinations to better suit your workflow, improving efficiency and ease of use. For more information see [Customizing Keyboard Shortcuts](#).
- **External Editor Settings:** Open images in external editing applications from within ACDSee, configure ACDSee Home to work with a variety of image editors, and specify which image editor ACDSee Home uses by default. For more information see [Configuring External Editors](#).



Some settings may not import from all older versions of ACDSee Home. (e.g. Options are only imported from 2022 or newer.)



The import tool will only import from an older version and within the same product model. (e.g. ACDSee Photo Studio Home 2026 can only import options from an older version of ACDSee Photo Studio Home.)



The import tool will always import from the most recent previous version that can be found. (e.g. If ACDSee Photo Studio Home 2022 and ACDSee Photo Studio Home 2023 are both installed, only the settings from ACDSee Photo Studio Home 2023 will be imported.)

About the ACDSee User Interface

The ACDSee Home user interface provides easy access to the various tools and features you can use to browse, view, edit, and manage your photos and media files. ACDSee Home consists of seven modes: Manage, Media, View, Edit, People, 365, and Dashboard.

Manage Mode



Manage mode is the main browsing and managing component of the user interface, and is what you see when you start ACDSee Home using the shortcut icon on your desktop. In **Manage** mode, you can find, move, preview, and sort your files, and access organization and sharing tools.

Manage mode consists of 15 panes, most of which can be closed when not in use. The [File List pane](#) is always visible, and displays the contents of the current folder, the results of your latest search, or the files in your database that match your filtering criteria. A status bar at the bottom of the **Manage** mode window displays information about the currently selected file, folder, or category. The current state of the **Activity Manager** can also be viewed from the status bar by hovering over the icon. For more information, see the [ACDSee Activity Manager](#).

You can open and close panes, move them to different areas of your screen, and stack them on other panes or dock them to the edge of the window. Most panes also have additional options you can set to further customize their behavior and appearance.

Manage mode also features a toolbar and a set of drop-down menus. The toolbar provides buttons for your home folder, and for navigating forwards and backwards through your folders. The drop-down menus provide quick access to the most common tasks.

Media Mode

2

Media mode is ACDSee's database-driven powerhouse for viewing and accessing the folders you have either browsed in **Manage** mode or cataloged into the ACDSee database. This streamlined, uncluttered view of the media assets managed by ACDSee offers sorting, grouping, and filtering in any combination.

View Mode

3

In **View** mode you can play media files and display images and documents in full resolution, one at a time. You can also open panes to view image properties, display areas of an image at varying magnifications, or examine detailed color information.

You can open **View** mode by selecting an image or document and clicking on the **View** mode tab, and you can use the Filmstrip in **View** mode to flip quickly between all of the files in a folder. **View** mode contains a toolbar with shortcuts to commonly-used commands, and a status bar at the bottom of the window, which displays information about the current image or media file.

Edit Mode

4

Edit mode works on the image data already rendered to RGB. Edits are independently applied to the converted RGB data in the order that you do them. This chain editing gives you full control over the pixels, allowing creative freedom to apply precise adjustments. This makes operations such as selections and blend modes possible.

People Mode

5

People mode is born of a union between ACDSee's industry-leading Face Detection & Recognition feature and a keen application of machine learning. Photographers from all walks of life will enjoy the dedicated space for distinguishing by client, family member, or person of interest, allowing for the management of people by merging, renaming, or deleting faces, or taking labeling suggestions from the AI assistant for grouping similar unnamed people.

365 Mode

6

365 mode provides an easy way to upload images to seedrive.acdsee.com to share with your contacts or the public. In **365** Mode, you can select the images on your computer and then drag and drop them directly into seedrive.acdsee.com.

Dashboard Mode


7

Dashboard mode allows you to quickly access and browse file, camera, and database statistics based on your ACDSee database and EXIF information. As **Dashboard** mode relies on information derived from your database, it is important to catalog in order to get the most out of it.

Switching Modes in ACDSee

In ACDSee Home, you can quickly switch between the seven modes—Manage, Media, View, Edit, People, 365, and Dashboard.

The mode buttons are located at the top right of the ACDSee Home window:



To Switch from One Mode to Another:

Click one of the following mode buttons:

- **Manage**: import, browse, organize, compare, find, and publish your photos.
- **Media**: view your entire image collection by date.
- **View**: display and examine photos at any magnification.
- **Edit**: fix and enhance photos using the pixel-based Edit tools.
- **People**: view faces identified through ACDSee's Facial Recognition.
- **365**: upload images to seedrive.acdsee.com to share with your contacts or the public.
- **Dashboard**: quickly access and browse file, camera, and database statistics.

Using Manage Mode

In Manage mode, you can browse, sort, catalog, manipulate, and share your files and images. You can combine different tools and panes to perform sophisticated searching and filtering operations, and view thumbnail previews of images and media files.

You can also switch very quickly to the other modes by clicking the mode buttons in the top right corner.

The panes in Manage mode are fully customizable, and can be moved, resized, hidden, docked, or closed. You can also stack the panes together for easy reference and accessibility, and to maximize your screen space.

If the pane you want to view is not visible, click **Panes** from the top left main toolbar and select a pane.

About the Manage Mode Panes

Manage mode consists of the following panes:

File List	This pane displays the contents of the currently selected folder, the results of your latest search, or the files and folders that match your selective browsing criteria. The File List pane is always visible, and cannot be hidden or closed. You can customize the File List pane by changing the way the files are displayed, or the size of the thumbnails.
Folders	This pane displays the directory structure of your computer, much like the directory tree in Windows Explorer. You can use the Folders pane to browse through the folders and display their contents in the File List pane. You can also display the contents of multiple folders in the File List by clicking the Easy-Select indicator opposite each folder, on the left side of the pane.
Calendar	This pane displays a calendar that you can use to organize and browse your files according to their associated dates.
Shortcuts	This pane stores shortcuts to your favorite images, files, folders or even applications. Dragging an image, file, or folder into the Shortcuts pane creates a shortcut to the original without affecting it in any way.
Advanced Search	<p>This pane provides access to a powerful advanced search utility. You can specify the type of search you want to perform, and enter your search criteria into the fields provided in the Advanced Search pane.</p> <p>You can also save a search and give it a name. Search presets are listed on the Advanced Search pane and the Catalog pane. On the Advanced Search pane, can select Search Presets from the drop-down list to run again. On the Catalog pane, Search Presets are listed below Auto Categories, where you can run them again by clicking once on the Search Preset name.</p>
Preview	This pane displays a thumbnail preview of any image or media file currently selected in the File List pane. You can adjust the size of the thumbnail by resizing the Preview pane, and also specify whether you want the Preview pane to play media files or just display the first frame.
Selective Browsing	This panel combines input from the Folders, Catalog, and Calendar panes to limit the list of files in the File List pane to those that match a specific set of criteria. You can include or exclude files by adjusting the different criteria in the Selective Browsing pane. You can access the Selective Browsing panel from the View menu.
Catalog	This pane lists the categories, auto categories, people, ratings, color labels, keywords, and search presets to help you sort and manage your files. You can also use the Special Items area in the Catalog pane to quickly view all the images on your computer or see any files not get categorized in the current folder.
Task	This pane displays menus of commonly-used buttons and commands from the menus and toolbars. The menus change dynamically based on your current location and selections in ACDSee.
Properties	This pane displays file properties and metadata for any file or folder you select in the

	File List pane. You can use the Properties pane to view and edit metadata for your files, and the EXIF metadata included in digital photos.
Map	This pane displays marked locations on a map for any file you select in the File List pane. You can use the Map to view and mark the geographic location of your files.
Image Basket	While browsing through your files and folders, you can place images in an Image Basket to hold them temporarily . You can then edit, print, or share those images without moving them all into a single folder.
Activity Manager	<p>The Activity Manager has three sections: Queued Activities, Idle Activities, and Activity History.</p> <p>Queued Activities: Importing images into ACDSee will display their progress in the Queued Activities section. You can pause or cancel them at any time.</p> <p>Idle Activities: Running Face Detection will display a counter indicating how many files remain to be scanned.</p> <p>History: View history of Queued Activities completed since you last launched ACDSee.</p>

Manage Mode Drop-Down Menus

The drop-down menus in Manage mode give you quick access to often-used tasks. The drop-down menus include the following:

- **Import:** where you can import photos from cameras and other devices.
- **Batch:** where you can run all the batch editing processes.
- **Create:** where you can create slide-show files, PDFs, PowerPoint presentations, online albums, or archives.
- **Slideshow:** where you can configure and run a slideshow.
- **Send:** where you can upload to photo sites, an FTP, or share photos by email.
- **Editors:** where you can list external editors for easy access.

Working with Manage Mode Panes

You can open and close panes in Manage mode to suit your preferences, and move, float, or stack any of the panes to customize the layout of the Manage mode window.

To Open or Close Panes in Manage Mode:

Click **Panes** and select the pane you want to open or close.

Moving Panes

You can move a pane from a docked or floating position to a new location. You can move one pane at a time, or several stacked panes.

To Move a Pane:

1. Drag the pane's title bar and hold your cursor over any of the arrows of the Docking Compass.
2. When the shaded marquee displays the position of the pane you want, release the mouse button.
3. To return a pane to its previous location, double-click its title bar.

To Move a Docked or Floating Pane:

Do one of the following:

- Drag the pane's tab to a new location. Only one pane moves.
- Drag the pane's title bar to a new location. Any panes stacked beneath it also move.



If you use dual monitors, you can move the panes to your second monitor to free up space on your main monitor.

Docking Panes

When you select a pane in the Manage mode, the Docking Compass activates to help you place the pane precisely. The Docking Compass consists of an outer and inner ring of arrows. When you hold your cursor over any of the arrows, a shaded marquee displays the potential position of the pane.

To Dock a Pane in Manage Mode Window:

1. Drag the pane's title bar or tab to activate the Docking Compass.
2. To dock a pane around the outer edge of the window, hold your cursor over any of the outer arrows of the Docking Compass, and then release the mouse button.
3. To dock a pane around the outer edge of the File List pane, or any another pane, hold your cursor over the inner arrows of the Docking compass, and then release the mouse button.

Stacking Panes

You can stack panes and reorder their tabs to suit your needs.

To Stack Panes:

1. Do one of the following:
 - Drag one pane's title bar onto the title bar of another pane until the shaded marquee appears, and then release the mouse button.
 - Drag one pane inside another, hold your cursor over the center of the Docking Compass, and then release the mouse button.
2. To reorder the panes, drag a tab to the left or right in the tab order.
3. To separate a tabbed pane, drag the pane's tab to another location on the screen.

Resizing Panes

You can resize all the panes in Manage mode, whether they are docked or floating.

To Resize a Docked Pane:

1. Hold your cursor over the edge of the pane until the cursor changes to arrows and lines.
2. Drag the edge of the pane to the size you want.

To Resize a Floating Pane:

Hold your cursor over the edge or corner of the pane and then drag the pane to the size you want.

Resetting the Layout

All panes can be restored to their default positions at any time in **Manage**, **Media**, **Edit**, and **People** modes.

To Reset the Layout:


Click **View | Reset Layout**.

Using Media Mode

Media mode offers a streamlined, database-driven approach to Digital Asset Management. Only the folders browsed in **Manage** mode and that have been cataloged into the ACDSee database will be displayed in **Media** mode, offering a clutter-free view of photographs and videos managed by ACDSee.

The **Media** mode interface is divided into four separate functional areas:

1. [Header Button Bar](#)
2. [My Folders](#)
3. [Display Area](#)
4. [Group By and Properties](#)



Header Button Bar

Located directly below the main menu, the Header Button Bar contains three buttons described below:


- Refresh
- Catalog
- Show Orphan Files

Header Button Bar Options

Refresh	Refreshes the My Folder pane's folder tree and the Display Area pane.
Catalog	For more about cataloging files, please see Cataloging Files in the Database .
Show Orphan Files	Displays missing files flagged as orphans. Orphans will be displayed in sepia.

My Folders

Located along the left side of the screen, the **My Folders** pane is a simple folder tree populated with all folders browsed while in **Manage** mode. To add additional folders to the **My Folders** pane without leaving **Media** mode, use the [Catalog Files tool](#).

The **My Folders** pane is hidden by default. To display the **My Folders** pane, click the Hide/Show icon  in the lower left of the Display Area.

Clicking a folder containing media in the **My Folder** pane will filter the Display Area's contents to display the selected folder's media.

Display Area

The **Display Area** pane occupies the large central portion of the screen and is used primarily to display images and videos that can be filtered, sorted, or grouped.

Double-click any image or video to display them in full screen. Videos displayed in full screen can be played without leaving **Media** mode. Double click the full screen image or video to return to the grid view.

Right-click individual media assets to produce a context-sensitive help menu containing the following options:

- **View:** Opens media asset in **View** mode.
- **Edit:** Opens media asset in **Edit** mode.
- **Rotate Left:** Press **Ctrl + L** to rotate left.
- **Rotate Right:** Press **Ctrl + R** to rotate right.
- **Show in File Explorer:** Opens to the media asset file's location in File Explorer.

Toggle Between Grid and Full Screen View

You can swap between **Grid** and **Full Screen** view by selecting the toggle button in the top left of the display, found directly to the left of the **Filter** option.

Filter By

When enabled, the tools in the **Filter By** toolbar are very powerful for tailoring the results displayed in the **Display Area** pane by filtering the results based on specific metadata.

To filter media assets in the **Display Area** pane, choose from a combination of any of the following:

- Enable the Tagged checkbox to display only those images with a tag.
- Make a selection from the ratings to display media with a specific rating. The button to the left of the ratings lets you choose whether the results will include media with a Rating less than or equal, greater than or equal, or matching the chosen rating.
- Make a selection from the color labels to display media tagged with a specific label.



Changes made to the **Filter By** tools will affect the results displayed in the **Group By** pane.


Sort and Group

Located directly above the media asset and to the right-side of the **Display Area** pane, the **Sort** and **Group** drop-downs are used to alter how the contents of the **Display Area** pane are presented. Unlike the **Filter By** field which refines the number of media assets displayed, the **Sort** and **Group** drop-downs do not change the number of media assets displayed. Both the **Sort** and **Group** drop-down results can be sorted forwards or backwards.



Selections made in the **Group** field will affect the results displayed in the **Group By** pane.

Group By and Properties Panes

Located along the right side of the screen, the **Group By** pane lists groups of media assets based on the selection made in the **Filter By** drop-down and the **Group** drop-down. The **Properties** pane displays key details such as IPTC, EXIF, and important ACDSee metadata. To display the **Group By** and **Properties** pane, click the Hide/Show icon  in the lower right of the Display Area.

The **Group By** pane results can be grouped forward and backwards.

The blue bar within each group tab is representative of the number of media assets in the group.

Clicking a tab in the **Group By** pane changes the display in the **Display Area** pane to reflect the group selected.

Navigation Buttons in Media Mode

When viewing an image in full screen, you can navigate between images by hovering over to the left or right side of the window and clicking on the navigational arrow that appears.

Deleting Images in Media Mode

There are three ways of deleting images in Media Mode:

- Right click on an image and select delete from the context menu
- Click on the Edit dropdown at the top of the screen and select Delete
- Click once on the image and press the Delete key

Using View Mode

You can use View mode to display your images, documents, and media files using their actual dimensions or at a [variety of magnifications](#). You can also display a group of images in sequential

order.

View mode contains four main areas:

- **View area:** This is the main viewing area, which displays the current image, document, or media file. You can customize the view, and zoom in or out on your images and media files.
- **Bottom toolbar:** Located below the main viewing area, the Bottom toolbar provides shortcut buttons to commonly-used tools and commands, such as the zoom and scroll tools. You can customize the toolbar to use large or small icons, or you can choose to not display the toolbar.
- **Filmstrip:** This is an area below the main viewing area, which displays thumbnails of the images in the current folder or in the group of images you selected in Manage mode. It provides a scroll bar along the bottom, so that you can scroll through your images, and buttons for moving to the next or previous image.
- **Status bar:** Located at the bottom of the window, the Status bar displays information and properties for the current image or media file. It also displays icons for rating, color labels, and tagging that you can click to edit.

View mode can also display the Properties pane to show [EXIF, IPTC and ACDSee Metadata information](#) about the image or file. View mode also has the [Navigator](#), [Magnifying Glass](#), and [Histogram](#) panes, each of which show detailed image information.

To Open an Image, Document, or Media File in View Mode:

In **Manage** mode, in the File List pane, do one of the following:

- Select a file and press **Enter**.
- Select a file and click the **View** mode button.
- Double-click a file.
- Right-click an image, document, or media file, and then select **View**.

To Open a Group of Images in View Mode:

1. In Manage mode, in the File List pane, select a group of images.
2. Press **Enter**.
3. To navigate through the images, do the following:
 - To view the next image in the sequence, click **Next**.
 - To view the previous image in the sequence, click **Previous**.

Viewing Images in Full Screen Mode

You can use the entire screen of your monitor to display images. In full screen mode, the window borders, menu bar, status bar, and toolbars are hidden, and only the image is visible. If you want to always view your images in full screen mode, you can set this option as the default for View mode.

To View Images in Full Screen Mode:

1. Open an image or a group of images in View mode.
2. Click **View | Full Screen**.
3. Right-click the image to access the View mode tools and options via a context menu.

To Exit Full Screen Mode:

Do one of the following:

- Press the **F** key.
- Right-click the image and select **View | Full Screen**.



Use the keyboard shortcut **F** in View mode to toggle in and out of a full screen view.

Using the View Mode Panes

To Open the View Mode Panes:

1. Open an image in View mode.
2. Do one of the following:
 - Click **Panes | Histogram** to display the histogram for the image.
 - Click **Panes | Magnifying glass** to display a pane which shows the area of the image under your cursor at a higher magnification.
 - Click **Panes | Navigator** to display a thumbnail overview of a magnified image.
 - Click **Panes | Page View** to open the Page View panel for multi-page images.
 - Click **Panes | Properties** to display the IPTC, EXIF and ACDSee Metadata for the image.
 - Click **Panes | Face Detection** to display and name the [detected faces](#).











Using the Bottom Toolbar












Use the Bottom toolbar to access commonly-used tools.




These tools are only available when viewing image files.

Bottom Toolbar

	Add to Image Basket	Adds the image to the active Image Basket.
	Rotate left	Rotates the image to the left.
	Rotate right	Rotates the image to the right.
	Face Tool	Uses ACDSee Face Detection to detect people in images. Identified faces can be assigned names.
	Scroll	Pans or scrolls the image when the image is zoomed to a larger size than the View mode area.
	Select	Selects a rectangular area of the image.
	Zoom	Zooms in or out on the image. Click to zoom in or right-click to zoom out.
	Full Screen	Displays the image on a full screen. Press F to view full screen.
	External Editors	Opens the file in an external editor of your choosing.
	Actions Browser Pane	Opens the Actions Browser pane that allows for the recording of all Edit mode adjustments and the application of edits to other images by "playing" the edits back. Use this method to batch edit multiple photos with any adjustment available in Edit mode. In addition, after applying a recording with adjustment layers, open the image in Edit mode and continue tweaking and adjusting the adjustment layers in the Layered Editor , allowing for non-destructive image editing.

	Auto Light EQ	Automatically previews a Light EQ™ adjustment of the image.
	Auto Lens	Previews a number of filters for the image without applying the filters to the file.
	Snapshots	Saves adjustments made to an image. The snapshot save point in the editing process can be returned to at any time. Unlike presets, snapshots save directly to the image, which allows switching between snapshot saves.
	Auto Advance	Turns on Auto Advance to quickly move through images while adding tags, ratings, labels, categories, or keywords.
	Show Face Outlines	Places a box around faces contained in an image.
	Toolbar Options	Produces a menu containing the Add or Remove Buttons menu item.
	Hide Bottom Panels	Hides the bottom filmstrip from view.
	Navigator	Displays the Quick Navigator pane so you can see a thumbnail overview of a magnified image. (Only visible for images that are zoomed in to a size larger than will fit on the screen.)
	Zoom slider	Controls the size of the image in the View mode area. Drag the slider to adjust the size.
	Zoom drop-down list	Displays a list of zoom sizes to select.
	Zoom Lock	Displays all images at the zoom option of the current image. If the zoom level is adjusted, the new zoom level is applied to all

		images that you view.
1:1	Actual Size	Returns the image to its actual size.
	Fit Image	Reduces the image to fit within the View mode area.

Using Windows Touch Gestures™ with View Mode

If you have a Windows Touch Gestures™-enabled device, you can use it with View mode for quick, easy viewing of photos.

To Use Windows Touch Gestures™ with View Mode:

Open an image in View mode.

- Swipe on the image to scroll through images one at a time. You can also use this method on the Filmstrip at the bottom of View mode.
- Hold and swipe slowly in one direction to go through all of the images in the folder.
- Hold down on an image, and then let go to achieve the same results as right-clicking with a mouse.
- Double-tap the image to return to Manage mode in ACDSee.
- Move two fingers apart to zoom in, and toward each other to zoom out.
- After zooming in further than 100%, you can pan the image with your finger.

Switching to Manage Mode

You can return to Manage mode at any time.

To Return to Manage Mode from View Mode:

Do one of the following:

- Double-click the image.
- Click the **Manage** mode button.

Using Edit Mode

Edit mode is where you can apply changes to your images. You can edit the overall look of your images by changing the lighting and color, or you can crop, flip, resize, or rotate your images. You can use selections to fix specific parts of your images. And you can also add final touches to your images, such as red eye removal, borders, and special effects.

In Edit mode, you can:

- [Use the Selection tools](#) or [Edit Brush](#) to select and apply edits to a specific part of the image.
- [Remove flaws](#) or [red eye](#).
- Add [text](#), [watermarks](#), [borders](#), a [vignette](#), a [tilt-shift](#), [special effects](#), or [drawings](#).
- [Crop](#), [flip](#), [resize](#), or [rotate](#) your images.
- Adjust lighting using the [exposure](#), [levels](#), [auto levels](#), [tone curves](#), and [lighting](#) filters.
- Adjust color using the [White Balance](#), [Color EQ](#), [Color LUTs](#), [Split Tone](#) or [Convert to Black & White](#) filters.
- Add details to your image using [Sharpen](#), [Clarity](#), [Remove Noise](#), [Add Noise](#) or [Blur](#) filters.

Using 365 Mode

You can use 365 mode to upload your images to seedrive.acdsee.com. seedrive.acdsee.com is an image sharing and storage service available to ACDSee Home users. With 365 mode and seedrive.acdsee.com, you can upload and browse through your online images without having to launch an Internet browser.

365 mode has two parts: seedrive.acdsee.com and Transfer. In seedrive.acdsee.com, you can browse through your images in your seedrive.acdsee.com account and modify your account settings. In Transfer, the screen splits into two. The bottom part of the screen displays the images in your computer, and the top part of the screen displays your seedrive.acdsee.com. You can simply click images in your computer displayed in the bottom part of the screen, and drag them into the top part of the screen to upload the images to your seedrive.acdsee.com account.



You cannot take an image from 365 mode and open it in Edit mode. To edit an image, select an image in Manage or View mode and open it in Edit mode.

Uploading Images

To Upload Photos to Your seedrive.acdsee.com Account:

1. In 365 mode, click **Sign In**.
2. Log in to your account.
3. Click **Transfer**.

Your screen splits in two, with the bottom part of the screen displaying images in your computer.

4. Select an image to upload. To select multiple photos, press **Shift** or **Ctrl** on your keyboard.

5. Click and drag the image into the top part of the screen to upload it to your seedrive.acdsee.com account.



There is no upload size limit when uploading your images to your seedrive.acdsee.com account.

Using Dashboard Mode

Dashboard mode provides an easy way to monitor your file, camera, and database statistics in one place. Camera data is gathered from your image metadata, and file information is analyzed from your ACDSee database. To see the most accurate information, make sure your files are [cataloged](#).

Cataloging Files

To catalog your files, do one of the following:

- Go to **Tools | Database | Catalog**.
- Browse your folders in Manage mode.

Dashboard Mode Tabs

Dashboard mode is organized into four tabs, each giving you a different view of your data:

- **Overview tab:** Provides a high-level summary of your photo activity and database status.
 - At the top, a graph shows your photo counts by month or year. Use the drop-down menu to switch between Yearly and Monthly views, and the Prev and Next buttons to move through time.
 - Below the graph, you will find:
 - **Database Summary:** Total Database Size, Total # of Files and Folders, and Last Backup Date.
 - **Cameras Summary:** Camera Most Used, Total # of Cameras, and Favorite ISO Setting.
 - **File Summary:** # of Image and Video Files, Favorite File Format, and Favorite Image Resolution.



This tab is useful for a quick health check of your photo collection and database.

- **Database tab:** Displays detailed information about your database so you can track its size, structure, and backup status.

- **Total Database Size:** Includes the database file path.
- **File Information:** A breakdown of Image Files, Video Files, and Other Files.
- **Folder Information:** Counts for Folders Browsed, Remote Folders Browsed, and Removable Folders Browsed.
- **Orphan Assets:** Shows the number of orphaned Files and Folders.
- **ACDSee Database Backup:** Displays your last backup date, so you can confirm your data is safe.
- **Thumbnail Information:** Includes the size of the Thumbnail Cache and how many images have thumbnails.



Use this tab to monitor database performance and ensure your backups and thumbnails are up to date.

- **Cameras tab:** Shows how you use your cameras and lenses.
 - The **Cameras Summary** panel (on the left) highlights your Most Used Camera, Lens, Focal Length, Aperture, Shutter Speed, and ISO.
 - The main display includes:
 - Circle graphs showing the number of photos by Camera, Lens, and Focal Length, with percentage breakdowns.
 - Bar graphs showing the number of photos by Aperture, Shutter Speed, and ISO.
 - You can toggle these graphs on or off from **View | Graphs**.



This tab helps you understand your shooting habits, such as which lenses or settings you use most often.

- **Files tab:** Displays information about your image and video files.
 - The **File Summary** section (upper left) shows the total number of files, your favorite file format, and your most common image resolution.
 - Two circle graphs provide a breakdown of File Formats and Bit Depths, with percentages displayed in a legend.
 - A bar graph displays the Top 20 Image Resolutions in your collection.



This tab gives you insight into the types of files you work with most frequently.

Chapter 2: Getting Help

Using the Quick Start Guide

The Quick Start Guide is designed to give you a brief orientation of the most important features in ACDSee. The first two intro pages allow you to configure some settings to facilitate your future workflow. After the first two intro pages, the Quick Start Guide contains a set of links on the left side that you can click to get a tour of the main features in ACDSee. You can also use the Next button.

To Close the Quick Start:

Uncheck the **Always show at start-up** option in the bottom left corner of the dialog box and click **Close**.

To Re-Open the Quick Start Guide:

On the Menu bar, click **Help | Quick Start Guide**.

To Use the Quick Start Guide:

Click the links on the left side of the Quick Start Guide or the **Next** button for a high-level tour.

To Set Preferences:

1. On the first page, click the **Browse** button to select the folder ACDSee will open to in the future.
2. On the second page, click the **Select** button to choose which folders you would like the ACDSee database to keep track of.
3. Also on the second page, you can choose an interval from the drop-down menu on the right side to specify how often ACDSee should remind you to backup your database.

Finding Other Resources and Support

Using the Help Menu

The Help menu on the ACDSee menu bar contains links to open plug-in help files and options that link you to the ACDSee website where you can find updates, newsletters, and system requirements. Other links take you to the registration page, or the forum homepage where you can join the community and participate in the ACDSee forums. The Help menu is also where you can convert a trial version of ACDSee to a full version by entering a license code.

Clicking **Help** displays a menu of links to online and offline help materials including our online help file, that you can open any time you are online by clicking **Help Contents**. From the help menu, you can also access in-app resources such as in-build plug-in help, the Quick Start Guide, and **About**, which gives you information about your software, your license, and your version.

Press **F1** to open related help file pages from within the application.

You will also find a link to [Customer Support](#).

Online Help and ACDSee Connect

As well as the links to online help found on the in-app help menu, we also have comprehensive tutorials on our YouTube channel, and have an online forum where you can discuss the software with other ACDSee users. When you visit [ACDSee Connect](#), you will find tutorial videos and online lessons.

Chapter 3: Manage Mode

Manage mode is the main browsing and managing component of the user interface, and is what you see when you start ACDSee Home using the shortcut icon on your desktop.

In Manage mode, you can:

- The [ACDSee Home Page](#) provides quick and easy access to searches and key functions.
- [Import your photos](#) from a device, CD or DVD, or disk.
- [Browse files and folders](#).
- [Catalog files](#) by tagging them, adding categories, color labels, ratings, keywords and other metadata.
- [Search for files](#) and create search presets.
- [Publish and share files](#), including emailing files, creating slideshows, and uploading images to your favorite photo website.
- [Print images](#).
- Manage your Queued and Idle Activities with [ACDSee Activity Manager](#).
- [Edit batches](#) of files.
- Manage and maintain your [ACDSee Home database](#).
- Automatically [advance](#) to the next image in the folder when you apply metadata.
- [Detect](#) faces in images.

ACDSee Home Page


The **ACDSee Home Page** appears by default when you launch the program. This behavior can be changed in the [Startup Options](#). The Home Page provides quick and easy access to searches and key functions, making it simple to start working on your projects.



Browsing folders or running searches will open in a new tab. For more information, see [Browsing with ACDSee Tabs](#).

There are three areas to the **ACDSee Home Page**:

1. [Quick Search Bar](#)
2. [Search Buttons](#)
3. [Action Buttons](#)



Quick Search Bar

Use the Quick Search Bar at the top of the Home Page to quickly locate files or folders. You can refine or expand your search using the Quick Search options and view the results in the File List pane.

There are three ways to control the Quick Search Bar:


- **Clearing Text:** Quick Search allows you to type in your search criteria. Clicking **X** will remove the text currently in the Quick Search bar.
- **Starting Search:** Click the magnifying glass or press the **Enter** key.
- **Adjusting Search Parameters:** Use the options menu to set the search parameters.

For more information, see [Using the Quick Search Bar](#).

Search Buttons

The Home Page includes five predefined searches for quick access:

- **Recently Modified:** Displays files modified within the last week by default. This search uses the Windows *Recently Modified* field.
- **Recently Added:** Displays files added within the last week by default. This search uses *Date Taken* by default, or can be changed to *Date Added to Database* in the Home Page options.

 The timeframe for **Recently Modified** and **Recently Added** files can be adjusted using the option menu in the upper-right corner of the button, or in the [ACDSee Home Page options](#).

- **Tagged:** Displays files that have been tagged. For more information, see [Tagging Images](#).
- **Embed Pending:** Displays files with ACDSee Metadata applied that has not yet been embedded. For more information, see [Embedding ACDSee Metadata in Files](#).
- **Unnamed Faces:** Displays files that contain detected faces without assigned names. For more information, see [Detecting Faces in Manage Mode](#).

Action Buttons

Below the search buttons, the Home Page includes five action buttons:

- **Customize Shortcut:** Opens the Customize Shortcuts dialog, allowing you to customize the keyboard shortcuts throughout the program. For more information, see [Customizing Keyboard Shortcuts](#).
- **Import:** Opens the **Import Window** for adding images. Use the Options menu to select a source such as device, scanner, disk, or CD/DVD to import from. For more information, see [Importing Files with ACDSee](#).

 Import will only run based on which **Import Source** you've selected.

- **Database:** Opens the Back Up Database dialog by default, or can be changed to open either the ACDSee Database Optimization Wizard, or the Database Maintenance window by changing the setting in the Options menu. For more information, see [Backing Up Your Database](#), [Optimizing the Database](#) and [Maintaining the Database](#).
- **Find Duplicates:** Opens the Duplicate Finder dialog, allowing you to locate duplicate files in your database. For more information, see [Finding Duplicate Files](#).
- **Catalog Files:** Opens the Catalog Files dialog for cataloging new files. For more information, see [Cataloging Files in the Database](#).

Importing Files with ACDSee Home

You can use ACDSee Home to download images from devices like your digital camera, flash drives, CD/DVDs, or other removable devices. In Manage mode, you can also use the **File | Import | From Disk** option to import files from a network, and any kind of disk or drive that can be mapped, while preserving the original folders and subfolders.

Import Status


When importing assets into ACDSee Photo Studio Home 2026, you can track their status, pause, or cancel them from the Activity Manager. For more information see [ACDSee Activity Manager](#).

Importing Files Using the Windows AutoPlay Dialog Box

When you connect your digital camera or other device to your computer, the Windows AutoPlay dialog box prompts you to choose one of the following:

- **Import pictures using ACDSee:** select this option to open the Import dialog box. You can then select settings to rename, backup, and place the files. You can save your import settings and give them a name so that you can re-use them later. You can also create advanced settings for import dates and RAW + JPEG options if your camera takes both file formats. You can also create a file renaming template to use with specific kinds of files or projects.
- **Manage pictures using ACDSee:** select this option to browse the files in ACDSee. You can then choose to import the files or simply copy and paste the files from the device.
- **Import pictures and videos using Windows:** select this option if you prefer to use Windows to import the files.

Depending on the other applications installed on your computer, there may be additional options.

 If you experience difficulties with your computer recognizing your device as a drive, explore your device's manual about mounting the device as a drive. Or use your computer's card reader to access your memory card.

Importing Files from Specific Types of Devices

For more specific instructions, select the type of device you connected:

- [Importing Photos from a Device](#)
- [Importing Photos from a CD or DVD](#)
- [Importing Photos from a Disk](#)

RAW + JPEG Options

Regardless of which type of device is being used to import photos, if the original camera takes both RAW and JPEG file formats, options are available to tailor the image import to a desired workflow.

To set the RAW + JPEG import options:

1. In the **ACDSee Import** dialog, click the **Advanced...** button at the bottom left.
2. In the **Advanced Import Options** dialog, navigate to the **RAW+JPEG** field set.
3. Enable one of the following:
 - **Place both in chosen destination folder:** Places both the RAW and JPEG files in the same folder determined in the **Location** field set of the **ACDSee Import** dialog.

- **Place JPEG in subfolder:** Places only the JPEG files in a subfolder identified in the **Subfolder name** field.
 - **Place RAW in subfolder:** Places only the RAW files in a subfolder identified in the **Subfolder name** field.
4. If either the **Place JPEG in subfolder** or **Place RAW in subfolder** radio buttons are enabled, enter a name in the **Subfolder name** field.
 5. Click **OK** in the **Advanced Import Options** dialog.
 6. Click **Import** in the **ACDSee Import** dialog.



If **Place JPEG in subfolder** is enabled, all JPEGs will be placed in the subfolder whether there are matching RAWs or not. The same also holds true when enabling **Place RAW in subfolder**. All RAW images will be placed in the subfolder whether there are matching JPEGs or not.

About Removable Devices

With ACDSee, there are several ways to obtain images from your digital camera, scanner, or memory card. For more information about how your device communicates with your computer, please consult your device's Help file or manual. Some different types of removable devices are:

- **USB Removable device:** removable devices include memory cards that you can attach to your computer using a USB card reader, camera memory cards that insert directly into slots on the computer, or flash drives. USB removable devices are detected by your computer and are shown in the structure as a removable drive.
- **Windows Image Acquisition (WIA):** cameras and scanners that use Windows Image Acquisition (WIA) drivers to communicate with the computer. Some cameras, including Canon cameras, use WIA. ACDSee Home automatically detects the WIA protocol.



You require DirectX 9.0c and QuickTime to copy and view audio or video files.

Importing Photos from a Device

The Import From dialog box gives you multiple options for importing your files from cameras, card readers, flash drives, and other mass storage devices. If you want to simply import files with a few clicks, you can. Or you can select from several options to streamline your workflow and perform multiple tasks with each import.

In the Import From dialog box, you can view the thumbnails of the files on the device by their date or file type. You can change the size of the thumbnails to make it easier to select those you want to import or leave on the device, and then view only those you have selected.

You can also choose the destination folder or subfolders for the files, create a backup set of files as you import, and rename the files during the import process, automatically rotating them if your camera

has this option. Advanced settings give you options to change the date you want to use, and where to place RAW and JPEG files if your camera creates both file formats.

You can even organize your files as you import by adding Categories, IPTC and ACDSee Metadata.

Then you can save all these settings as a preset to use or adapt later.



If your camera connects to the computer as a removable drive, you can also simply copy photos directly from the File List and [Folders pane](#) because ACDSee Home detects and displays the removable device in the Folders pane. If you are not sure how your camera connects to your computer, please see About Removable Devices in [Importing Files with ACDSee](#).



Some cameras, for example, Canon, use Windows Image Acquisition (WIA) to communicate with a computer. If your devices use these protocols, you can import by clicking **From Device** on the **File | Import** menu. ACDSee Home automatically detects these protocols.

To Download Photos Using the "Import From" Dialog Box:

1. Connect your camera or device to the computer. Make sure your camera is turned on, and the cable is properly connected to your computer.
2. Do one of the following:
 - If the Windows AutoPlay dialog box opens, select **Import pictures using ACDSee**.
 - If you have more than one device connected to your computer, select the device you want to use from the list, and then click **OK**.
 - In Manage mode, click **File | Import | From Device**.
 - Press **Alt + G** on the keyboard.
3. In the Import From dialog box, select from the import options as described below.
4. Click **Import**.
5. To browse your imported photos, click **Yes** when the Import Complete dialog box displays. A new tab will open displaying your results. For more information, see [Browsing with ACDSee Tabs](#).



You may require Direct X 9.0c and QuickTime to download audio and video files from your camera.

Import From Options

Select items to import

Select items to import

You can control which items are imported by choosing one of the following:

- **New:** only imports files that have not been imported in the past.
- **All:** imports all files.
- **Custom:** imports the selected files. You can control which files are imported by checking or unchecking their checkboxes.

View by

Date

Displays all the files grouped by the dates they were created. To deselect a date, check the checkbox beside the date. To deselect all dates, uncheck the **All Dates** checkbox.

File Type

Displays all the files grouped by their file type. To deselect a file type, check the checkbox beside the file type. To deselect all file types, uncheck the **All File Types** checkbox.

View all

Displays all the thumbnails of the files on the device.

View selected

Displays only the files selected for import.

Choose import preset

Import settings drop-down menu

Displays the names of recently used import settings to use again, or you can select one of the following:

- **Current:** uses the current settings to import.
- **Last used:** uses the import settings from the last import.
- **None:** clears all the current import settings.

Save import settings

Saves all the current import settings with a name so that you can use them again. To save (or edit) import settings, select the **Save** icon and type in new name (or re-save existing settings).

The new name for the import settings appears in the drop-down menu.

Delete import settings



Deletes the saved import settings currently selected in the Import settings drop-down menu.

Location

Choose Destination drop-down menu

Displays the names of recently used destinations to use again, or you can select one of the following:

1. **Last used:** Uses the destination from the last import.

-
2. **None:** Clears all the current destination settings.

Place in Subfolders drop-down menu

Displays the following pre-defined subfolder options to select:

- **Single folder by name:** Creates a new subfolder with the name you type into the Name field, which activates when you select this option. All the files are placed into a folder with the new name.
- **Single folder by today's date:** Creates one folder using today's date as the name and places all the files into the folder.
- **Nested folder by today's date:** Creates a series of nested folders, one below the other, based on today's date and the format you select in the **Format** field. The folders are created as the sample shows and all the files are placed in the lowest folder.
- **Nested folders by file's date:** Creates multiple sets of nested folders based on the files' dates and on the format you select in the **Format** field, which activates when you select this option. The folders are created as the sample shows and the files are imported into the lowest folders on each date.
- **Separate folders by file's date:** Creates separate folders based on the individual file dates in the format selected from the **Format** drop-down options.
- **Preserve subfolder names:** Preserves existing folder names when you use the From Disk option to import. For example, if you have a flash drive or CD containing images in a complex set of subfolders, the whole folder tree is imported intact.

Format

Displays date format options for the Nested folder options (see above).

Sample

Displays a sample of the nested folders that will be created using the current settings (see above).

Backup to drop-down menu

Creates a backup set of files using an exact duplicate of the subfolders you have selected under **Place in**.

You can also do one of the following:

- Click **Browse** and then navigate to an existing folder to use as a backup destination.
- Click **Browse** and then **Make New Folder** to create a new folder as a backup destination.



While existing ACDSee Metadata is included in the backup copy, any Catalog settings (IPTC or ACDSee Metadata) added during import will not be included.

File

Rename files to drop-down menu

Renames each file as it imports according to these predefined renaming templates:

- **Date/time - filename:** Creates each filename using the file date and time the file was created plus the original filename.
- **Date/time:** Creates each filename using the file date and the time it was created.
- **Camera - sequence number:** Creates each filename using the camera name and a sequential number starting at one.
- **Date/time - sequence number:** Creates each filename using the file date and the time it was created plus a sequential number starting at one.
- **Camera - filename:** Creates each filename using the camera name and the original filename.

When you create and save your own renaming templates, they also appear in this list for you to select.

Edit

Opens the Rename Templates dialog box where you can [create and save your own renaming templates](#).

Apply Metadata drop-down menu

Select the names of saved metadata presets or select Manage presets to open the Manage Metadata Presets dialog box of options.

Customize

Properties pane Metadata tab: enter ACDSee and IPTC Metadata into to the fields to add to the files you are importing.

Properties pane Categories tab: assigns the imported files to any category selected in this tab. You can select multiple categories.

Automatically rotate images

Rotates your images automatically if your camera creates the information needed for this option to work.

Delete items from source after import

Deletes the imported items from their original location or locations after import.

Advanced

ACDSee database date

Opens the Advanced Import Options dialog box where you can change the date settings for files and specify where to place RAW and JPEG files.

To set the ACDSee Home database, use one of the following as the file date:

- **Exif date:** uses the EXIF date embedded in the image by the camera.
- **File modified date:** uses the date the file was last modified.

- **Specific date:** uses the date you select by clicking the in the calendar drop-down arrow.

RAW+JPEG

To specify where to place RAW+JPEG files select one of the following:

- **Place both in chosen destination folder:** Places RAW and JPEG files in the folder you have selected under **Choose destination** on the Import From dialog box.
- **Place JPEG in subfolder:** places the JPEG files in the folder you have selected under **Choose destination** on the Import From dialog box. Then creates a new subfolder with the name you type into the **Subfolder name** field, which activates when you select this option. All the JPEG files are placed into the new subfolder.
- **Place RAW in subfolder:** places the RAW files in the folder you have selected under **Choose destination** on the Import From dialog box. Then creates a new subfolder with the name you type into the **Subfolder name** field, which activates when you select this option. All the RAW files are placed into the new subfolder.



The values set in the IPTC fields are reflected in their corresponding EXIF field.

Importing Photos From a Scanner

You can scan images using ACDSee and import them to specific, accessible locations.

To Specify a Destination for Your Scanned Images:

1. Click **Tools | Options | Manage Mode**.
2. On the Manage mode page, in the Scanning Destination section, click the **Browse For Folder** button.
3. In the Browse For Folder dialog, select a destination folder for your scanned images.
4. Press **OK**.

To Scan Images:

1. In Manage mode, click **File | Import | From Scanner**.
2. Configure your scanning settings as desired. As the scanning dialog is controlled by Windows, these settings will vary, depending on your OS and version of ACDSee.
3. Navigate to the location you set as the destination for your scanned images using the Folders pane.

Importing Photos From a CD or DVD

You can download photos from a CD or DVD using the Import From dialog box, or the [Folders pane](#). Before you import photos, you can browse to the CD and view them just like any other folder and then simply copy and paste them into a new location.

If you use the Import From dialog box, you can set the subfolder options to import complex folder structures intact, including all the folder names. You can also organize your files as you import them, as well as create a duplicate backup folder, simultaneously.

To Import Photos from a CD or DVD:

1. Insert the CD or DVD into the drive.
2. Do one of the following:
 - If the Windows AutoPlay dialog box opens, select **Import pictures using ACDSee**.
 - If you have more than one CD or DVD drive connected to your computer, select the device you want to use, and then click **OK**.
 - In Manage mode, click **File | Import | From CD/DVD**.
3. In the Import From dialog box, select the [Import From options](#) you want to use, and then click **Import**.
4. To browse your imported photos, click **Yes** when the Import Complete dialog box displays. A new tab will open displaying your results. For more information, see [Browsing with ACDSee Tabs](#).

Importing Photos From a Disk

ACDSee Home makes it easy to import photos from any other storage device, computer, network, flash drive etc. In fact, any device that your computer can map to. When you connect a removable drive, or to a network, disk or another computer, ACDSee Home sees it as a removable drive and you can browse to it, and around it, using the Folders pane. You can just copy and paste the files into ACDSee.

If the files in the disk or drive have a complex folder structure or you want to organize, rename, and back up the files as you import them, it is worth using the Import From dialog box, which has import settings do all these tasks simultaneously.

To Import Photos from a Disk:

1. Connect the disk to the computer.
2. Do one of the following:
 - If the Windows AutoPlay dialog box opens, select **Import pictures using ACDSee**.
 - If you have more than one disk or drive connected to your computer, select the device you want to use, and then click **OK**.
 - In Manage mode, click **File | Import | From Disk**.
3. In the Browse for Folder dialog box, navigate to the removable drive or device in the folder tree, and then click **OK**.
4. In the Import From dialog box, select the [options](#) you want to use, and then click **Import**.
5. To browse your imported photos, click **Yes** when the Import Complete dialog box displays. A new tab will open displaying your results. For more information, see [Browsing with ACDSee Tabs](#).

Creating a Renaming Template

In the Import From dialog box, you can create, name, and save a template that gives each file a unique name as they are imported and placed on your hard drive. You can then re-use the template each time you import photos. Renaming templates can have a numerical sequence, custom text, and file-specific information in each new file name. You can create and save different renaming templates for different sorts of files. For example, you could have a different renaming template for a different camera, or a different type of file.



To Create a Renaming Template:

1. In the Import From dialog box, select **Rename files to**.
2. From the drop-down list, select one of the following system templates:
 - **Date/time - filename**: Renames the files using the date and time each file was created and the original file name.
 - **Date/time**: Renames the files using the date and time each file was created.
 - **Camera - sequence number**: Renames the files using the camera name and a sequential number.
 - **Date/time - sequence number**: Renames the files using the date and time each file was created and a sequential number.
 - **Camera - filename**: Renames the files with the name of the camera and each file's original name.
3. To create your own renaming template, or add to a system template, click **Edit**.
4. In the Rename Templates dialog box, select from the options as described in the table below.
5. Click **OK**.



If you check the **Skip video and audio files** checkbox, the rename process will not rename video and audio files.

Rename Templates Options

System template drop-down list	Click the drop-down list to select a different pre-defined system template.
New rename template 	<p>Click to open the New Rename Template dialog box where you can type in a name for your own renaming template. Give the renaming template a name that clearly identifies how you plan to use the template, or what kind of information the name will contain. For example, Camera name_photographer.</p> <p>When you click Save, the name of your new template is added to the drop-down list of system templates.</p>
Delete 	Deletes the renaming template currently selected in the drop-down list unless it is a pre-defined system template, which cannot be deleted.
Rename Template	<p>Use this field to create the renaming template. You can type in the photographer's name and an underscore between each element of the template to make it easier to read.</p> <p>Use the following placeholders to ensure that each filename is unique:</p> <ul style="list-style-type: none"> • Insert an *. When your files are renamed, the * will be replaced by the original file name. • Insert a #. When your files are renamed, each # will be replaced by a sequential number. If you have copious amounts of files, insert several ##s. For example, if you enter ###, the first file renamed will be numbered 001, the next 002, and so on. If you have over 1000 files, insert ####. • Insert a metadata placeholder < > and the data inside these brackets is replaced with whatever data you have chosen. For example, if you choose <Camera:Model>, the model of the camera is inserted into each file name.
Insert Metadata	Click to open the Choose Properties dialog box, where you can select from a long list of metadata to insert into your template.
Sample	As you type, or add placeholders in the Rename Template field, the same updates to show you a sample of how renaming template will look.
Skip video and audio files	Skips the renaming of video and audio files during the rename process.

Importing a Lightroom® Database

You can use the Adobe® Lightroom® Database Importer to import your collections, keywords, ratings, and color labels from Lightroom® into ACDSee. Your keyword hierarchies will import independent of whether they are embedded in the images selected for import.



You cannot import smart collections or Lightroom CC catalogs, only Lightroom Classic catalogs.



You cannot begin importing while Lightroom® is open.



If you have a hierarchy in your Collections in ACDSee Home that is identical to your hierarchy in Lightroom®, these collections will merge.

To Import Your Lightroom® Database:

1. In Manage mode, choose **Tools | Database | Import | Lightroom Database**.
2. In the Adobe Lightroom Database Importer, press **Next**.
3. Check the checkboxes of the database information you would like to import into ACDSee, including Ratings, Labels, Collections, and Keywords.
4. Use the Browse button next to the Location field to navigate to the location of your Lightroom® database file.



By default, the field displays the default location where Lightroom® stores its database, so you will only need to browse if you have moved your database.

5. Press **Next**.
6. Check the summary to ensure that the displayed information is correct. If you see a mistake, use the Back button to return to the previous page to make any corrections.
7. Press **Next**. Green checkmarks will display next to the items that are successfully completed, and red crossmarks will display next to items that failed.
8. Press **Finish**.

Lightroom is a registered trademark of Adobe Inc.

Working with Images on Mobile

You can access, browse, view, delete, and copy and paste images on your mobile phone with ACDSee. To edit images on your mobile device, you will need to copy them to a local folder.

To Access the Images on Your Phone Using ACDSee:

 Make sure that file sharing is enabled on your mobile device.

1. With your phone plugged in, open ACDSee.
2. In Manage mode, using the Folders pane, navigate to your phone under This PC/Computer.
3. Using the Folders pane or File List pane, navigate to your images. They are usually stored in a folder called DCIM.

 ACDSee displays file information supplied by your device in the Properties pane.

To View an Image from Your Mobile Phone:

In the File List pane, double-click the image.

 You can use the Filmstrip to navigate through the images in the folder.

To Copy Images from Your Mobile Phone to Another Folder Using ACDSee:

In the File List pane, select the images and do one of the following:

- Right-click and choose **Copy**. Browse to another folder, right-click and choose **Paste**.
- Right-click and choose **Copy To Folder...** In the **Copy To Folder** dialog, select the destination folder and click **OK**.
- Go to **Edit | Copy**, or press **Ctrl + C**. Then, in the destination folder, go to **Edit | Paste**, or press **Ctrl + V**.

To Delete Images from Your Mobile Phone Using ACDSee:

 It may be necessary to change settings on your mobile device to allow files to be deleted using your PC.

In the File List pane, select the images and do one of the following:

- Right-click and choose **Delete**.
- Press **DEL**.
- Go to **Edit | Delete**.


Sending Images to ACDSee from Your Mobile Device Using ACDSee Mobile Sync

You can use the ACDSee Mobile Sync app to send photos and videos directly from your mobile device into ACDSee Photo Studio on your PC. This free app is available on iOS from the Apple App Store and for Android on the Google Play Store.



ACDSee Mobile Sync will keep track of which photos have been sent to ACDSee Home and indicates new and unsent items using a colored border.

In Manage mode, you will be able to access images you have sent to ACDSee Home by clicking the ACDSee Mobile Sync node icon in the Folders pane.



Getting Started

To download the app, you can:

- Download it in the [Apple App Store](#), for iOS. In the App Store, type **ACDSee Mobile Sync** in the Search bar.
- Download it in the [Google Play Store](#), for Android. In the Play Store, type **ACDSee Mobile Sync** in the Search bar.

After installation, open the ACDSee Mobile Sync app on your device. Follow the prompts to give the app access to your photos and to assign the target (ACDSee on your PC). If your app doesn't find the target, you can scan the Quick Response (QR) code found on your PC.

To open the QR code, do one of the following:

- Open **Tools | Show ACDSee Mobile Sync Details...**
- In the Notification Area, right-click on the ACDSee app icon and select **Show ACDSee Mobile Sync Details...**

Then scan the QR code using your mobile device camera to add your ACDSee software as a target.

If you cannot scan the QR code, you can also add your ACDSee software as a target using your host name or IP address.

To add your ACDSee software as a target using your host name or IP address:

1. Make sure you are on the same WiFi network as your PC.
2. On the Mobile Sync app, on the QR scanner page, select **Add Without QR Code**.



If you skipped the intro, or want to add an additional target, you can reopen the scanner page by going to Settings and selecting **Add Target**.

3. Enter your Host name or IP Address and enter the Port. This information can be found above the QR code when you select **Show ACDSee Mobile Sync Details...** on your PC.
4. The name of your target will appear. Select **Add this Target**.
5. This will add your ACDSee software as a target, allowing you to send photos and videos to it.



You must be connected to the same WiFi network as the PC that is running ACDSee Home in order to use ACDSee Mobile Sync to send photos and videos.

Sending Images and Videos

You can send images and videos from the ACDSee Mobile Sync app to ACDSee. ACDSee Mobile Sync keeps track of which items have already been sent. ACDSee Home will notify you with a pop-up in the lower right corner when it has received your sent items. You can then click on the ACDSee Mobile Sync node icon in the Folders pane in Manage mode to view the received files.

To send all new items, press the **Send** button. If you press and hold the **Send** button, it will send the selected photos and videos to the default target.

To send specific items, select them and press the **Send** button.



You can use context menus within the app for more specific selection options.



You can customize the location of your ACDSee Mobile Sync folder on your hard drive. See [Setting the ACDSee Mobile Sync Options](#).

Troubleshooting for Mobile Sync

If you have any issues connecting your device to use Mobile Sync, check out our troubleshooting guide on the [ACDSee Mobile Sync webpage](#).

Browsing Files in the File List Pane

The File List pane is the large pane in the center of the Manage mode window. The File List pane displays the contents of the currently selected folder, the results of your latest search, or the files and folders that match your selective browsing criteria. The File List pane is always visible, and cannot be hidden or closed.

Files display as thumbnails in the File List pane by default. However, you can change the File List pane view from thumbnails to details, list, icons, tiles, or Filmstrip. You can sort your files according to name, size, properties, and more. You can also use filters to control which files display in the File List pane.

Using the File List Pane

There are three sections in the File List pane: the Contents bar, the File List drop-down lists, and the File List toolbar. The overlay icons, which appear on the thumbnails, allow you to rate, tag, and label your images or documents and indicate additional information, such as if the file has been processed or geotagged.

The Contents Bar

The Contents bar is located at the top of the File List pane and describes what you are currently browsing. When you are using the Folders pane, the Contents bar will display the path or paths to the folders you are browsing, as in the following example:



If you are browsing files by category or rating with the Catalog pane, the Contents bar displays the selected classifications, as in the following example:











The Contents bar also displays a date range when browsing with [the Calendar pane](#), and a summary of your search criteria when you use the Advanced Search pane.





File List Drop-Down Lists








Filter	Displays a list of filter options such as rating and category. You can also select Advanced Filters and create a custom filter.
Group	Displays a list of file attributes that you can use to group files in the File List pane.
Sort	Displays a list of file attributes that you can use to sort the files in the File List pane.
View	Displays a list of view options for viewing files in the File List pane.
Select	Displays a list of file selection options.





File List Toolbar

	Add to Image Basket	Adds selected images to the Image Basket.
	Rotate left	Rotates selected images to the left.
	Rotate right	Rotates selected images to the right.
	Compare images	Opens selected images in the Compare Images Viewer.
	Auto Advance	Turns on Auto Advance to quickly move through images while adding tags, ratings, labels, categories, or keywords.
	Zoom slider	Controls the size of the thumbnails in the File List pane. Drag the slider to adjust the thumbnails.
	Photos	Displays the contents of the selected folder as thumbnails.
	List View	Displays the contents of the selected folder as a file list.

Overlay Icons

Icon	Name	Description	Instructions
	Sound / Playing Sound	Appears if the file contains embedded or associated audio. The second icon appears if you click on the sound icon and the embedded sound begins playing.	Left-click to play embedded audio.
	Rating	Appears if the file has been rated in the ACDSee Home database.	
	Color Label	Appears if the file has been assigned a color label.	
	Embed Pending	Appears if the file has ACDSee Metadata stored in the ACDSee Home database that has not yet been written to the file.	<p>Right-click and choose either:</p> <ul style="list-style-type: none"> • Embed ACDSee Metadata: writes the metadata to the file. • Clear Embed Pending Icon...: clears this overlay icon, but does not write the metadata to the file.

Icon	Name	Description	Instructions
	File format	Displays the file format.	Left-click to display the File Information, Image Attributes, and EXIF Metadata (summary) on the File tab of the Properties pane.
	Category	Appears if the file has been categorized.	Left-click to open the Categories section on the Organize tab of the Properties pane.
	Collection	Appears if the file has been added to a collection.	
	Shortcut	Appears if the item is a shortcut to another file.	
	Offline	Appears if the file is stored on an offline device.	
	Excluded items	Appears if the file has been excluded from the ACDSee Home database.	
	Tagged items	Appears if the file has been tagged.	

Icon	Name	Description	Instructions
	Untagged items	Appears if the file has not been tagged.	
	Geotagged items	Appears if the file has been geotagged.	Left-click to open the Map pane.
	Auto-rotate	Appears if the file has been automatically rotated.	Left-click to rotate the image original permanently and update the EXIF information.
	Edited	Appears if the file has been edited.	

Changing Overlay Icon Visibility

You can change whether overlay icons are visible, visible in color, and which icons are in color.

To Change Overlay Icon Visibility:

In Manage Mode, at the top of the File List pane, do one of the following:

- Click **View | Toggle Overlay Mode** to control whether the overlay icons are invisible, visible in grayscale, or visible in color. Toggle the ([I]) key to move through the available modes.
- Click **View | Highlight Overlay** to select which icons appear in color. Toggle the ([I]) key to select from the available options.



Note that this does not apply to all overlay icons. For more control over which icons are visible, see [Setting the Thumbnail Info Options](#).

Maximizing the File List Pane

To make the most of your available screen space, you can choose to maximize the File List pane and hide the rest of the Manage mode panes. The only parts of the Manage mode window that remain visible are the File List pane and whichever toolbars you are currently using.

To Maximize the File List Pane:

1. Click **View | Maximize File List**.
2. To show only the File List pane and its toolbar, click **View | Full Screen**.
3. Click the **Close Full Screen** button in the upper right corner to return to Manage mode.

To Manage Your Files:

Do one of the following:

To delete a file, in the File List pane, right-click the file and choose **Delete** from the context menu, or press **Delete**.

To rename a file, right-click the file and choose **Rename** from the context menu, or press **F2**. You can also Type a new name for the file and press **Enter**.

Browsing Using the Folders Pane

The Folders pane displays a directory tree of all the folders on your computer in the same style as they appear in Windows Explorer. You can select one or more folders in the Folders pane to display their contents in the [File List pane](#). The Folders pane also displays your Cloud Drives as a node, allowing you to navigate your cloud content like any other folder.

You can also use the Folders pane to create shortcuts to your favorite files, folders, or applications. Then, instead of having to search for a specific file, you can quickly access it in the [Shortcuts pane](#).

Whenever you browse to a folder using the Folders pane, the ACDSee Home database catalogs any images, documents, or media files in the folder.


To Open or Close the Folders Pane:

In Manage mode, click **Panes | Folders**.

When you connect a removable device, such as a mass storage device or digital camera, the Folders pane displays the device as another drive, and assigns it a drive letter automatically.

You can access the device, and its contents, by clicking on it in the Folders pane.

Selecting Multiple Folders

Easy-Select bars are indicators on the left side of the Folders and Catalog panes, they look like this: . You can use the Easy-Select bars to select multiple folders, categories, or ratings, and display their contents in the File List pane.

To Use the Easy-Select Bar:

In the Folders pane, select the indicator to the left of each folder with contents you want to display.

You can also use the Easy-Select bars with the [Selective Browsing pane](#).

Creating and Managing Folders

You can use the Folders and File List panes to create, delete, rename, and move folders on your hard drive to help organize your files.

To Manage Your Folders:

1. In the Folders pane, browse to where you want to add, delete, or rename a folder.
2. Do one of the following:
 - To create a folder, click **File | New**, and then select **Folder**. Type a name for the new folder and press **Enter**.
 - To delete a folder, select a folder and press **Delete**.
 - To rename a folder, right-click the folder you want to rename and select **Rename**. Type a new name for the folder and press **Enter**.



You cannot rename a drive or any folder on a read-only file system, such as a CD-ROM.

Browsing Using ACDSee Tabs

ACDSee Tabs in **Manage Mode** allow you to open and manage multiple folders, search results, and more—all within a single window. You can easily open folders in new tabs, retain search results for later reference, and conduct multiple searches, switching between them as needed.

When working with assets in **Manage Mode**, you can open up to **25** different tabs.

Startup Behavior

To set the **Startup Behavior**, go to **Tools | Options**, then select **Manage Mode**.

You can configure ACDSee to launch with one of four startup behaviors:

- **Open ACDSee Home Page:** Displays the ACDSee Home Page on launch.
- **Open Start Folder:** Opens a new tab showing your designated Start Folder. Also determines where a new tab will start.
- **Reopen Last Active Tab:** Re-opens the last active tab you were using before closing ACDSee.
- **Reopen All Previous Tabs:** Restores all tabs that were open prior to closing the application.

Managing ACDSee Tabs

Opening a New Tab to the Start Folder

To open a new tab to the Start Folder, perform one of the following:

- Click the **+** to the right of the currently visible tab(s).
- Right-click on the tab-bar and select **New Tab**, or press **Ctrl + T**.
- Right-click on any folder and select **Open in New Tab**.



The Home folder can be changed in the Manage mode options. See [Setting the Manage Mode Options](#).

Opening a New Tab to a Specific Folder

To open a new tab to a specific folder, perform one of the following:

- Right-click on a folder and select **Open in New Tab**. You can open folders this way from the File List pane and the Folders pane.
- Middle-click a folder.
- Right-click a tab-bar and select **Duplicate**, or press **Alt + D**. This duplicates the currently selected tab.

Closing Tabs

Closing a Single Tab

When you have more than one tab open, individual tabs can be closed by performing one of the following:

Click the X on the tab.	Appears when two or more tabs are open.
Middle-click on a tab.	Closes the clicked tab.
Right-click on a tab and select Close Tab , or press Ctrl + W .	Closes the currently selected tab.

Closing Multiple Tabs

When you have more than one tab open, multiple tabs can be closed by performing one of the following:

Right-click a tab and select Close Other Tabs .	Closes all tabs except the selected one.
Right-click a tab and select Close Tabs to the Left .	Closes all tabs to the left of the selected tab.
Right-click a tab and select Close Tabs to the Right .	Closes all tabs to the right of the selected tab.



Manage Mode will always have at least one tab open.

Tab Navigation

Tabs can be navigated quickly using keyboard shortcuts:

Activate Next Tab	Press Ctrl + Page Down or Ctrl + Tab .
Activate Previous Tab	Press Ctrl + Page Up or Ctrl + Shift + Tab .

Transferring Files Between Tabs

You can drag and drop files between tabs by selecting the assets you want to move. Drag the files up to the target tab and hover briefly to switch to that tab, then drop them into the file list.

Managing Panes and Options in ACDSee Tabs

In **Manage Mode**, many options and panes can be customized independently per tab. This includes settings for **Filter**, **Group**, and **View** options, as well as the **Folders**, **Catalog**, **Calendar**, and **Advanced Search** panes. When a new tab is opened, its options and panes are duplicated from the previously selected tab. When ACDSee closes, all tabs close, but the program restores the options from the last active tab upon restart.

Performing Searches Using ACDSee Tabs

Searches are performed within tabs, allowing you to retain results by opening a new tab and continuing your work. You can easily return to your original search tab at any time. Searches in the **Advanced Search**, **Catalog**, or **Calendar** panes, as well as selections within those panes, are specific to each tab—enabling multiple searches and comparisons across tabs.

Using Microsoft OneDrive™

You can use Microsoft OneDrive™ directly from Photo Studio, allowing you to access all of your photos without the need to migrate.

Local and Cloud Access:

When browsing in OneDrive™, you'll have the option to select whether or not files automatically download to your PC, or remain stored on the cloud.




File Context Menu:

Right clicking on either a OneDrive™ folder in the folders pane, or any individual file will provide the following context menu options:

- **Always Keep on this Device:** This option will tell the selected files or folders to download and keep local copies of the items on your PC.

- **Free Up Space:** This option will tell OneDrive™ to not download the selected files or folders, and remove any local copies. This will limit what data is visible, but will free up space on your PC.

OneDrive™ will store and display files in three ways:

- **Local:**  Files with the unfilled green checkmark circle indicate that they have temporarily downloaded from OneDrive™ onto your PC. OneDrive™ may offload the files automatically when syncing back to the cloud at a later time.
- **Always Local:**  Files that have been set to always keep on this device are indicated by the filled in green checkmark circle. OneDrive™ will retain a copy of the file locally when it syncs with the server, ensuring that the file is always available on your PC.
- **Cloud:**  Files with the cloud icon indicate that they presently exist within the cloud only, and are available for downloading/viewing.



Cloud files will be downloaded automatically when taken to View or Edit mode. When accessing a large file, it may take longer than usual to switch modes or switch between files if it is still being downloaded.

OneDrive™ Status Column:

You can see the status of your files in OneDrive™ in a variety of ways:

In Manage mode you'll see the status of your files in Filmstrip, Thumbnails, and Tiles view automatically. Thumbs & Details, and the Details views can have OneDrive status added.

To add OneDrive status to Thumbs & Details or Details:

1. Click on View directly above your image files, and select Thumbs & Details, or Details
2. Right click the Details Header bar and select Choose Details...
3. Click File Properties, then OneDrive Status, and click the Add -> button.
4. Select Ok.



List and Icons views do not display OneDrive status.

Viewing and Embedding Metadata to Your Files on OneDrive™

EXIF and IPTC metadata is not visible until the file has been downloaded to your PC.

You can still add new ACDSee metadata to the file even while it's only on the cloud.

If you'd like to embed ACDSee metadata to the file, please see [Embedding ACDSee Metadata in Files.](#)

Moving Files to OneDrive™:

Select one or more files outside of OneDrive™ and right click to open the context menu and select **Move to OneDrive**. Files will be moved to your root OneDrive™ folder.



If you have both a personal and business OneDrive™ connected, you'll be able to select from either one.

Browsing Files By Date or Event

With the Calendar pane you can browse your collection of image and media files using the dates associated with each file. The Calendar pane includes Events, Year, Month, Day view and the Photo Calendar, which shows thumbnails per day within a month. You can click any date in the Calendar pane to display a list of files associated with that date.

To Open the Calendar Pane:

In Manage mode, click **Panes | Calendar**.

The Calendar pane opens in the center File List pane area.









Your images will not display in the Calendar pane until you have either browsed the folder containing the images or used the Catalog Files wizard to catalog your images so they are in the ACDSee Home database.



If you are using the Photo Calendar, you only see thumbnails if there are photos on a particular day in that month. Days that have no photo, are blank.

Calendar Pane View Options

	Events View	Switches the Calendar pane to Events view. In the Events view you see only those months during which images or media files are available. Next to the month you see the number of dates on which images or media files are available. Expand the month to see the dates and the number of pictures available for those dates. You can add a description and a thumbnail image to help you remember the event.
	Year View	Switches the Calendar pane to Year view. In Year view you see a series of tables. Each table represents a specific year. Next to the year you see how many images or media files are associated with that year. The months during which images or media files are available are highlighted.
	Month View	Switches the Calendar pane to Month view. In Month view you see a series of tables. Each table represents a specific month. Next to the month you see how many images or media files are associated with that month. The dates on which images or media files are available are highlighted.
	Day View	Switches the Calendar pane to Day view. In Day view you see a series of tables. Each table represents a specific day. Next to the date you see how many images or media files are associated with that date. The time at which the images or media files are available are highlighted.
	Photo Calendar	Switches the Calendar pane to the Photo Calendar. In the Photo Calendar, you see a single month with thumbnails for any day that contains photos. A pop-up of the first four images opens if you hover your cursor over a thumbnail. Click on a thumbnail and all the pictures for that date display in the File List. The total number of photos belonging to that month is in the top right corner of the calendar. Drag the title bar to float this pane onto another monitor and drag a corner to resize it and make the thumbnails bigger or smaller.
	Options	<p>Use the Calendar pane options to specify which date you want to use to organize your files. For example, you can quickly change the setting so that the photos are displayed by the following:</p> <ul style="list-style-type: none">• Date the ACDSee Home database cataloged the file• Date the image was taken• Date the file was modified• Date the file was loaded to your computer

Select Options to open the Calendar dialog, where you can set filter options, choose the day to start the week, and set clock formats.



Table of Contents

Opens a list of event dates.



Only available in Events View.



In all views apart from Events View, you can use **Shift + Left Arrow** or **Shift + Right Arrow** to navigate between dates with images. For example, in Month View, if you had taken pictures in August, September, and November, by using **Shift + Right Arrow**, you will skip the empty month of October.

Adding Descriptions and Thumbnails in Events View

You can add a description and a thumbnail image to dates in Events view to help you remember the event.



Try right-clicking the Calendar Title bar and select **Floating** to move the pane to a new location.

To Add a Description to a Date in Events View:

1. Expand the month to see the dates on which images or media files are available.
2. Click **Enter event description here** and replace the highlighted text with a new description.
3. Press **Enter** or click outside of the description area. The description is saved.

To Select a Specific Thumbnail in the Events View or Photo Calendar:

1. Expand the month to see the dates on which images or media files are available.
2. Click on a date to display the images or media files in the File List pane.
3. Click and drag an image or media file and drag it to the thumbnail area for the date.

When you release the mouse button the thumbnail is saved. You can reset the default thumbnail by right-clicking the thumbnail and selecting **Restore Default Thumbnail**.

To Navigate a Long List of Dates in Events View:

1. To expand and collapse specific groups click the **+/-** signs which are located on the left side of the group header.
2. To expand and collapse all groups right-click a group header and select either **Open All Groups** or **Close All Groups**.

3. To scroll through multiple groups click the **Next Group** and **Previous Group** buttons, which are located at the bottom of the File List scroll bar.
4. At the bottom of the Calendar pane scroll bar, click the **Table of Contents** button and select a date.

Browsing Your Favorite Files

You can create shortcuts to your favorite files for easy access.

Accessing the Shortcuts Pane

Click **Panes | Shortcuts**.

Creating a Shortcut

You can create shortcuts to folders and files, and even run executable files, from inside the Shortcuts pane. Favorite shortcuts can be copied, renamed, moved, or deleted just like a folder. You can even use an executable shortcut to start another application from inside ACDSee. You can also create a shortcut by dragging a file, folder, or executable file directly from the File List pane to the Shortcuts pane.

To Add Files to the Shortcuts Pane:


1. In the File List pane, select a file, folder, or executable file.
2. Do one of the following:
 - Right-click the item you selected, and then select **Add to Shortcuts**.
 - Click **File | Add to Shortcuts**.
3. Type a name for the new shortcut and click **OK**.

Creating a New Folder

You can create a folder, or an entire directory tree, in the Shortcuts pane to help organize your favorites.

To Create a New Folder:

1. In the Shortcuts pane, right-click the Shortcuts folder, or a folder you previously created, and then select **New | Folder**.
2. Type the name of the folder and press **Enter**.

 If you move a file or a folder that is a shortcuts, you break the link and the shortcut no longer works.

Deleting a Shortcut or Folder

You can delete a shortcut or folder from within the Shortcuts pane.

To Delete a Shortcut or Folder:

In the Shortcuts pane, right-click the shortcut or folder, click **Delete**, and then click **Yes** to confirm that you want to delete the shortcut or folder.

Detecting Faces in Manage Mode

ACDSee automatically adds file information and thumbnails to the database as you browse. This process is called cataloging. Once the folder you are browsing has been cataloged, ACDSee begins the process of detecting faces in your images. As you open other folders, ACDSee will prioritize scanning faces in the most recently viewed folder, placing them at the front of the queue, before continuing to process the remaining images. You can view the scanning progress in the **Idle Activities** section of the **Activity Manager**. You can find the **Activity Manager** pane on the right side of the application by default, press **Ctrl + Shift + 6**, or go to **Panes | Activity Manager**. ACDSee will continue scanning until Face Detection is complete, or has been manually paused or turned off.

Scanning for Faces:

In the **Idle Activities** section of the **Activity Manager**, you will see a display of the number of images queued for scanning.

If your queue has become too large and you wish to reset it, you can clear it using the options gear in the top-right corner of the **Idle Activities** section. You can also flip the toggle on the right side of the Face Detection section to turn it off at any time.



You can also detect faces on an image by image basis in View mode. Face Detection will scan each image for faces as you open it.

After Face Detection has run on the folders you have browsed, you can open the images in View mode, where the faces will be outlined. You can assign names to the detected faces in [View mode](#).

To Enable or Disable Face Detection:

Choose **Tools | Options | Face Detection** and check or uncheck the **Enable Face Detection** checkbox.

Once you have assigned names to detected faces in View mode, you can use the People group of the [Catalog pane](#) to find photos based on the individuals in them. You can also search by name in the [Quick Search bar](#) and the [Advanced Search pane](#). You can manage the names assigned to faces through Face Detection using the [People mode](#).

To Remove Face Detection and Recognition on Selected Images:

You can remove face detection and recognition data on images selected in Manage mode.

1. In Manage mode, select one or more images.
2. Choose **AI | AI Face Detection | Remove Faces**, or right-click an image select **AI Features | AI Face Detection | Remove Faces**.

These images will remain marked as having been scanned for faces, and **Face Detection** will not re-scan them, unless triggered by the **Redetect Faces** command, or [enabling the option to rerun Face Detection](#).

To Rerun Face Detection on Selected Images:

You can force Face Detection to re-scan selected images in Manage mode.

1. In Manage mode, select one or more images.
2. Choose **AI | AI Face Detection | Redetect Faces**, or right-click an image and select **AI Features | AI Face Detection | Redetect Faces**.

To Rerun Facial Recognition on Selected Images:

In order to correct names mistakenly assigned to faces by ACDSee, you can rerun facial recognition on faces you have not manually named within the selected image or images. This clears all names assigned by ACDSee's facial recognition, but leaves manually entered names. ACDSee will then attempt to recognize unnamed faces based on names you have entered manually.

1. In Manage mode, select one or more images.
2. Choose **AI | AI Face Detection | Rerun Recognition**, or right-click an image select **AI Features | AI Face Detection | Rerun Recognition**.



Faces can only be auto named if the [Enable Auto Naming](#) option is enabled.

Embedding, Retrieving, and Importing Face Data

Any interaction you make with the Face Detection feature will create "face data", which is added to the database, and will, therefore, trigger the [Embed Pending icon](#). Face data is embedded in your image's XMP file, just like any ACDSee Metadata. By embedding this face data into your files as well, you can share it, restore it, or make it available in a new database.

To Embed Face Data:

You can embed your face data using the Embed ACDSee Metadata dialog. See [Embedding ACDSee Metadata in Files](#).

To Retrieve Face Data Embedded in Files:

Do one of the following:

- Choose **AI | AI Face Detection | Import ACDSee Face Data**.
- Choose **Tools | Database | Catalog Files**. In the Catalog Files dialog, in the Import from Cataloged Files section, check the **ACDSee Face Data** checkbox. Press **Start**.

To Import Embedded Face Data From Lightroom or Picasa :

1. In Manage Mode, select the images for which you have embedded face data in another application.
2. Select **AI | AI Face Detection | Import Lightroom or Picasa Face Data**.
3. A warning dialog will pop up asking if you want to overwrite any existing face data and add face data from another program to the files. Select **OK** if so.
4. Your face data will import and the face data will be added to your database.

Changing Views

You can select different views to display your files in the File List pane, including thumbnail previews and file details. You can also customize the appearance and size of thumbnails, and specify the information displayed in the Details view.

To Change the File List View:

In Manage mode, in the File List pane, under **View**, select from the following:

Views

Thumbs+Details	Displays file names and details in a list, and adds a thumbnail preview to the Filename column.
Filmstrip	Displays thumbnail previews of your files in a single row across the bottom of the File List pane, and displays the currently selected file in an expanded Preview pane.
Thumbnails	Displays thumbnail previews of all image and media files (and some document types) in the File List pane. You can customize the appearance of thumbnails, and specify what information to display with them.
Tiles	Displays each file in the File List pane on a "tile" that includes a thumbnail preview and file information. You can resize the tiles using the Zoom slider.
Icons	Displays files in a list, represented by large default system icons for each file type.
List	Displays a list of file names and extensions.
Details	Displays a list of file names and details about each file, such as size, format, and creation date. You can customize the appearance of the Details view mode, as explained below, and specify what information it displays.
Toggle Overlay Mode	Controls whether overlay icons are invisible, visible in grayscale, or visible in color. Use the ([I]) key to choose.
Highlight Overlay	Controls which overlay icon is colored. Use the ([I]) key to rotate through.

Customizing the Details View

You can set the Details view to automatically resize columns, display or hide grid lines, and select an entire row when you select a column entry in that row. You can also change the appearance of the Details view, select which columns to display, and customize the column order.

To Select Columns and Set Column Order:

1. In Manage mode, from the File List drop-down, click **View | Choose Details**.
2. In the Choose Details dialog box, do one or more of the following:
 - To add a column, select a folder or detail name in the Available Details pane, and then click **Add**. Adding a folder adds all detail names within the folder.
 - To remove a column, select a detail name in the Currently Displayed Details pane, and then click **Remove**.
 - To move a column to the left in the File List pane, select its name in the Currently Displayed Details pane and click **Move Up**.

- To move a column to the right in the File List pane, select its name in the Currently Displayed Details pane and click **Move Down**.

3. Click **OK**.



You can click **Reset** to display only the default column names in the Currently Displayed Details pane, and you can also move a column in the File List pane by dragging its header to a new position. A vertical line indicates where the column will be inserted.

Filtering Files

You can use the Filter By options to identify the types of files and folders you want to display in the File List pane.

To Filter Files in the File List Pane:

Do one of the following:

- Click **View | Filter By** and select a filter option.
- Click the **Filter** drop-down and select a filter option.



If all your thumbnails seem to disappear, click **Filter | All** and they reappear.

To Create a Custom Filter:

1. Do one of the following:

- Click **View | Filter By | Advanced Filters**.
- Click the **Filter** drop-down and select **Advanced Filters**.

2. Select **Apply filtering criteria**.

3. Select or clear one or more of the following options to show or hide that file or folder type in the File List pane:

- **Show image files**
- **Show media files**
- **Show folders**
- **Show archive files**
- Select **Show hidden files and folders** to show files and folders that are normally hidden by your operating system.

- Select **Show THM files** to show thumbnail files.
- Select **Show XMP files** to show the XMP sidecar files.

4. Click **OK**.

Grouping Files

If you have to browse a lot of images in the File List you should consider using Group By to organize images into different groups. You may find it easier to find images when they are organized into groups. For example, if you use more than one camera, you can quickly organize your images according to the camera you used to capture the images. Similarly, if you save your images into different file formats you can quickly organize your images according to their file format.



Group By only works in the Thumbs, Thumbs + Details, Details, Tiles, and Icons views.



The Edited State group is particularly useful for finding images that you have edited.

To Group Files in the File List:

1. Browse to the folder or folders containing your files.
2. Do one of the following:
 - Click **View | Group By** and select a group option.
 - Click the **Group** drop-down and select a group option.

Navigating Through Groups in the File List

To Expand and Collapse Specific Groups:

Click the **Expand** or **Collapse** arrows, on the left side of the group header.

To Expand and Collapse All Groups:

Right-click a group header, and then select either **Open All Groups** or **Close All Groups**.

To Display a Preview of the Images in a Closed Group:

Hover your cursor over the group header.

To Scroll Through Multiple Groups:

Click the **Next Group** and **Previous Group** buttons at the bottom of the File List scroll bar.

To Display the Table of Contents:

Do one of the following:

- Click **View | Group By | Table of Contents**.
- Click the **Group** drop-down list and select **Table of Contents**.
- At the bottom of the File List scroll bar, click the **Table of Contents** button.

To Quickly Jump to a Specific Group:

1. Display the table of contents.
2. Click the group that you want to display.

To Change the Sort Order of the Groups:

Do one of the following:

- Click **View | Group By** and select either **Group Forward** or **Group Backward**.
- Click the **Group** drop-down and select either **Group Forward** or **Group Backward**.

Removing Groups from the File List

To Remove a Group:

Do one of the following:

- Click **View | Group By | None**.
- Click the **Group** drop-down list and select **None**.

Selecting Files in One or More Groups

To Select Files in Groups:

Do one of the following:

- Click the group header to select all of the files in that group.
- Press and hold the **Ctrl** key and click two or more group headers to select all of the files in those groups.

Sorting Files

In Manage mode, you can sort your files according to different file properties to quickly organize your images, find specific files, and create a range of files with similar attributes for easy selection.

To Sort Items in the File List:

1. Click **View | Sort By**, and then select a sort option:
 - **Filename**
 - **Size (KB)**
 - **Image Type**
 - **Modified Date**
 - **Image Properties**
 - **Caption**
 - **Rating**
 - **Tagged**
 - **More** (sort by metadata, EXIF, file properties, image attributes, IPTC information, or multimedia attributes)
2. To set the direction of the sort, click **View | Sort By**, and then select a direction:
 - **Sort Forward**
 - **Sort Backward**



Your sort settings are saved until you change them. For example, if you sort images in the File List pane according to Rating, the images will remain sorted according to Rating until you change the sort settings.

Sorting Files Using Column Headers

You can quickly sort files in Details view mode using column headings.

To Sort Files Using a Column Header:

1. Click a column header. An arrow appears, indicating the sort direction.
2. Click the column header again to change the sort direction.

Custom Sorting Files

You can use custom sorting to customize the order of files in the File List pane. After custom sorting your files, ACDSee Home automatically saves the file order for the selected folder until you change it or delete the custom sort order.

To Customize the Sorting Order of Your Files:

1. Select one or more files.
2. Drag the selected files to a new location in the File List.



To delete a custom sort order, click **View | Sort By**, and then select **Delete Custom Sort**.

Selecting Files

In the File List pane, you can select all of your files and folders at once, select all of the files in the current folder, select only the image files, or clear your selection entirely.

You can also set an option to automatically select new files whenever you add them to the File List. Click **Tools | Options | File List** to set this option.

To Select Your Files or Folders:

- **Click** a thumbnail to select the file.
- **Ctrl + click** to select more than one file.
- **Shift + click** to select a number of files in a row.



Click off to the side in the file list pane to clear your selection.

To Select Your Files or Folders Using the Menu:

1. In Manage mode, click **Edit**.
2. Select one of the following:
 - **Select All**: selects all files and subfolders in the current folder.
 - **Select All Files**: selects all files in the current folder.
 - **Select All Images**: selects all image files in the current folder.
 - **Select Tagged**: selects all tagged image files regardless of their folder.
 - **Select by Rating**: displays a list of ratings, and selects all files currently assigned to the rating you select.
 - **Clear Selection**: clears your selection.
 - **Invert Selection**: selects all files except for your original selections.

Previewing Images

You can preview image, audio, and video files in the Preview pane. By default, the Preview pane displays a thumbnail of the currently selected image or media file. You can resize the pane to adjust

the thumbnail dimensions, and reposition the pane anywhere on your screen. You can set the Preview pane to display highlights of the image's EXIF information for quick reference.

To Open or Close the Preview Pane:

Do one of the following:

- Click **Panes | Preview**.
- Press **Ctrl + Shift + P**.

To Show or Hide What Displays in the Preview Pane:

You can customize the options displayed in the Preview pane when you have an image displaying. Right-click the image in the Preview pane, select **Image and Information**, and then select one of the following:

- **Show Image**: displays only a preview of the image.
- **Show Information**: displays EXIF information about the image. This is called the Information palette.

The Information Palette

The Information palette is located in the bottom left of ACDSee and provides immediate access to the most useful elements of an image's EXIF information. It includes:

- Camera Name and Lens Model
- Dimensions
- File Size
- Exposure Program
- White Balance
- Metering Mode
- Flash
- RAW (will be blank for files that are not RAW)
- ISO
- F-Stop
- Shutter Speed
- Exposure Compensation
- Focal Length



If you are unsure what a certain symbol means, you can hover your mouse over it for a pop-up explanation.

To Customize the Preview Info:

You can customize what information displays at the bottom of the Information palette section of the Preview pane. The date and time that the image was taken is selected by default.

1. Right-click the date and time at the bottom of the Information palette in the Preview pane.
2. Click **Choose Preview Info...**
3. In the Choose Details dialog box, select the item listed under Currently Displayed Details and press the **Remove** button.
4. From the Available Details column, choose an item by checking the checkbox next to it and pressing the **Add** button.
5. Click **OK**.

To Preview Audio or Video Files:

1. Click **Tools | Options | Preview**.
2. Check the **Preview audio and video clips** checkbox.
3. Click **OK**.



The Information palette also displays in View and Edit mode. To turn off the Information palette, deselect **Info Palette** under the View menu in Edit mode, or Panes menu in View mode.

Rotating Images

You can rotate images in Manage and View modes using the Rotate icons in the bottom toolbar.





When you rotate unedited JPEG images, ACDSee performs a lossless rotation, meaning no information is lost.

To Rotate Images:

1. In Manage mode or View mode, select one or more images.
2. Click the **Rotate Left** or **Rotate Right** icon in the bottom toolbar.

Rotate Icons

	Rotate Left	Rotates the image 90° to the left.
	Rotate Right	Rotates the image 90° to the right.












Comparing Images

You can use the Compare Images feature to compare a group of images. The tool highlights both the similarities and the differences in the properties, metadata, and pixel intensity levels of images you select. You can save your preferred images to a new location on your hard drive, or tag images you would like selected in Manage mode, and then delete, move, rename, or alter the images.

To Compare Images:

1. In the File List pane, select the images that you want to compare.
2. Click **Tools | Compare Images...** Up to four images display in the Compare Images Viewer.
3. To change which image displays in the comparison view, do one or more of the following:
 - In the Comparison List, right-click an image and click **Send to Active View** (indicated by a pale box).
 - In the Comparison List, drag an image to a box in the Compare Images Viewer.
 - In the Compare Images Viewer, right-click an image and click **Next Image** or **Previous Image**.
 - In the Compare Images Viewer, right-click an image and click **File | Remove From View** or click the **Remove** icon in the image toolbar.
4. To tag images, do one of the following:
 - In the Comparison List, check the checkbox that is located at the bottom of the image on the right side.
 - In the Compare Images Viewer, right-click an image and click **Tag** or click the **Tag** icon in the image toolbar.
 - Click the **Tag All** button in the bottom left corner to tag all of the images, or click **Untag All** to untag all of the images.
5. To rate images, right-click an image, click **Set Rating**, and then select an appropriate rating.
6. To categorize images, right-click an image, click **Set Categories**, and then select an appropriate category (or create an appropriate category).
7. Click **OK**, located in the bottom right corner.

Compare Images Toolbar

	Previous	Swaps the selected image with the previous image in the Comparison List.
	Next	Swaps the selected image with the next image in the Comparison List.
	Zoom In	Increases the magnification of the selected image.
	Zoom Out	Reduces the magnification of the selected image.
	Zoom menu	<p>Opens a menu of zoom options. Select from the following options:</p> <ul style="list-style-type: none"> • Actual Size: displays the image at its original size. • Fit Image: displays the image at the largest magnification that fits in the Compare Images Viewer. • Fit Width: displays the image to fit between the left and right sides of the Compare Images Viewer. • Fit Height: displays the image to fit between the top and bottom of the Compare Images Viewer. • Zoom Lock: displays all images at the zoom option of the current image. If the zoom is adjusted, the new zoom level is applied to all images that you view. • Zoom To: opens a dialog box where you can select a zoom option.
	Pan Lock	Locks the panned image area, so that when you zoom and pan an image to a specific area, the Compare Images Viewer displays the same area for all images you view.
	Exposure warning	Indicates pixels that may be over or underexposed.
	Properties	<p>Displays properties for each image in the Compare Images Viewer. Click the Metadata Setup button to specify which file properties are displayed.</p> <p>The Compare Images tool displays the file properties in a field below each image. Differences in properties are bolded, while similarities are displayed in regular font.</p>
	Histogram	Displays a histogram for each image in the Compare Images Viewer.
	Metadata Setup	<p>Opens a dialog box where you can select the metadata to display for each image in the Compare Images Viewer (ensure Properties  is toggled to on).</p>















	One Image	Displays one image in the Compare Images Viewer.
	Two Images	Displays two images in the Compare Images Viewer.
	Three Images	Displays three images in the Compare Images Viewer.
	Four Images	Displays four images in the Compare Images Viewer.
	Properties Pane	If one image is displayed, this button opens the Properties, Histogram, Magnifying Glass, and Navigator panes.
	Help	Opens the Help file.

Image Toolbars

Each image in the Compare Images tool has a toolbar located below it. You can use this toolbar to adjust each image individually.

	Save	Opens a dialog box where you can save the image with a different file name and a different file format.
	Previous	Swaps the displayed image with the previous image in the Comparison List.
	Next	Swaps the displayed image with the next image in the Comparison List.
	Zoom In	Increases the magnification of the image.
	Zoom Out	Reduces the magnification of the image.
	Delete	Deletes the image from your hard drive.
	Remove	Removes the image from the Comparison List.
	Tag	Tags the image so that it will remain selected when you close the Compare Images tool.

Gathering Images in an Image Basket

You can use image baskets to gather and hold images and media files from different locations or folders. Once you have placed items in an image basket, you can use any of the tools or features in ACDSee Home to edit, share, or view those files. You can create up to five image baskets and use them simultaneously.

To Open an Image Basket:

In Manage mode, click **Panes | Image Basket | New Image Basket** or press **Ctrl + Shift + 9**. Repeat this step to open up to five image baskets.

To Add Files to an Image Basket:

Do one of the following:

- In the File List pane, select the files you want to add. Drag the items to the Image Basket.
- In the File List pane, right-click selected files and choose **Add to Image Basket** from the context menu. You can also use this method in View mode.
- In the File List pane, select the files you want to add and press **Ctrl + B**. You can also use this method in View mode.



The last image basket that you interacted with is considered the "active" basket. This will be indicated with a star next to the basket's name. The active basket is the one that images will be added to when using the context menu or keyboard shortcut in Manage or View mode.



You can also add images to an image basket by dragging them from Windows Explorer.

To Remove Files from an Image Basket:

In the Image Basket, right-click the files, and select **Remove from Image Basket** or press **Alt + X**. To remove all files, right-click the Image Basket, and then select **Clear Image Basket**.

To Rename an Image Basket:

In the Image Basket, right-click and choose **Rename Image Basket** from the context menu. In the Rename Image Basket dialog, enter a name in the field and press **OK**.

To Delete an Image Basket:

In the Image Basket, right-click and choose **Delete Image Basket** from the context menu or press **Ctrl + Shift + -**. Deleting an image basket will not delete the images within it.

Using the ACDSee Activity Manager

The ACDSee Activity Manager allows you to monitor and manage background activities including:

Queued Activities:

- Import
- Resize
- Convert File Format

! Features that run using the **Activity Manager** are shown in the menu with a + next to them.

Idle Activities:

- Face Detection

Opening the Activity Manager


To open the **Activity Manager** do one of the following in **Manage mode**:

- Click **Panes | Activity Manager**.
- Click the **Activity Manager** icon in the Status bar.

Queued Activities


View your imports and other running activities from the **Queued Activities** section of the **Activity Manager**.

When an **Activity** is queued, it will begin immediately, or may start in the **Queued** state if you already have activities in progress. The bar represents the **Activity** progress, while the number represents the number of images left to scan.



Activities that are currently running can be paused by clicking the **Pause** button.

Activities that are currently paused can be restarted by clicking the **Play** button.

Activities that are either running or paused can be canceled at any time by clicking the **Cross**  button.

Pausing an **Activity** will cause the next **Queued Activity** to start right away, unless **Pause All Queued Activities** has been selected.



Multiple **Queued Activities** can run concurrently with a maximum of 6. The number that can run concurrently depends on your CPU.

When clicking the **Play** button for a **Queued Activity**, one or more running **Activities** will pause, and the **Activity** that was clicked on will immediately jump to the top of the list and begin.

Completed **Activities** can be found in the **History** section where you can view a list of files completed by each **Activity**. For more information see [History](#).



To see a list of options available in **Queued Activities**, click on the gear button to the right side of **Queued Activities**. See [Queued Activities Options](#).

Currently running activities will always be at the top of the list in **Queued Activities**. As these activities are completed and move to **History**, the next **Queued Activity** will move to the top of the list and begin. Paused **Activities** can be dragged and dropped within **Queued Activities** to rearrange the order that they are processed in.



Paused Activities cannot be dragged above any currently running **Activity**.

Preventing Conflicts or Loss of Data

Because activities run in the background, ACDSee Home uses specific methods to prevent file conflicts when multiple activities access the same files.

- If an image is queued for an activity and is taken to **Edit** mode, the image is skipped by the queued activity.
- Multiple activities that modify the same files cannot run at the same time.
- Activities that create new files cannot run alongside other activities on the same folders.
- Commands that read or write files in **Manage**, **View**, or **Media** mode pause activities until the command is complete. Paused activities then resume automatically.
- Options or commands that restart ACDSee Home (such as resetting the layout) are blocked while activities are running.
- Database and licensing commands require you to cancel activities before ACDSee Home restarts.

Notifications



Activity Manager notifications appear in the bottom-right corner of the screen when activities are queued and completed.


- Click **Show** to open the **Activity Manager**.
- Click **Browse** to open a new tab to the folder containing the activity's output files.
- To customize which notifications are muted, go to **Tools | Options... | Activity Manager**.


- Each notification includes a **More Options ...** menu next to the **X**, allowing you to adjust notification settings directly from the notification.
- Notifications will display the activity Status. For more information about Activity Status please see [History](#).

Notification Status

There are 4 possible Notification Statuses:

- **Completed:** If an activity completes successfully, the notification will display **Completed**.
- **Completed with errors:** If an activity completes, but there is an error for any of the files, the notification will display **Completed with errors**.
 If an error occurs in an activity, the notification will always display error, even if files produce a warning, or are skipped.
- **Completed with skipped files:** If an activity completes, but one or more files have been skipped, the notification will display **Completed with skipped files**.
 If a file is skipped by an activity and no error has occurred, the notification will always display as skipped.
- **Completed with warnings:** If an activity completes, but there is a warning for any of the files, the notification will display **Completed with warnings**.

If any activity completes with errors, skipped files, or warnings, a **Caution icon**  will display on the notification.








Idle Activities

When assets are being scanned for **AI Face Detection**, their progress can be viewed within the **Idle Activities** section of the **Activity Manager**. Here, you can see the current status, how many assets are left to be completed, and quickly disable each tool with the switch on the right side.

Idle Activity States:

Idle Activities can be in one of four different states:

Waiting: 	When in the Waiting state, the number of assets remaining will increase as files are added to the queue. This occurs while browsing, cataloging, or importing files.
Scanning: 	When in the Scanning state, the tool is actively detecting Faces, and the remaining number will decrease as files are completed.
Disabled: 	When in the Disabled state, the tool has been manually deactivated and will not run until turned back on.
Completed: 	When in the Completed state, the tool has finished its queued files.


To see a list of options available in **Idle Activities**, click on the gear button  to the right side of **Idle Activities** in the **Activity Manager**. See [Idle Activities Options](#).

History

When a **Queued Activity** has been completed, or an **Advanced Search** has run, it will appear in the **History** section of the **Activity Manager**.



For **Advanced Searches** that have run, click its entry in the **History** to open the **Advanced Search** pane with the criteria preloaded.

 The History section will be cleared automatically when Home is shut down.

For **Queued Activities** that have completed, click the **Details View** button  to view a comprehensive list of assets for each completed **Activity**.

The **Details View** for each History entry shows the following fields:

- **Status:** Status includes 4 possible states: Success, Error, Warning, and Skipped.
 - **Success:** The action has successfully completed.
 - **Error:** The action has completed, but one or more files have not been created/modified due to an error.
 - **Skipped:** The action has completed, but one or more files were skipped due to being in use elsewhere.
 - **Warning:** The action has completed but one or more files have a warning issued.

 Activities that complete with either errors, or files skipped, will display the **Caution icon**  in the **History**.

- **Filename:** Displays the source file's filename.
- **Details:** Displays the outcome of the action.

- **Source:** Displays the source location of the file that was modified.
- **Destination:** Displays the destination location of the file that was modified.

Clearing History


Items in **History** can be cleared either individually, or all at once.

To Clear One Item at a Time:

Click on the **Cross**  to the right side of the item in **History**.

To Clear the Entire History at Once:

Click on the **Clear Activity History**  button on the right side in **History**.



Activity Manager Options:

Click on the gear icon to the right of **Queued** and **Idle Activities** to display the list of available options:

Queued Activities Options:

Pauses or resumes all activities within **Queued Activities**.

Pause/Resume All Queued Activities





Pausing all activities with **Pause All Queued Activities** will disable the **Play** button for each activity until **Resume All Queued Activities** has been enabled.

Clear All Queued Activities

Clears **Queued Activities** of all active or paused activities.

Idle Activities Options:

Disable/Enable AI Face Detection

Click to disable or enable the AI Face Detection tool. AI Face Detection can also be manually disabled or enabled by clicking the switches from on  to off  or vice versa.

Clear AI Face Detection Queue

Removes all items from the AI Face Detection queue.

Cataloging and Managing Files in ACDSee Home

In addition to its browsing, viewing, and editing capabilities, ACDSee Home features integrated management tools you can use to organize and sort your images and media files. These tools include batch functions (tools that can alter or adjust multiple files at the same time), category and rating systems, and a powerful database to hold all of your important image information.

You can use the ACDSee Home batch functions to convert the file format, rotate, resize, rename, and adjust the time stamp or the exposure of a single image, a group of images all at once. With the category, color label, and rating systems, you can create a virtual folder structure, and use it to find related images and media files with a single click.

ACDSee Home displays file properties and image information in an easily accessible Properties pane that you can use to directly add and edit file information, including ACDSee Metadata. You can add an author, description, notes, and keywords to your files, and adjust the category and rating assignments at the same time.

Organizing with the Catalog Pane

The Catalog pane is one of the most useful panes in Manage mode as it provides so many tools for organizing, managing, and finding your files. You can drag files into the categories, ratings, keywords, or color labels of the Catalog pane to assign and quickly organize your files. The Auto Categories section can be used to find files with specific information such as file size, keywords, or shutter speed. The Saved Searches section allows you to create and run custom searches. Special items such as the Image Well display all the images on the computer in one click, or you can click Uncategorized to display only those that are not yet in a category.

To Open the Catalog Pane:

In Manage mode, click **Panes | Catalog**.

The Catalog pane opens on the left, tabbed with the Folders and Calendar panes.

Categories

Categories are an easy way to organize your files into context-related sections. When you assign a file to a category, you do not move the file from its folder or create an extra copy. Your categories can be simple or complex and use any names you choose. There are different icons to use for different

categories to help you identify them at a glance. Once your files are in categories, you can search, sort, group, and find them by category.

One way to assign files to a category is to select and drag one or more files from the file list and drop them onto the category. You can choose colored icons to identify your categories, and cycle through the available icons using the **J** key. A file can belong to multiple categories, but it will only have one icon. For comprehensive categories management, use [the Organize tab of the Properties pane](#).

People

The People group in the Catalog pane will display the names of individuals you have assigned in the [Face Detection Pane in View mode](#). You can select a name to display all of the photos with that individual in it, provided that they have been identified using Face Detection. You can also set Face Search Options which allow you to choose whether to display Assigned Names, Suggested Names, or both Assigned Names and Suggested names using the settings menu (gear icon) in the top right corner of the People group.

To assign names to faces, use [People mode](#).

Keywords

You can use keywords to organize your files into hierarchies. You can create and assign hierarchical keywords [in the Organize tab of the Properties pane](#). You can add keywords to images quickly using drag and drop. You can also manage your keywords in the context menu, by using right-click.

Ratings

You can assign a numerical rating from 1 to 5 to your images and files. Once you have assigned ratings, you can search, sort, and catalog your files based on the ratings, or a combination of ratings, categories, auto categories etc. A file can have only one rating. When a file has a rating, the number appears on top of the thumbnail in the File List pane. Ratings can be managed in [Assigning and Searching Categories and Ratings](#).

Color Labels

You can use color labels to catalog your files. You can use different colors to represent different stages of your workflow. As you review your photos or documents, [you can assign color labels](#) and rename them accordingly.

Auto Categories

Most digital cameras create and embed information about the file as you take a photo. This information is called metadata and can include the name and model of the camera, the file size, shutter speed, camera settings used in the shot and much more. ACDSee Home uses this information to create auto categories. You can [search using auto categories](#) to find images containing that

metadata. You can select one or more auto categories to find files, for example, photos of a certain size, taken by a particular camera. You can also add to this data using the Properties panes.

Advanced Searches

If you find yourself creating the same search criteria frequently, you can save the search to use again later. Search Presets appear at the top of the Advanced Search pane but they also appear in the Catalog pane for you to re-run using a single click on the name or in the white checkbox of the Easy-Select bar.

To Create a New Search Preset from the Catalog Pane:

1. In the Advanced Searches area of the Catalog pane, click the **New Search Preset** button.

The Advanced Search pane opens.

2. Enter your search criteria and then click the **Save** icon to save your preset.

The new search preset appears in the Advanced Searches area on the Catalog pane and in the Search Presets drop-down list of the Advanced Search pane.



Search Presets that are saved with missing information such as blank criteria, will display as a **Search Template** and display in the Catalog pane with a * at the end. **Search Templates** cannot return results, as they are missing information. Instead they can be opened in the Advanced Search pane to add the missing information. For example: If you regularly search for images with **Rating 5**, but want to search a different Keyword each time, a saved **Search Template** could be made with the Rating criteria set and the Keyword criteria to be filled in each time.

Special Items

You can use Special Items to quickly view all of the images in your database and any uncategorized images. Select one of the following items:

- **Image Well:** displays all images cataloged in the ACDSee Home database. If you have a substantial image collection, it may take a few moments to gather all of the information.
- **Videos:** displays all videos cataloged in the ACDSee Home database. This will return any video formats supported by ACDSee. If you have a substantial file collection, it may take a few moments to gather all of the information.
- **Embed Pending:** displays all the files with database data that has changed but has not yet been embedded in the files.
- **Uncategorized:** displays any images cataloged in the database that have not been assigned to a category.
- **No Keywords:** displays any images cataloged in the database that have no ACDSee keywords assigned.
- **Unnamed Faces:** displays all photos in which one or more faces have been detected but not named.

- **Auto-Named Faces:** displays all photos with one or more faces that have been automatically named by ACDSee using facial recognition.



Faces can only be auto named if the [Enable Auto Naming](#) option is enabled.

- **Suggested Names:** displays all photos with suggested names using Face Search. You can use this item to quickly confirm or deny suggestions across your image collection.
- **Tagged:** displays all the tagged images in your file collection.

The ACDSee Home Database and Embedded Data


When you assign a file to a rating, or category, this information is stored in the ACDSee Home database. If you choose to, you can also embed this information in each individual file, making it easier to relocate and share files, or retrieve the information from the file if you need to. In the database, information is always associated with a particular file. If you move or rename files using an application other than ACDSee Home (like Windows Explorer) the link between the file and the ACDSee Home database will be broken. If this happens, and you have embedded the information in each file, you can rebuild the database and retrieve all the information.

You can also use the Properties pane to add information to the ACDSee Home database like captions, keywords and much more. Taking the time to assign categories and add keywords, notes, etc., makes it much easier to find and organize your files. Learn more about [organizing using the Properties Pane](#).



ACDSee uses XMP to embed ACDSee Metadata into each file. Only some file formats and file extensions support XMP. These include GIF, JPEG, DNG, PNG, PSD, TIF, AVIF, and JPEG-XL. In the case of these file formats, the ACDSee Metadata is embedded inside the file and so you can rename or move the file outside of ACDSee and still be able to retrieve the ACDSee Metadata. For formats that currently do not support XMP, including RAW and ABR, the ACDSee Metadata is written to a sidecar file that is stored in the same folder as its file. Because a sidecar file is separate from the file itself, you need to rename or move them together, or you could lose the ACDSee Metadata permanently.

Easy-Select Bars

The Easy-Select bars are the indicators on the left side of the Folders and Catalog panes. They look like . You can use these indicators to select multiple folders or categories, and display their contents in the File List pane. In the Catalog pane you can also use the Easy-Select indicators to select combinations of categories, ratings, auto categories, search presets, and special items. For example, you could display all your photos with a rating of 1 that belonged to the category People.

You can also use the Easy-Select indicators with the Selective Browsing pane (**View | Selective Browsing**).

When you use the Match Any/All buttons and the Easy-Select indicators together, the Catalog pane becomes a powerful search tool for finding unique sets of files.

To Use the Easy-Select Bar:

In the Folders or Catalog pane, select the indicator to the left of each item with contents you want to display. The indicator changes orientation to point to the item you have selected.



If you select a category, rating, or combination that does not have any files that match, the File List displays a message and shows no thumbnails. The quickest way to return to a folder with files is to click the back arrow.

To View Cataloged Files:

Select one or more categories, ratings, auto categories, search presets, or special items. Files assigned to those classifications are displayed in the File List pane.







The Contents bar at the top of the File List pane displays whatever categories or items are currently selected. You can browse through specific categories, ratings, or items within specific folders using the Selective Browsing pane.

Match All Match Any

There are two Match All/ Match Any drop-down lists on the Catalog pane; one at the top of the pane that affects categories and one that affects search presets. You can use the Match All and Match Any options to affect the display of thumbnails in the File List in the following way:

- **Match All:** to be included, a file has to belong to all the categories or searches you select. So the file has to be in both or **all** of the categories or searches before it will display in the File List. Match All is more exclusive. You can use it to limit the number of files that display and narrow a search down.
- **Match Any:** to be included, a file can belong to **any** of the categories or searches you select. So **any** files in the selected categories or searches will display in the File List. Match any is more inclusive.

Catalog Icons

	Category	Identifies files that have been assigned to a category.
	Ratings 1-5	Identifies file ratings.
	New Search preset	Opens the Advanced Search pane so that you can create a new search preset.
	Easy-Select indicator (selected)	Selects the category, rating, auto category, or other item for display in the File List pane.
	Easy-Select indicator (not selected)	Does not select the category, rating, auto category, or other item for display in the File List pane.
	Match Any/All	Controls which images are displayed in the File List pane.



To hide the icons in the Catalog pane, click **Tools | Options**, and then select **Catalog**. Uncheck the **Show Icons** checkbox in the Options dialog box.

Creating Categories

Create and manage a system of categories for your files in the Organize tab of the Properties pane. You can easily customize your category system in a way that makes sense to you.

Select the Organize tab in the [Properties pane](#) to create, rename, delete, and move your categories. You can also access the Categories pane by choosing **Panes | Categories**.

To Create a Category:

- Do one of the following:
 - Right-click a category in the Catalog pane, and then select **New Category**.
 - In Manage mode, click **Edit | Set Categories | New Category**.
- Select one of the following:
 - Create a new, top-level category
 - Create a sub-category within the current selection
- If you are creating a sub-category, select a top-level (or parent) category from the drop-down list. (If you right-clicked a category in the Catalog pane, the new sub-category will be added below that category by default.)
- Type a name for the new category in the **Name** field.
- Click **OK**.



When you create a new top-level category, you can select an icon to help identify the category. The Icon drop-down only appears if the **Show Icons** checkbox is checked on the Catalog page of the Options dialog box. In Manage mode, click **Tools | Options**, and then select **Catalog**.

Manage Categories

To Manage Your Categories:

Select a category in the Catalog pane, and do one of the following:

- To edit the category, right-click the selected category and select **Edit**.
- To delete the category, right-click the selected category and select **Delete**.

In the Categories group in the Catalog pane:

- To move the category, drag it to the new location.

To Delete Categories:

In the Properties pane, located to the right of the File List pane, do one of the following:

- In the Organize tab, right-click on the **Category** you wish to delete, and then select **Delete** from the context menu.
- In the Organize tab, click on the Easy-Select bars to the left of any Categories you wish to delete, then press **Delete Selected Categories**.

In the Catalog pane, located to the left of the File List pane, do one of the following:

- Right-click on the **Category** you wish to delete, and then select **Delete** from the context menu.

To Delete all Unassigned Categories:

Categories that do not have any assets assigned to them can be deleted quickly with the **Delete all Unassigned Categories** option.

- Click **Tools | Metadata | Delete All Unassigned Categories**.

Filtering Categories:

In the Properties pane, categories can be filtered within the **Organize tab** by clicking in the Filter Categories text field and typing any word. The categories displayed will filter dynamically as you type.

Quick Category Sets

If you have a long list of categories, or would like to break your categories up into different events or areas of interest, you can use the Quick Category Sets feature.

To Create Quick Category Sets:

1. First create the categories you want in your set.
2. In the Properties pane, click the Quick Categories drop-down list and select **New Quick Categories Set....**
3. Customize the number of rows and columns for your set by selecting values from the Rows and Columns drop-down menus.
4. Enter your commonly used categories into the entry fields. For sub-categories, use the pipe key. Example: A|B|C.
5. Click the **Save** button.
6. Click **OK**. This category set will be listed in the Quick Category drop-down list.
7. Select one or more files and click a button in the category set. The category will be assigned to the selected files. The button text color will change to indicate that the category is assigned to currently selected files, and will display in italics if assigned to only some (but not all) of the currently selected files.



Make sure the category button name matches the category name in the category tree.

Assigning and Searching Categories and Ratings

You can assign files to a rating, or one or more categories, without moving the file or making an extra copy.



If the Properties pane or Catalog pane is not visible in Manage mode, click **Panes | Properties** or **Panes | Catalog**.




Quickly Assign Ratings in Thumbnail View

The rating number you select can be reflected as a star rating in other applications. Give your favorite shots a high rating, and your least favorite shots a low rating.

To Assign Ratings:

1. Hover over a thumbnail to display the gray box with diagonal line through it.
2. Click the gray box to make your selection.

Example of Hovering Over a Thumbnail to Select a Rating:

1. A screenshot of the ACDSee Photo Studio Home 2026 interface. It shows a photo of a plant with white flowers. In the top right corner, there is a 'JPG' label and a rating bar with numbers 1 through 5. A mouse cursor is hovering over the number 3.
2. A screenshot of the ACDSee Photo Studio Home 2026 interface. It shows the same photo of a plant. The rating bar is now visible, and the number 3 is selected, indicated by a white background and a black outline. A mouse cursor is hovering over the number 3.
3. A screenshot of the ACDSee Photo Studio Home 2026 interface. It shows the same photo of a plant. The rating bar is visible, and the number 3 is selected. A menu icon (three horizontal lines) is visible in the bottom left corner.



Use the keyboard shortcut **Ctrl + 0-5** to quickly rate a file.

Assign and Search Categories and Ratings in the Catalog Pane

The Catalog pane allows you to both assign categories and ratings as well as search them.

To Assign Files to Categories or Ratings in the Catalog Pane:

1. In Manage mode, do one of the following:
 - Drag selected files to a category or rating in the Catalog pane.
 - Drag the category or rating from the Catalog pane to selected files.
 - Select one or more files, then right-click the categories/ratings. Select **Assign items** from the context menu.
 - Right-click the files, and then click **Set Categories** and click the category in the fly out, or click **Set Rating** and click the rating.

2. In View mode, do one of the following:

- Click **Edit | Set Categories** and then click the category to which you want to assign the file.
- Right-click the file, click **Set Categories**, and then click the category to which you want to assign the file.
- Click **Edit | Set Rating** and then click the rating to which you want to assign the file.
- Right-click the file, click **Set Rating**, and then click the rating to which you want to assign the file.
- On the status bar, click the rating icon, and then click a new rating. This icon only appears once a rating is set.

3. If you are comparing images and want to categorize them, do one of the following:

- Right-click one of the files, click **Set Categories**, and then click the category to which you want to assign the file.
- Right-click one of the files, click **Set Rating**, and then click the rating to which you want to assign the file.



Ratings embedded by ACDSee can be seen in other applications supporting xmp:rating and vice versa. To embed metadata into one or more selected files click **Tools | Metadata | Embed ACDSee Metadata | Embed In Selected Files**.

Use the Context Menu (Right-Click) in the Category Tree to Do the Following:

- Assign Items
- Unassign Items
- Create New Category
- Search
- Cut
- Copy
- Paste
- Delete
- Edit Category

To Search a Category or Rating in the Catalog Pane:

Click the Category name or Rating number to display all corresponding files in the File List pane.

Assign Categories and Ratings in the Properties Pane

The Properties pane provides another way to assign categories and ratings.

To Assign Files to Ratings in the Properties Pane:

1. In the File List pane, select the files you want to assign a rating.
2. In the Properties pane, select the **Metadata** tab.
3. Click the rating you want these files to have from the numbers listed at the top of the Properties pane.


To Assign Files to Categories in the Properties Pane:

1. In the File List pane, select the files you want to assign a rating.
2. In the Properties pane, select the **Organize** tab.
3. Find the category you want these files to have from your Categories list and:
 - Check the boxes you wish to apply.
 - Click the Easy-Select bar on the left side of a Category to select it. Multiple Easy-Select bars can be selected at the same time. Press **Assign Selected Categories**.



Assign files quickly with a category sets button. See [Create Quick Category Sets](#).

Selecting All Categories:


Easily select all available categories at once with the **Select All Categories** button .

Unassigning Categories or Ratings from Files

You can remove a file from a category or rating without moving or deleting the original file, or affecting any other files assigned to that classification.

To Unassign Categories or Ratings from Files:

1. In the File List pane, select the files you want to unassign the categories or ratings from.
2. Do one of the following:
 - Right-click a selected file, and then click **Set Rating | Clear Rating**.
 - Right-click a selected file, click **Set Categories**, and then click the name of the category from which you want to remove the file, or to remove all categories, click **Uncategorize All Selected Items**.
 - In the **Properties pane**, within the **Organize tab**, find the categories you wish to unassign and uncheck the checkboxes.
 - Click the Easy-Select bars to the left of each **Category** you wish to **unassign**, and press **Unassign Selected**.
 - Uncheck a checkbox for a category or a radio button for a rating in the Catalog pane.

- Right-click a category or rating in the Catalog pane, and then click **Unassign Items**.
- Click the **Unassign All Categories** button  found in the **Properties Pane** to remove all categories from your currently selected images.



You can reset ratings in the Properties pane by right-clicking on the rating.

Clear All Selected Categories:

Easily clear all categories currently selected with the **Clear Selection** button .

Assigning Color Labels

Color labels are useful for naming and quickly identifying your processing plans for your images and documents. Different colors can be used to represent different stages of your workflow. For example, as you review your photos or documents you can quickly label files to upload, print, reject, review, or sharpen, or any other term that matches your workflow needs. Once your files have been labeled, you can click a color label in the Catalog pane to instantly display all of the files assigned to that label.

You can also use color labels in combination with the Group by, or Filter By features to refine your list. Color labels, like tagging, categories, and ratings, are a way to set aside, organize, and group your photos or documents without moving them into different folders.




If the Properties pane or Catalog pane is not visible in Manage mode, click **Panes | Properties** or **Panes | Catalog**.

Create a Color Label Set

Begin by creating a label set so you can quickly select and assign specified labels. Once you have a label set in place, you can assign your images or documents to the appropriate labels corresponding to your workflow.

To Create a Color Label Set:


1. In the Catalog pane, click the Labels settings button  and select **Edit Label Sets**.
2. Enter names for your labels and click the Save icon.
3. Click **Save As** from the Save Label Set dialog box.
4. Enter a name for your new label set.
5. Click **OK**.


Once you have created color label sets, you can access them from the Catalog pane by clicking the Labels settings button and selecting from the drop-down list. Before assigning a color label, make sure the intended label set is active. The active label set name is shown in brackets in the label header.

Assign Color Labels


You can assign Color Labels to files by using the following:

- Hover icons in thumbnail view
- Catalog pane
- Properties pane
- Edit menu in Manage and View mode
- Context menu
- Keyboard shortcuts


 ACDSee uses XMP to embed ACDSee Metadata into each file. Only some file formats and file extensions support XMP. These include GIF, JPEG, DNG, PNG, PSD, TIF, AVIF, and JPEG-XL. In the case of these file formats, the ACDSee Metadata is embedded inside the file and so you can rename or move the file outside of ACDSee and still be able to retrieve the ACDSee Metadata. For formats that currently do not support XMP, including RAW and ABR, the ACDSee Metadata is written to a sidecar file that is stored in the same folder as its file. Because a sidecar file is separate from the file itself, you need to rename or move them together, or you could lose the ACDSee Metadata permanently.


 You can also set labels from the status bar in View and Edit mode.

To Assign a Color Label Using the Label Line Hover Icon in Thumbnail View:

1. Hover over a thumbnail to display the gray label icon. 
2. Click the gray label icon to make your selection.

Example of Hovering Over a Thumbnail to Click and Select a Color Label:





Use the overlay icon on one of a number of selected files or images to assign the label to all.

To Assign a Color Label to a File Using the Catalog Pane:

1. In Manage mode, do one of the following:
 - Drag selected files to a color label in the Catalog pane.
 - Drag the color label from the Catalog pane to selected files.

To Assign Files to Color Labels in the Properties Pane:

1. In the File List pane, select the files you want to assign a color rating.
2. In the Properties pane, select the color label from the boxes along the top.

To Assign Color Labels Using the Edit Menu in Manage and View Mode:

- Click **Edit** | **Set Label** and then select a color.

To Assign Color Labels with the Context Menu:

- Right-click the file, click **Set Label**, then select a label name.

To Assign Color Labels Using Keyboard Shortcuts:

- Keyboard shortcuts are available for the five color labels, plus Alt-0 to clear the label (exactly the same as ratings, except Alt is used instead of Ctrl)



Search Files Assigned to a Label

To Search All Files in the Database Assigned to a Label:

- Click the color label in the Catalog pane to display all corresponding files in the File List pane.
- Use the Advanced Search pane.
- Use Quick Search.

To Search All Files in the File List Assigned to a Label:

Click the **Filter** drop-down above the File List pane and select a label name. All files assigned to that label in the current file list will be selected.

To Select All Files in the File List Assigned to a Label:

Use Alt-1 through Alt-5 for the five colors, plus Alt-0 to clear the label, (exactly the same as ratings, except it uses Alt instead of Ctrl).

Removing Color Labels and Color Label Sets

To Remove a Color Label from a File:


1. In the File List pane, select one or more files you want to remove a label from.
2. Do one of the following:
 - Right-click a selected file, and then click **Set Label | Clear Label**.
 - In the Properties pane, click the gray unlabeled icon.
 - In the Properties pane, right-click on the color label.

To Delete a Label Set:

1. In the Catalog pane, click the Labels settings button and select **Edit Label Sets**.
2. Select the set you want to delete from the Labels Sets drop-down list.
3. Click the delete button.

Creating Collections

Collections is a powerful grouping and search query tool. You can use the Collections pane to group accumulated photos based on a common variable, such as the camera used, location, or size. You could also use Collections to group photos for sorting, processing, sharing, and much more.



To Create a Collection:

1. In Manage mode, choose **Panes | Collection**. The Collections pane will appear tabbed in the Folders pane.
2. In the Collections pane, right-click and select **Create Collection...** from the context menu.
3. In the Create Collection dialog box, configure the options as described below.
4. Press the **Create** button.

Create Collection Dialog Box Options

Name	
Name	Enter a name for your collection.
Location	
Inside a Collection Set	Check this checkbox if you would like to place this collection inside of another previously-created collection set, thereby developing a hierarchy. Choose the collection set you would like to add your image to from the drop-down menu.
Options	
Include selected photos	Check this checkbox to include any currently selected photos in the collection.
Set as target collection	Check this checkbox to designate this collection as the target collection for images you will add photos to. You will be able to quickly send images directly to this collection by selecting images and pressing Ctrl + Alt + C . To customize the keyboard shortcut, see Customizing Keyboard Shortcuts .


To Add Photos to a Collection:

Do one of the following:

- In the File List pane, select the images before using the Create Collection command described above. Then check the **Include selected photos** checkbox inside the Create Collection dialog box.
- In the File List pane, right-click the images and choose **Collections | Add to | [name of the collection]**.
- Drag and drop the images from the File List pane to the collection inside the Collections pane.
- Select the image in the File List pane. In the Organize tab of the Properties pane, in the Collections group, check the checkbox next to the collection.

To Set a Collection as Your Target Collection:

You can set a specific collection as the target collection, allowing you to quickly add images to it using a keyboard shortcut. A target collection will display a blue circle icon next to it in the Collections pane.

 You cannot set a smart collection as a target.

Do one of the following:

- When creating a collection, check the **Set as target collection** checkbox in the Create Collection dialog box.

- Right-click a collection in the Collections pane and choose **Set as Target Collection**.

To Add Images to Target Collections:

Select the image and press the **Ctrl + Alt + C** key.



You can customize this keyboard shortcut. See [Customizing Keyboard Shortcuts](#).

To Search for Collections:

You can search for collections, collection sets, and smart collections in the Filter Collections field at the top of the Collections pane.

- Enter the name, (or portion of the name), of the collection, smart collection, or collection set you are looking for. If the collection you are searching for is part of a collection set, the search will return the root collection set if one of the sub-collections contains the text you entered in the Filter Collections field.

To Remove an Image from a Collection:

1. Select the collection.
2. Right-click the image and choose **Collections | Remove from Selected Collection**.



This will only remove the image from the collection and will not delete the image.



You can remove multiple images from a collection at once by selecting them all and then right-clicking and choosing **Collections | Remove from Selected Collection**.

To Remove an Image from All Collections:

To remove an image from all collections, right-click the image and choose **Collections | Remove from all collections**.



This will only remove the image from all collections and will not delete the image.



You can remove multiple images from all collections at once by selecting them all and then right-clicking and choosing **Collections | Remove from all collections**.

Collections Sets

You can create a collection set and add other collection folders inside. You can use this method to create a hierarchy for further organization. You cannot add images to collection sets themselves. You

can only add images to folders (collections) inside of collection sets. Selecting the root of a collection set will display all of the images in all of the collections inside of the root.

To Create a Collection Set:

1. In the Collections pane, right-click and select **Create Collection Set...** from the context menu.
2. In the Create Collection Set dialog box, enter a name for your collection set.
3. Check the **Inside a Collection Set** checkbox if you would like to add your collection set inside of another collection set. Select the collection set from the drop-down menu.
4. Click **Create**.

To Add Collections to Collection Sets:

Do one of the following:

- Check the Inside a Collection Set checkbox while creating a collection inside the Create Collection dialog box. Select the collection set from the drop-down menu.
- In the Collections pane, drag and drop the collection from the root level to the collection set.

Smart Collections

Smart collections are collections with queries built into them based on search criteria you specify. These search queries get saved to the database. When you catalog new images in the future, those that fit the criteria of your search query will automatically show up in your smart collection. You can also create a search query to locate files based on the date they were cataloged.

To Create a Smart Collection and Add Search Criteria to Your Query:

1. In the Collections pane, right-click and select **Create Smart Collection...** from the context menu.
2. In the Create Smart Collection dialog box, configure the options as described below.
3. Press the **OK** button.

Create Smart Collection Dialog Box Options

Name	Enter a name for your smart collection.	
	It is recommended that you give your smart collection a name reflective of the search query assigned to it. This will save you the time of having to open it to find out what it contains.	
Location	Inside a Collection Set	Check this checkbox if you would like to place this collection inside of another previously-created collection set, thereby developing a hierarchy. Select the collection set you would like to add your smart collection to from the drop-down menu.
Match	<p>Press the Add button to select search criteria for your query. In the Add Search Criteria dialog box, choose criteria by clicking the plus + signs to expand the tree and check/uncheck the checkboxes on and off to select your properties. Press OK. Your chosen criteria will appear in the Match field box. Refine each item by clicking the underlined variables and selecting an option from the drop-down, or entering a number into the field.</p> <p>For example, if you chose Size as your search criteria, click "is" and select "is not", "is less than", "is less than or equal to", "is greater than", "is greater than or equal to", or "is between". Then click the "0" and enter the size value.</p>	

To Remove Criteria from Your Search Query:

Select the criteria from the Match field and select **Remove**.

To Edit Your Search Query:

1. Right-click your smart collection in the Collections pane and choose **Edit**.
2. In the Edit Smart Collection dialog box, add and remove search criteria as described above.
3. Click **OK**.

Using the Properties Pane

The Properties pane displays all the metadata for your files. It also displays file properties such as file size, creation date, and read-only or hidden status. You can use the Properties pane to add, change,

or delete the metadata for image and media files.

The Properties pane is open in Manage mode on the right of the File List pane by default. The Properties pane is available in all modes except 365 mode, People mode, and Dashboard mode.

To Open the Properties Pane in Any Mode:

Click **Panes | Properties**.



The Metadata panel offers adjustable width for metadata fields. Simply hover between a corresponding label and field to display the double arrow cursor. Click and drag to adjust width. Double-click to toggle between the width of the longest label in the group or the longest label in the pane.

Properties Pane Areas

The Properties pane is divided into 3 tabs: Metadata tab, Organize tab, and File tab.



Use the overlay icons, which appear as you hover over a thumbnail, to tag, rate and add color labels to your images. Alternatively, you can display these settings in the Properties pane by clicking **Tools | Options | Properties Pane** and selecting **Show Tagged, Rating, and Color Labels**.

Metadata Tab

The Metadata tab displays the rating, category, IPTC, EXIF, and ACDSee Metadata stored with a photo. The ACDSee Metadata fields are available for you to enter the caption for your photographs as well as date, author, and notes. The keywords field is display-only and can be entered in the Organize tab. The label field can be entered here or selected from the Labels section in the Catalog pane. IPTC information is automatically embedded into your image, while ACDSee Metadata is not embedded in your files, but instead is held in the database. ACDSee Metadata can be embedded into all your files (or just selected ones) by clicking the **Tools | Metadata | Embed ACDSee Metadata** command.

The IPTC data fields provide a standard means for entering and storing information about your photographs such as description, creator, and copyright information. ACDSee supports fields defined in IPTC Core 1.1.

The EXIF data fields hold information captured by your camera such as shutter speed, camera model, and GPS information.

Certain EXIF fields are no longer visible by default. The EXIF Artist, Copyright, Image Description, and Date/Time Original fields are automatically modified when their matching IPTC fields are modified, (see table below). This change reflects the recommendations of the Metadata Working Group (MWG). If you need to have these fields visible in the EXIF section you can adjust your settings by clicking **Tools | Options | Properties Pane** and clicking the **Manage Metadata Views** button.

Matching IPTC and EXIF Fields

IPTC		EXIF
Description	writes to	Image Description
Creator	writes to	Artist
Copyright Notice	writes to	Copyright
Date Created	writes to	Date/Time Original



When ACDSee parses metadata from a file, the content of the field is displayed without mapping.

Organize Tab

The Organize tab displays four groups of useful, quick access tools: ACDSee Metadata, Categories, Collections, and Keywords. Categories, Keywords, and Collections can be viewed in a file tree format within the Organize tab. Right-clicking on any categories, keywords, or collections, will allow you to add or remove them as you see fit. You can create category and keyword sets to quickly categorize your files. Use the category, keyword, and collection trees to create a hierarchy to easily organize your files in a way that holds meaning for you.

- **ACDSee Metadata:** Update your important ACDSee Metadata information from within the Organize tab, such as **Caption**, **Database Date**, **Imported Date**, **Author**, and **Notes**. ACDSee Metadata can also be updated on the Metadata tab.
- **Categories:** View, filter, and manage categories and quick categories associated with your selected files. For more information see [Creating Categories](#).
- **Collections:** View and access collections associated with your selected files. For more information see [Creating Collections](#).
- **Keywords:** View, filter, and manage keywords associated with your selected files. For more information see [Creating and Assigning Hierarchical Keywords](#).

File Tab


The File tab displays detailed file information and image attributes for a selected file or files. You can set or change the Read-Only and Hidden properties of a file or folder, and view a summary of any EXIF information contained in a file.

Embedding ACDSee Metadata into Files



If you have metadata in your files and they are copied, moved, or renamed, outside of ACDSee, the link between the file and the database will be broken, but you can rebuild the


 database using the embedded data in the file.

 ACDSee uses XMP to embed ACDSee Metadata into each file. Only some file formats and file extensions support XMP. These include GIF, JPEG, DNG, PNG, PSD, TIF, AVIF, and JPEG-XL. In the case of these file formats, the ACDSee Metadata is embedded inside the file and so you can rename or move the file outside of ACDSee and still be able to retrieve the ACDSee Metadata. For formats that currently do not support XMP, including RAW and ABR, the ACDSee Metadata is written to a sidecar file that is stored in the same folder as its file. Because a sidecar file is separate from the file itself, you need to rename or move them together, or you could lose the ACDSee Metadata permanently.

Browsing and Cataloging with Auto Advance

You can use Auto Advance to quickly move through your images while adding tags, ratings, labels, categories, or keywords. You can use Auto Advance in Manage and View mode.

To Turn on Auto Advance in Manage Mode:

At the bottom of the File List toolbar, toggle the **Auto Advance** button or press **Ctrl + Q**. 

To Use Auto Advance:

When Auto Advance is enabled, adding (or clearing) a tag, rating, color label, keyword, or category will advance the selection to the next image in the folder, allowing you to continue adding metadata. This is particularly useful when paired with keyboard shortcuts, as you can organize entire folders without moving your hands from the keyboard.

To select which types of applied metadata will trigger Auto Advance, see [Setting the Auto Advance Options](#).

 Keywords and Categories are disabled by default.

Manage Mode

In Manage mode, using the keys on the numpad, apply the following keyboard shortcuts to make the most out of Auto Advance:

Turn on the numpad by pressing the Num Lock key before utilizing any of the following keyboard shortcuts.

/	Tag
*	Purple Color Label
9	Blue Color Label
8	Green Color Label
7	Yellow Color Label
6	Red Color Label
5	Rating of 5
4	Rating of 4
3	Rating of 3
2	Rating of 2
1	Rating of 1
0	Remove Rating
+	Next
-	Previous
.	Removes Color Label.



If the Num Lock key has not been activated, this will act as the Delete button.

You can also [customize keyboard shortcuts](#).

Keywords and Categories

You can streamline the process of adding keywords and categories to your images by combining customized keyboard shortcuts and Auto Advance.

Keywords

In the Properties pane, on the Metadata tab, in the IPTC group, you can add keywords to the Keyword field, press **ENTER**, and Auto Advance will move to the next image. You can also use the same method in the Keywords field on the Organize tab of the Properties pane. In both locations, you can add

multiple keywords at once, separating them with commas. You can continue the process for all images without moving your hands from the keyboard.

Categories

In the Properties pane, on the Organize tab, expand the Categories group. Add categories to images by checking the checkbox of your desired category. Or do one of the following:

- Right-click the image, and choose **Set Categories** | **[your desired category]** from the context menu.
- Choose **Edit** | **Set Categories** | **[your desired category]**.

Use any of these methods and Auto Advance will move to the next image.

To utilize this same type of convenience in all IPTC fields, see [To Use Keyboard Shortcuts to Enter Metadata into the Same Field of Multiple Photos](#).

View Mode

To Turn on Auto Advance in View Mode:

In the Bottom toolbar, toggle the **Auto Advance** button or press **Ctrl + Q**. 

To Use Auto Advance in View Mode:

1. Choose **Panes** | **Properties**.
2. Add ratings, color labels, tags, categories, or keywords in the Properties pane and Auto Advance will advance it to the next image in the Filmstrip, allowing you to continue adding metadata.

In View mode, use the following keyboard shortcuts to navigate your folder:

Home	Selects the first image in the folder.
End	Selects the last image in the folder.
Page Down	Next
Page Up	Previous

Using the Map Pane

Use the Map pane to add photo locations from anywhere in the world to your photos. You can then recall and view that information for reference at any time. Use the map to select groups of files for further workflow steps, and select photos for display in View mode.

The location of files displayed in the Map pane is based on the latitude and longitude information in the file properties. If you have a camera with geotagging capabilities, the geographic location is automatically conveyed visually on the map. You can also add map coordinates to files by dragging them directly onto the map and pressing the **Save All** button.

Geotagged images are indicated on the map with pins. You can click a pin on the map to select files within a geographic location for viewing or processing. If your geotagged image pin is not displayed on the map, try using the keyboard shortcut **F5** to refresh the map.



The following file formats can be added to the map: JPG, TIFF, RAW, DNG, and PNG.



ACDSee automatically adds file information, including geographical tags, to the database as you browse. However, if you have a large number of files, you may want to catalog those files first to speed up the loading time for the pins on the map. To catalog your files, click **Tools | Database | Catalog Files**.

To Open the Map Pane:

In Manage mode, click **Panes | Map (Ctrl + Shift + M)**.

The Map pane appears above the File List pane in Manage mode by default. You can drag the Map title bar to a new location and float the pane or dock it in another position like the other movable panes in ACDSee.



You can toggle the Map on and off with the keyboard shortcut **Ctrl + Shift + M** in Manage mode.

To Add Files to the Map by Dragging:

1. In Manage mode, drag one or more files onto the map.
2. Click **Save All** in the top left corner of the map.



Ideally images should be geotagged prior to processing. If an image is geotagged after it has been edited and the Restore to Original command is used, then the geotag will be lost.

To Delete a Pinned Location on the Map:

Right-click the geotagged image thumbnail and select **Map | Remove from Map**.

To View a Geotagged Image on the Map:

Right-click the geotagged image thumbnail and select **Map | View on Map**.

To Find a Location:

To find a specific location, enter a place or landmark into the **Search for Location** field at the top right of the Map pane.

To Set Default Location, Zoom, and Map Type:

1. Pan to your preferred location on the map, then adjust the zoom-level and select your preferred map type (Map, Satellite, or Terrain).
2. Click **Tools | Map | Set default map location**.



Note: the map reflects the current File list. If the File list has images mapped to a different location from your default setting, then that location will be displayed.



To pan and zoom the map to a specific location, enter the location into the Map search field and press **Enter**.

Reverse Geocoding:

The Reverse Geocoding command allows you to save location information into certain IPTC fields. These include: Country, Country Code, State/Province, and Location.

1. In Manage mode, drag one or more files onto the map.
2. Click **Save All** in the top left corner of the map.
3. Press the **Reverse Geocode** button to preview the location information.
4. Click **Save** to save this information into the IPTC fields of the selected images.



If images with multiple different locations are selected, only one of those locations will be used to do the reverse lookup.

Using the Map Pane to Further Your Workflow

With the images from a particular location all selected, here are a few possible workflow options:

- Enter Edit mode to process this selection together.
- Use the **Batch** tool to apply the same settings on photos from the same location.
- Click **Slideshow** to view and present a slideshow of the photos from this location.
- **Send** photos from this location via email.



If a geotagged image does not display, try using the keyboard shortcut **F5** to refresh the map.

Pin Legend



Indicates geotagged location.



Indicates more than one geotagged location in this area. (Zoom in to see locations)



Indicates selected geotagged location.



A dot on a pin of any color indicates unsaved image location.

Creating and Assigning Hierarchical Keywords

You can add keywords to your files, and build a hierarchy from those keywords. These groups are maintained in the keyword tree. Select the Organize tab in the [Properties](#) pane to create, rename, delete, and move your keywords.

You can also access the keywords pane by choosing **Panes | Keywords**.



You can view all images assigned to specific keywords by clicking specific keywords in the Keywords group in the Catalog pane.

Creating Keywords

Creating New Keywords:

In the Properties pane, located to the right of the File List pane, do one of the following:

- In the Organize tab, at the bottom of the Keyword group, right-click **Keywords**, and then select **New Keyword** from the context menu.
- Type a keyword into the field at the top of the Keyword group and press **Enter**.

Assigning Keywords to Files:

- Select one or more files, then check the boxes next to the appropriate keywords you wish to apply.
- Select one or more files, then click the Easy-Select bar on the left side of a **Keyword** to select it. Multiple **Easy-Select bars** can be selected at the same time. Press **Assign Selected Keywords**.
- Select one or more files, then right-click the keyword. Select **Assign items** from the context menu.
- Select one or more files, then drag them onto the keyword.
- Select one or more files, then select a keyword from the [Quick Keywords](#) set. The keyword will be assigned to your file and also added to the tree.

In the Keywords group in the Catalog pane, you can:

- Select one or more files, then drag the keyword from the tree onto them.

To Establish a Hierarchy, Do One of the Following:

- In the keyword field, type the lesser or more specific keyword, followed by the less than symbol, followed by the greater or more general keyword.


Example:

1. **Owl < Bird**

or

2. **Madrid < Spain < Europe**

- Right-click an existing keyword, then select **New Keyword**. The new keyword will automatically become a child to the existing keyword.

 When assigning multiple keywords to a file, it is important to note that separating keywords with commas will not generate a hierarchy.

Managing Keywords

To Manage Your Keywords:


Select a keyword in the Organize tab, and do one of the following:

- Right-click the selected keyword and choose **Unassign Item**.
- Click on the Easy-Select bars to the left of any keywords you wish to **unassign**, then press **Unassign Selected Keywords**.
- Click off the **checkbox** for any currently assigned keyword to **unassign** it.
- To edit the keyword, right-click the selected keyword and choose **Edit**.
- To delete the keyword, right-click the selected keyword and choose **Delete**.
- To duplicate a keyword, right-click the selected keyword and choose **Copy**, then **Paste** where desired.


In the Keywords group in the Catalog pane, you can do any of the management actions above, as well as:


- To edit the keyword tree, click and drag the keyword to other parts of the tree.

To Unassign All Keywords:

You can unassign all **Keywords** assigned to your currently selected images by pressing **Unassign All Keywords**  in the bottom-right of the **Keywords** section.

Selecting All Keywords and Clearing Selections:

All keywords can be selected at once by pressing **Select All Keywords** .

All keywords can be cleared at once by pressing **Clear Selection** .

To Delete Keywords:

In the Properties pane, located to the right of the File List pane, do one of the following:

- In the Organize tab, at the bottom of the Keyword group, right-click on the **Keyword** you wish to delete, and then select **Delete** from the context menu.
- In the Organize tab, click on the Easy-Select bars to the left of any keywords you wish to delete, then press **Delete Selected Keywords**.

In the Catalog pane, located to the left of the File List pane, perform the following:

- Right-click on the **Keyword** you wish to delete, and then select **Delete** from the context menu.

To Delete all Unassigned Keywords:

Keywords that do not have any assets assigned to them can be deleted quickly with the **Delete all Unassigned Keywords** option.

- Click **Tools | Metadata | Delete All Unassigned Keywords**.

To Filter Keywords:

In the Properties pane, keywords can be filtered within the **Organize tab** by clicking in the Filter Keywords text field and typing any word. The keywords displayed will filter dynamically as you type.

Creating Quick Keywords

You can use Quick Keywords to keep organized and to streamline your workflow by creating a group of related keywords that hold an association for you. This is ideal for keywords you would like to be easily accessible, rather than buried in the hierarchical tree. You can create multiple groups and choose between them based on the photos you are viewing at the time. ACDSee comes pre-loaded with a variety of usable sample Quick Keywords sets. You can also add these keywords to your tree.

Example:

Italy

Florence	Venice	Lake Como
Rome	Milan	Verona
Genoa	Bologna	Naples

To Assign a Keyword from Quick Keywords:

Select one or more files, then click the keyword.

To Create Quick Keywords Sets:

1. On the Organize tab, in the Keywords group, select **New Quick Keywords Set...** from the drop-down menu. The Quick Keywords dialog box opens.
2. Customize the number of rows and columns for your set by selecting values from the Rows and Columns drop-down menus.
3. Enter up to 250 associated or commonly-used keywords in the open fields. To create a hierarchy within a field, use the pipe key. Example: A|B|C.
4. Click the **OK** button.
5. In the New Preset dialog, enter a name for your set. Click **OK**.
6. Apply keywords from your set by selecting a file and clicking the applicable keyword from the Quick Keywords Table. The keyword will be added to the tree. If you specified a hierarchy in the keyword set, the parent keyword will appear in the tree with the child under it. The text of the keywords in the table will change color to indicate that the keyword is assigned to the currently selected files, and will display in italics if assigned to only some (but not all) of the currently selected files.



Quick Keyword sets are saved in the Presets folder under ACDSee in your AppData folder, which you can find using the following path: C:\Users\<Your Name>\AppData\Local\ACD Systems\Presets

Importing and Exporting Keywords

You can import keywords into ACDSee from other users. You can also share your keywords by exporting them. Keywords are imported and exported as .txt files.



You can import Adobe® Lightroom® keywords.

To Export Keywords:

1. Choose **Tools | Metadata | Export Keywords...**
2. Browse to the location of your keywords file.
3. Enter a name for your keywords file.
4. Press **Save**.

To Import Keywords:

1. Choose **Tools | Metadata | Import Keywords...**
2. Browse to the location of your keywords file.

3. Select your file and press **Open**. The keywords within your file will be loaded into the ACDSee keywords tree and listed alphabetically. Conflicting keywords will be merged.

Copying and Moving Files

You can use the Copy To Folder and Move To Folder commands to relocate files and folders on your hard drive, and specify how to handle overwriting existing files. You can also select from a list of previously accessed folders to save time looking through your directory structure.



When you use ACDSee Home to relocate your files, by default any ACDSee Metadata associated with those files is copied to the new location. However, if you do not want to copy the associated files, clear the **Include related files for non-RAW images** checkbox.



When you do NOT use ACDSee Home to move or copy your files, you break the link to any database information you have added to those files. This is because ACDSee Home cannot track the files. You will lose important categorizing and other database information. You can fix this by clicking **Change Binding** and rebinding the database. If you have embedded the database information in the files themselves, you can also retrieve this information using **Tools | Database | Catalog Files**.



ACDSee uses XMP to embed ACDSee Metadata into each file. Only some file formats and file extensions support XMP. These include GIF, JPEG, DNG, PNG, PSD, TIF, AVIF, and JPEG-XL. In the case of these file formats, the ACDSee Metadata is embedded inside the file and so you can rename or move the file outside of ACDSee and still be able to retrieve the ACDSee Metadata. For formats that currently do not support XMP, including RAW and ABR, the ACDSee Metadata is written to a sidecar file that is stored in the same folder as its file. Because a sidecar file is separate from the file itself, you need to rename or move them together, or you could lose the ACDSee Metadata permanently.

To Copy or Move Files:

1. Do one of the following:
 - In the File List pane, select one or more files, and then click **Edit | Copy To Folder** or **Move To Folder**.
 - While viewing an image or media file in View mode, click **Edit | Copy To Folder** or **Move To Folder**.
2. In the Copy To Folder or Move To Folder dialog box, do one of the following:
 - Select the **Folders** tab, and locate the folder on your hard drive where you want to place the files.

- Select the **History** tab, and select a folder from the list of recently-accessed folders.
 - Select **Create Folder** and enter the name of a new folder.
3. In the **Overwriting duplicate files** drop-down list, select one of the following options to specify how ACDSee Home should handle overwriting files:
 - **Ask**: prompts you for confirmation when overwriting a file.
 - **Rename**: prompts you to rename a file.
 - **Replace**: overwrites any file with the same file name and extension.
 - **Skip**: cancels the operation if there is a file with the same file name and extension.
 4. Click **OK**.

Copying Images to the Clipboard

You can copy an image to the Clipboard and then paste it into another application. Using the Copy Image command transfers only the image data to the Clipboard: no EXIF, IPTC or metadata information is retained.

To Copy an Image:

1. In Manage mode or View mode, select the image file you want to copy.
2. Click **Edit | Copy Image**, right-click on the image and select **Copy**, or press **Ctrl + Insert**.
3. Paste the image into your other application.

To Copy an Image as a File Path:

1. In Manage mode or View mode, select the image file you want to copy the file path for.
2. Right-click on the image and select **Copy as Path**.
3. Paste the image file path in its desired location.

Pasting Files and Folders

You can cut or copy files to the Clipboard, and then paste them into another folder without losing your ACDSee Metadata.

To Cut and Paste Files:

1. In Manage mode, in the File List or Folders pane, select one or more files or folders.
2. Click **Edit | Copy** or **Cut**.


3. In the Folders pane, browse to a new location.
4. Click **Edit | Paste** to place the files or folders into the new location.

Replacing or Overwriting Files

When copying or moving files from one location to another, a file name collision occurs if a file already exists in the destination folder with the same file name and extension as a file you are relocating. In ACDSee, you can view both of the files involved in the Confirm File Replace dialog box. If the files involved are image files, ACDSee Home displays thumbnail previews of both files, and provides options to replace the existing file, rename, delete, or skip the file you are moving, or cancel the operation entirely.

To Use the Confirm File Replace Dialog Box:

1. If you are moving a number of files and want to handle all potential file name collisions in the same manner, check the **Apply to all** checkbox.
2. To help determine any differences between the two files, use the toolbar between the two preview fields to shrink or enlarge the size of the previews.
3. Do one of the following:
 - To replace the destination file with the source file, click **Replace**.
 - To rename the new file before moving it into the destination folder, type a new name for the file in the **Rename to** field, and then click **Rename**.
 - To skip this file, and leave both files intact, click **Skip**.
 - To delete either the destination or source file, click **Delete** below the file you want to remove from your hard drive.
 - To cancel the operation and not move or copy any more files, click **Cancel**.

 In the Confirm File Replace dialog box, **destination file** refers to the file that exists in the target folder, and **source file** refers to the file you are moving or copying.

Renaming a File or Folder

You can rename a file or folder on your hard drive in the Folders and File List panes.

To Rename a File or Folder:

1. In Manage mode, in the File List or Folders pane, select the item you want to rename.
2. Click **Edit | Rename**.

3. Without removing or changing the file name extension, such as “.jpg”, type a new name for the file.
4. Press **Enter**.



You can rename multiple files at the same time using the [Batch Rename](#) tool.

Storing Files in Private Folders

You can store confidential files in private, secure folders. When you add a file to a private folder, it will disappear from its original location. Private folders are password-protected and you can only view the files in them in ACDSee.

When you add files to a private folder, all information related to the file is deleted from the database. This means that though the file can be restored, database information cannot. The only way to preserve database information is to back up or export the database before you add files to a private folder. There is also no way to restore images from a private folder if you forget the password, so make sure it is memorable.

To Open the Private Folder Pane:

In Manage mode, click **Panes | Private Folder**.

To Create a Private Folder:

1. Close any open private folders.
2. Right-click the private folder icon in the Private Folder pane and select **Create Private Folder**.
3. In the **Enter Password** text box, type a password for the private folder. Your password must be less than 40 characters long.
4. In the **Re-enter Password** text box, type the password again to verify it.
5. Click **OK**.




A new folder will not display in the Private Folder pane. Private folders are hidden and are only identified by their password. When you have a private folder open you will see any subfolders that exist within the private folder, but do not confuse these subfolders with the private folder itself.

To Open a Private Folder:

1. Close any open private folders.
2. Click **Panes | Private Folder**.
3. Click the **Open** button in the Private Folder pane header.

4. In the **Enter Password** text box, type the password of the private folder that you want to open.
5. Click **OK**.

 The contents of an open private folder remain visible until you close it. Remember to close your private folder if you have to step away from your computer and do not want anyone to see its contents.


To Close a Private Folder:

Do one of the following:

- Click the **Close** button in the Private Folder pane header.
- Click **File | Exit** to exit ACDSee. The private folder is closed automatically.

To Add Files to a Private Folder:

1. Open the private folder to which you want to add files.
2. Click and drag the files onto the private folder icon in the Private Folder pane. A warning message displays.
3. Click **Yes** to move the files to the private folder.

 When you add files and folders to a private folder they are removed from their original location in the file system and added to the password-protected private folder. There is no way to recover files and folders from a private folder if you have forgotten your password. Ensure that you choose a password that you will be able to remember.

To Add an Existing Folder and its Contents to a Private Folder:

1. Open the private folder to which you want to add files.
2. Click and drag the folder onto the private folder icon in the Private Folder pane.
3. Click **Yes** to move the folder and its contents to the private folder.

To Restore Folders and Files from a Private Folder:

1. Open the private folder containing the folders or files that you want to restore.
2. Select the folders or files and click **File | Restore from Private Folder**.
3. Click the browse button, navigate to the folder where you would like to move the folders or files, and then click **OK**.
4. Click **OK**.



ACDSee Home moves the folders or files from the private folder to the selected location. These folders and files are now visible to anyone with access to the computer.

To Delete a Private Folder, or the Folders or Files in the Private Folder:

1. Open the private folder containing the folders or files that you want to delete.
2. Do one of the following:
 - To delete the private folder, right-click the private folder icon and select **Delete**.
 - To delete folders or files in a private folder, right-click them and select **Delete**.

A warning message displays.

3. Click **Yes** to delete the private folder and all of its contents, or the selected folders or files in the private folder.



Use caution when deleting folders or files in private folders. If you delete folders or files in private folders they are permanently destroyed. Restore the folders and files if you want to move them from the private folder to a non-secure location on your computer.

Tagging Images or Files

You can tag images to identify certain characteristics. This could be your best photos from an event or images you wish to review. You can use this same method for organizing and categorizing your documents and other files.

The tagging checkbox is at the bottom right corner of the thumbnails. Check the checkbox to tag or un-tag photos or documents. Photos remain tagged until you uncheck the checkbox.

You can display all your tagged photos or files with one click by clicking **Tagged** under Special items in the Catalog pane. Tagging, like categories and ratings, is a way to set aside, organize, and group your photos or files without moving the files into different folders.



Tagging is intended as a temporary means of separating your images and files. Once tagged, you can move or apply categories and ratings to the images and files, and then clear all of the tags. Categories, ratings, color labels, and folders are more effective for organizing and grouping your images and files over a long period of time.

To Tag a Selected Image or File:

- Use the keyboard shortcut \ backslash key to apply the tag.
- Check the checkbox in the bottom right corner of the thumbnail.

- Right-click on one or more thumbnails and select **Tag**.
- In the Properties pane, check the tag checkbox at the top left corner in the **Metadata** tab.

To Untag a Selected Image or File:

- Use the keyboard shortcut **** backslash key to remove the tag.
- In the Properties pane, uncheck the tag checkbox at the top left corner in the **Metadata** tab.

To Untag All Tagged Images or Files:

1. Click **Tagged** in the Catalog pane to display all tagged files in the File List pane.
2. Use the keyboard shortcut **Ctrl + A** to select all.
3. Click the backslash key **** to remove the tag.

To Display Tagged Images or Files:

In Manage mode, click **Panes | Catalog** to display the Catalog pane, then click **Tagged** in the Special Items section.

Tagged photos or files from all your folders display in the File List pane.

To Tag an Image or File in View Mode:

Do one of the following:

- In View mode, check the checkbox in the bottom right corner of the status bar.
- In View mode, click **Panes | Properties** to display the Properties pane, click the Metadata tab, then check the **Tagged** checkbox in the top left corner.

To Tag an Image When You Are Comparing Images:

1. In the Comparison List, check the checkbox in the bottom right corner of the image thumbnails.
2. Click **OK**. The Compare Images Viewer closes. You will see a checkmark in the checkbox of the images that you tagged.

Managing Metadata Views

To Select a Metadata View:

1. Click **Panes | Properties** to open the Properties pane.
2. Select the Metadata tab of the Properties pane.

3. Click the Metadata View drop-down list in the Metadata tab to select one of the view options: Default Metadata View (most commonly used fields), All EXIF, All IPTC, ACDSee Metadata, or saved custom views.



You must have an image selected to view the Metadata tab.

Default Metadata Views:

There are 5 built-in Metadata Views to select from:

- Default Metadata View
- All EXIF Metadata
- All IPTC Metadata
- All Video Metadata
- ACDSee Metadata



Video files will only be played if **Windows** can play them. **Metadata** for videos will only appear if the video can be played.


To Create a Customized Metadata View:

1. Click the Metadata View drop-down list in the Metadata pane and select **Manage Metadata Views....**
2. In the Choose Metadata to Display dialog box, select **New Metadata View** from the drop-down list.
3. Click the plus + signs to expand the tree and check/uncheck the checkboxes on and off to select your preferences. See Manage Metadata View options below.
4. Click the save button and enter a name for your customized view.
5. Click **OK**.

Manage Metadata Views Options

- When all items in a group are selected, the group checkbox is checked.
- When no items in a group are selected, the group checkbox is unchecked.
- When some, but not all items in a group are selected, the group checkbox is solid.

Check/uncheck the checkboxes to make your selections.



You can choose whether or not to display maker notes by checking or unchecking the **Display Maker Notes** checkbox.

Adding ACDSee Metadata to Multiple Files

You can add information to your images using IPTC and ACDSee Metadata. IPTC information is automatically embedded into your image, while ACDSee Metadata can be embedded into your file, or stored in the database.

We recommend entering and editing metadata prior to processing your images.



You cannot set IPTC and EXIF information for read-only files, such as those on a CD-ROM.



If the Properties pane is not already open, select **Panes | Properties**.

To Add Metadata to One or More Files:

1. In **Manage** mode, select one or more files in the File List pane.
2. In the Properties pane, select the **Metadata** tab.
3. Enter information into the metadata fields.
4. Click **Apply** or press **Enter** to apply your changes.



When you click **Apply** or **Enter** in Manage Mode, the focus is returned to the File List pane allowing you to quickly make another file selection using your keyboard.



To include numbers in a sequence with your metadata, select the files and enter **<#>** as the start number, in whichever field you want. Ex) Entering **<5>** will begin the sequence at 5.

Metadata Tab Keyboard Shortcuts

This Shortcut	Has This Result
Tab	Jumps focus forward from field to field.
Shift + Tab	Jumps focus backwards from field to field.
Ctrl + K	Places the cursor in the ACDSee Metadata Keywords field of the Organize tab in the Properties pane.
Alt + K	Places the cursor in the IPTC Keywords field of the Metadata tab in the Properties pane.
Enter	Applies your changes.
Esc	Discards your changes.



If you click away from the Properties pane, any metadata that you have just entered will be lost. You must click **Apply** or press **ENTER** to apply your changes.

To Use Keyboard Shortcuts to Enter Metadata into the Same Field of Multiple Photos:

1. Select the first photo in your list and enter content into a Metadata field.
2. Press the **Page Down** key to move to the next photo. The cursor remains in the same field of the Properties pane for each photo, allowing you to quickly enter content for the same field for multiple photos.
3. Enter content into the field and again press **Page Down** to move to the next photo.
4. Continue Step 3 until complete.



You do not need to click the **Apply** button when using this shortcut.



You can use the **Page Up** key to move back to the previous photo.

Embedding and Importing Categories and Keywords between ACDSee and IPTC

There are quick commands to embed your ACDSee keywords and categories into IPTC metadata, as well as importing from IPTC keywords and supplemental categories into your ACDSee keywords and categories.

To Embed ACDSee Keywords and Categories to IPTC Keywords and Supplemental Categories

Select a file, Right-Click and choose **Metadata | Embed to IPTC | Embed Keywords to IPTC** or **Embed Categories to IPTC**.

or

Select a file, and choose **Tools | Metadata | Embed to IPTC | Embed Keywords to IPTC** or **Embed Categories to IPTC**.

Merging or Overwriting IPTC Metadata

When embedding **ACDSee Metadata** into **IPTC metadata**, you can choose how the data is saved alongside previously saved metadata.

- Merge: **ACDSee Metadata** will be added to any existing **IPTC Keywords** and/or **IPTC Supplemental Categories**.
- Overwrite: **ACDSee Metadata** will replace any existing **IPTC Keywords** and/or **IPTC Supplemental Categories**.

To Import Keywords and Supplemental Categories from IPTC to ACDSee Keywords and Categories

Select a file, Right-Click and choose **Metadata | Import from IPTC Keywords** or **Import from IPTC Supplemental Categories**.

or

Select a file and choose **Tools | Metadata | Import from IPTC Keywords** or **Import from IPTC Supplemental Categories**.



Importing from IPTC metadata to ACDSee Metadata always acts as a merge.


Removing IPTC Keywords from Auto Categories

You can remove unused IPTC keywords from the ACDSee Home database. Once removed, the IPTC keywords will no longer display under Keywords (IPTC) in the Photo Properties' Auto Categories list of the Catalog Pane.



This process also applies for the Supplemental Categories field. This field is only visible if selected from the Choose Metadata to Display dialog box found under **Tools | Options | Properties Pane** by pressing the **Manage Metadata Views** button.

To Remove IPTC Keywords and Supplemental Categories:

1. In Manage mode, select any image which supports IPTC.
2. If the Properties pane is not already displayed, click **Panes | Properties**.
3. To ensure the image is writable, do the following:
 - Select the **File** tab and check to see if there is a checkmark in **Read only**.
 - If there is a checkmark, the image is not writable. Uncheck the **Read only** checkbox to make the file writable.
4. In the **IPTC** section of the Metadata tab, click the keyword picker button  beside the **Keywords** field.
5. In the IPTC Keywords Picker dialog box, click **Edit List**.
6. Select the keyword you want to remove from the Value list.



To select more than one keyword, press and hold the **Ctrl** key while selecting the keywords.

7. Click **Remove**.
8. Click **OK**.
9. Click **OK** again to confirm.



Only keywords that are not in use can be removed from the list. To find photos associated with a keyword, click the keyword listed under Photo Properties in the Auto Categories list of the Catalog pane.

Changing the Date and Time Properties of Images

You can use the Batch Adjust Time Stamp tool to change the date and time properties of one or more images in Manage mode or in View mode.

To Change the Date and Time Properties of a File:

- Do one of the following:
 - In Manage mode, select one or more images, and then click **Tools | Batch | Adjust Time Stamp**.
 - In View mode, click **Tools | Modify | Adjust Image Time Stamp**.
- On the Date to Change tab, choose from the following:

Date to Change

EXIF date and time	EXIF date/time original	The original date/time the image was captured.
	EXIF date/time digitized	The date/time the image was converted to a digital image (usually the same as original).
	EXIF date/time	The date/time the image was last edited.
File last-modified date and time	The date/time the image or file was last edited. For example, image editing or updates to metadata.	
File creation date and time	The original date/time the file was created.	
ACDSee Database date and time	The date and time held in the ACDSee Database.	

- On the **Advanced Options** tab, select the options for the Adjust Image Time Stamp tool described below, then click **Next**.


Advanced Options

Accept defaults and start conversion	Accepts the default settings for the new time stamp options. To start changing the date and time of your images, click Adjust Time Stamp .
Automatically close wizard when finished	Closes the Adjust Image Time Stamp wizard as soon as the process is complete.
Save current settings as defaults	Remembers the current settings and applies them the next time you change time stamps.

4. On the Choose new time stamp page, select one of the following options:
 - **Use different date and time:** replaces the selected date and time with another time stamp property from the same file. Select the file property you want to use from the **Select date and time** drop-down list.
 - **Use specific date and time:** changes the selected time stamp in each file to a specific date and time. Type the new date and time for the time stamp in the **Date** and **Time** fields.
 - **Shift to a new starting date and time:** replaces the earliest time stamp with a date and time you specify, and shifts all later time stamps ahead accordingly. Specify the time stamp for the earliest file in the **Date** and **Time** fields.
 - **Shift date and time by a specific number:** shifts all the time stamps either forwards or backwards by a specific number of hours (to adjust for time zones). Select either **Shift forward** or **Shift backward**, and type a number into the **Hours**, **Minutes**, and **Seconds** spin boxes.
5. Click **Adjust Time Stamp** to begin adjusting your files.
6. When the wizard is finished, click **Done** to return to ACDSee.


Backing Up Your Files to Another Computer

The Sync wizard will guide you through the process of creating a synchronized copy of your files to protect you from local hard drive failure. This is also known as a back up. You can synchronize your local folders with a network drive, remote computer, or external hard drive. You can name the synchronization, specify the actions you want to take each time you synchronize your files, schedule the synchronization to run at specific intervals, and edit or remove the synchronization at a later time.

 The Sync wizard does not backup your database when your files are copied to a new location. To back up files with database information, use the [ACD Database Backup wizard](#).

To Create a Synchronization:

1. In Manage mode, click **File | Sync | Create Sync**.
2. On the Welcome page, click the **Next** button when you are ready to continue.
3. On the Synchronization Options page, do the following:
 - In the **Source folder** field, specify the folder containing files you would like to copy.
 - In the **Backup destination** field, specify a folder on a network drive, remote computer, or external hard drive in which to place the backup files.
 - In the **Options** area, specify how Sync should handle errors and logs.
 - In the **Confirmations** area, specify how Sync should handle file duplication conflicts.
 - Click **Next** when you are ready to continue.
4. On the Synchronization Schedule page, do the following:
 - In the **Name** text box, type a name for your synchronization.
 - In the **Schedule** area, specify whether you would like to run the synchronization immediately, or schedule the synchronization.
 - Click **Finish** when you are ready to complete the wizard.

 **Schedule:** an account with no password cannot set up a schedule. You must set a password for your account for schedules to work. A blank password will not work; you must have a real password with more than one character.

Updating or Deleting a Synchronization

You can adjust the settings of a synchronization, schedule it to run at regular intervals, or delete the synchronization from ACDSee.

To Update or Delete a Saved Synchronization:

1. In Manage mode, click **File | Sync | Edit Sync**.
2. In the Saved Synchronizations dialog box, select a synchronization from the list.
3. Do one of the following:
 - To schedule the synchronization, click **Schedule**. Specify how often to run your synchronization, and then click **OK**.
 - To adjust the settings, click **Edit**. In the Edit Synchronizations dialog box, update the folder containing files you would like to copy, and a folder on a network drive, remote computer, or external hard drive in which to place those files. In the **Options** area, update how Sync should handle errors and logs. In the **Confirmations** area, update how Sync should handle file duplication conflicts. Click **OK** when you are finished.

- To rename the synchronization, click **Rename**. Type a new name for the synchronization and click **OK**.
- To delete the synchronization, click **Delete**.

4. Click **Close**.

Running a Saved Synchronization

After you create a synchronization, you can run it at any time, even if it is scheduled to run at regular intervals.

To Run a Saved Synchronization:

In Manage mode, click **File | Sync**, and then select the name of the synchronization you want to run.

Searching with ACDSee Home


ACDSee Home includes a number of ways to search your computer for files and folders. You can use the Advanced Search pane to search by file name, keywords, or image properties. You can create advanced searches to locate files that fall within a date or rating range and then save and name the search to use later. You can also use the Duplicate Finder to locate and manage identical files.


For simpler searches, you can use the Quick Search bar to quickly locate files and folders, or search the database for specific names and keywords. You can also customize the Quick Search bar to only search for specific items or certain parts of the database.

Also, you can use the Catalog pane to quickly locate and list all images on your hard drive, or to locate any files in a folder that have not been categorized. If you are working with larger image collections, you can use Selective Browsing to specify broad or narrow criteria for the images you want to display in the File List pane.

Using the Quick Search Bar

You can use the Quick Search bar in Manage mode to quickly locate files or folders. You can use the Quick Search options to refine or expand your search, and view the results in the File List pane.

You can choose whether the Quick Search searches just the files currently in the file list, or the entire database, by clicking this icon .

When performing a quick search, you can select the type of search to perform by clicking on the magnifying glass icon  found directly to the right of the Quick Search field.

Search types will utilize different **separators: Delimiters, Operators**, or none:

- **Delimiters** are commas and spaces. Search types that use delimiters will separate search terms by commas or spaces.
- Starts With and Ends With do not use any separators. All text typed is literal. For example: Cat, Dog will search for "Cat, Dog", including the comma and space.
- Classic Quick Search uses the **operators** + , -, |, and space (which is treated the same way as a +).

Quick Search Types:

Search Type	Result	Separators	Examples
Contains Any	Searches for items that contain any terms specified within the search criteria. Includes sub-string searches.	Delimiters	Cat, Dog returns all results containing Cat or Dog or any combination of the two. This includes sub-string searches, for example: Searching for Cat would also bring results for words that have cat in them, such as catalog.
Contains All	Searches for items that contain all terms specified within the search criteria. Includes sub-string searches.	Delimiters	Cat, Dog returns all results containing both Cat and Dog.
Contains Words	Searches for items that contain whole words specified within the search criteria.	Delimiters	Cat, Dog returns all results that include the whole words Cat and Dog.
Does Not Contain	Searches for items that do not contain any of the terms specified within the search criteria. Includes sub-string searches.	Delimiters	Cat, Dog returns all results that do not include the search terms of Cat or Dog.
Starts With	Searches for all items that begin with the characters specified within the search criteria. Includes sub-string searches.	None	Cat returns all results that begin with Cat. This includes results that include but are not limited to the searched term, such as catalog.

Search Type	Result	Separators	Examples
Ends With	<p>Searches for items that end with the characters specified within the search criteria. Includes sub-string searches.</p> <p>Please note: If searching for a file name, you must include the file extension.</p>	None	<p>Sing returns all results that end with Sing. This includes results that may not begin with the term specified, such as "rising".</p> <p>Sing.jpg returns all results that end with Sing.jpg. This means only results that include sing, with a file extension of .jpg will be returned.</p>
Classic Quick Search	<p>Performs searches for items using ACDSee's legacy Quick Search engine. If searching for a file name, search will utilize the "Starts with" search style. All other search fields search for whole words.</p> <p>Operators:</p> <p>+: searches for all items containing both search terms. Items that only contain one of the terms are excluded. Spaces are also treated as + operators.</p> <p>-: searches for all items containing the first search term, that don't also include the second term.</p> <p> : Searches for all items containing either of the search elements.</p>	Operators	<p>Cat -Dog returns all items that contain Cat, except those that also contain Dog. Be sure to insert a space before the minus sign. If you do not insert a space, ACDSee Home will assume you are searching for a hyphenated word.</p> <p>Cat Dog includes all items with either Cat or Dog in the search.</p> <p>Cat+Dog+-</p>

Search Type	Result	Separators	Examples
			<p>Kittens returns items that include both Cat and Dog, but not those that include Cat and Dog and Kittens.</p> <p>Cat+Dog or Cat Dog returns items containing both Cat and Dog.</p> <p>Cat+Dog Kittens includes items that contain both Cat and Dog, and those that contain Kittens.</p>

Running a Quick Search:

Do one of the following:

1. In the Quick Search bar, type the term or part of a term you want to search for.
2. Click the drop-down list beside the Quick Search field and select a previously entered search term.



You can use the keyboard shortcut **Ctrl + F** to put the focus in the Quick Search bar and immediately begin typing.

Choosing Fields to be Included in Search:

- Select Tools | Options.
- Select Quick Search under Manage Mode.
- Toggle fields to be included or excluded from the search, then select Ok.

Using the Advanced Search Pane

You can use the Advanced Search pane to search for your files and folders. You can search by a wide variety of options such as file names, text strings, metadata fields, file properties, or image attributes. You can also search for patterns in file names and find duplicate files.

You can even save a search and give it a name. Search Presets are listed on the Advanced Search pane and the Catalog pane. On the Advanced Search pane, you can select Search Presets from the drop-down list to run again. On the Catalog pane, Search Presets are listed below Auto Categories where you can run them again by clicking once on the Search Preset name.



The Advanced Search pane will not return results for folders that are not cataloged in the ACDSee Home database. Cataloging happens automatically when you browse to a folder. You can also click **Tools | Database | Catalog Files**.

To Open the Advanced Search Pane:



In Manage mode, click **Panes | Advanced Search**.

Advanced Search Pane Areas

The Advanced Search pane contains several areas to help you manage your searches. When you create a search, remember that the search tool will only return files that match **all** of the criteria that you specify.

Search Presets

In the Search Presets area, you can save a complex search to use later, select a search to run again, or delete a search preset.

Search Presets	<p>If you have a search preset, it is listed in this drop-down list for you to select and run again. When you click Start at the bottom of the pane, the search results are listed in the File List pane.</p> <p>Search Presets are also listed on the Catalog pane, from where you can run them with a single click on the Search Preset name.</p>
Save a search preset 	<p>Click the Save icon. When the Search Preset dialog opens, type in a name for the search. If you use a descriptive name, it makes it easier to remember the criteria in your search preset.</p>
Delete a search preset 	<p>Select a search from the drop-down list and then click the Delete icon. Click Yes to confirm the deletion, when the prompt opens.</p>

Source

When searching for files, you can search three different source locations:

Database	Searches using the Database source will look for files within the cataloged files in Photo Studio.
Folders	Searches using the Folders source will look for files within a selection of folders. You can select one or more folders to be searched, or simply select Sync to the current folder to use the folders currently selected in the Folders pane.
Current View	Searches using the Current View source will look for files within your currently selected file list in Photo Studio. This can include one or multiple folders, different metadata from the Catalog pane, or even the results of your previous search.

Criteria

You can choose from a wide range of criteria and file types. In the header, use the **File Type Selector** button to open the menu with different searchable file types.

Press the + button to open the **Criteria Picker** to display the full list of searchable criteria. Click a criteria on the left side of the picker to add it to the right side. Once on the right side, criteria can be managed by moving them up and down, changing their **AND/OR** state, or removing them with the delete button. Click the OK button to update the **Advanced Search** pane with your selected criteria. Most criteria search for a single metadata field, allowing you to fine-tune your searches. Each criterion is divided by buttons displaying the **AND/OR state** on the Advanced Search pane, clicking the button will change its state between **AND & OR**.

For more information and examples, see [Choosing Criteria in the Advanced Search Pane](#).



When criteria have been added to the **Advanced Search** pane, many will include a **gear icon**. Clicking on the icon will provide additional ways to customize your search.

History

When an **Advanced Search** has been run, it will appear in the **History** section of the **Activity Manager**. Clicking on the **Advanced Search** entry in the **History** will open the **Advanced Search** pane with the search criteria preloaded. For more information see [Activity Manager](#).

Options

Folder Handling

You can choose how results are returned when folders match the search criteria:

Return those folders	Returns folders that meet the search criteria
Return those folders as well as their contents	Returns folders that meet the search criteria as well as their contents
Return only the contents of those folders	Returns the contents of folders that meet search criteria, without displaying the folders themselves





Searches will always return files that meet the search criteria regardless of this setting.

Choosing Criteria in the Advanced Search Pane

When using the Advanced Search pane, you can choose to search a large assortment of criteria from ACDSee Metadata, IPTC, EXIF, and other file information. See table below for commonly used criteria, and examples of other criteria datatypes.

Data Types	Definitions and Examples
Filename	<p>Search for files or folders by name. Search terms can be separated by semicolons for all the search types except Pattern Match. You can select between Any of or All of for each search field to determine how your search terms are handled. Any of will search for items that include Any of your search terms, while All of will search for items that include All of the search terms. Search history is stored for Filename searches. Use the UP and DOWN arrow keys to select different auto-complete suggestions from your history, and press ENTER or TAB to enter the selected suggestion. Change to the Pattern Match search type to make use of Wildcards:</p>

Data Types	Definitions and Examples		
	Wildcard	Result	Example
	?	Matches any single character in the file name.	ca?.jpg results in cat.jpg, cap.jpg, and car.jpg, but not cats.jpg
	*	Matches zero or more characters in the file name.	cat* results in cat.jpg, cats.jpg, and cathy.jpg
	[...]	Matches any of the enclosed characters.	ca[tr] results in cat.jpg or car.jpg, but not cap.jpg
	[!...]	Matches any character not enclosed.	cat[!0] results in cata.jpg and catb.jpg, but not cat0.jpg
	[...-...]	Matches any character in the specified range.	cat[a-f0-9] results in cata.jpg, catb.jpg, catf.jpg and cat0.jpg, cat1.jpg, ..., cat9.jpg
	\	Blocks the use of other wildcard characters that are also characters permitted in a file name, such as square brackets: []. The * and ? characters are not permitted in file names so this function does not work with them.	Because square brackets are wildcards, if you wanted to search for a file name that contains a bracket, you must precede the bracket with a backslash: ACD\[123\] results in ACD [123].gif
 Patterns are not case-sensitive. To use multiple patterns, separate the names with spaces or			

Data Types	Definitions and Examples
	 semicolons. To match a pattern containing a space or semicolon, enclose the pattern in double quotation marks. If you do not include the * wildcard in your pattern, the pattern is matched as a sub-string. For example, cat would match cat, cathy and bobcat, and is equivalent to the pattern *cat*.
Text	String-based search on several common fields. Choose from any or all of: Keywords, Categories, People, Labels, Captions, and Notes. Search history is stored for Text searches. Use the UP and DOWN arrow keys to select different auto-complete suggestions from your history, and press ENTER or TAB to enter the selected suggestion.
People, Keywords, and Categories	Combination string and lookup list searches. Open the Value Picker to choose values from the database, or type custom strings in the text field. Search terms can be separated by semicolons.
Rating	Select the ratings you'd like to search.
Label	Select the labels you'd like to search. Choose from any of your label sets, or change to Text Search to search for custom values.
String	Search for strings of text, can be separated by semicolons. Example: Maker
Date/Time	Search for a date and time. Set the precision to day or second. Example: Date/Time Original
Lookup List	Select one or more values from the Value Picker. Example: Image Type
Integer	Search an integer number. Example: ISO
Rational	Search for a rational number as a fraction or decimal number. Example: F-Number



When using a semicolon(;) to separate search terms, you can use two semicolons(;;) to search for a literal semicolon instead.

Using Selective Browsing

You can use selective browsing to browse for files that are located in a specific folder, assigned a specific date, and/or assigned to a specific Catalog classification. By adjusting the selective browsing criteria, you can quickly include or exclude files from the File List pane, and view only those files you want to browse.

To get the most out of selective browsing, it is recommended that you [catalog](#) and [organize](#) your files in the ACDSee Home [database](#). The more information you enter for your files, the more helpful you will find the selective browsing feature.

To Use Selective Browsing:

Open the Selective Browsing panel by clicking **View | Selective Browsing**. The panel appears on the left side of the File List pane.

Setting Selective Browsing Criteria

The Selective Browsing panel is divided into three areas: Folders, Catalog, and Calendar, each of which corresponds to the Manage mode pane of the same name. When the Selective Browsing panel is open, the [Contents bar](#) in the File List pane is replaced by the Selective Browsing bar, which lists all of the current browsing criteria.

When you add a folder, date range, or organize method to the Selective Browsing panel, ACDSee Home excludes any files that do not match that criteria. You can add or remove criteria to narrow or broaden your results.

To Add Selective Browsing Criteria:

With the Selective Browsing panel open, do any of the following:

- In the [Folders pane](#), select one or more folders.
- In the [Catalog pane](#), select one or more categories, and/or a rating.
- In the [Calendar pane](#), select one or more date ranges.

As each criteria is added to the Selective Browsing panel, ACDSee Home searches its database for files in that folder, that match the date range, and are assigned to the classification, and displays them in the File List pane. You can then select those files and use the ACDSee Home features to edit, share, move, and view them however you want.

You can also adjust or refine your criteria in the Selective Browsing panel:

- To remove a selected criteria from the Selective Browsing panel, right-click any of the criteria, and then select **Remove From Scope**.

- To exclude all of a certain type of criteria, click the bar above the list, and toggle the option to include that type in the scope. For example, to exclude the listed folders from the scope, click the **Folders** bar, and then click **Include Folders in Scope**. The folders you selected will still be displayed in the Selective Browsing panel, but will not factor in the results.
- To remove all criteria of a certain type, click the bar above the list, and select **Clear All**.

The default behavior for categories in the Selective Browsing panel is to display files that match any of the categories listed. You can refine your results by choosing to display only those files that are assigned to all of the specified categories. To toggle between behaviors, right-click the bar above the categories you selected, and select **Match Any** or **Match All**.

Tips for Selective Browsing

When you add a criteria to the Selective Browsing panel, you are indicating that the files you want to browse must have that attribute. For example, if you select a folder in the Folders pane, then ACDSee Home displays only files in that folder. If you select a rating in the Catalog pane, ACDSee Home displays only files assigned to that rating.

You can combine criteria to refine your selective browsing even further. For example, if you select a category and a date range, then ACDSee Home displays only those files that belong to both the category and date range you selected. ACDSee Home does not display items that fall within the date range unless they are also assigned to the correct category, and does not display files assigned to that category unless they also match the date range.

Hiding the Selective Browsing Panel

You can use the Auto Hide feature to automatically hide the Selective Browsing panel and increase space for the File List pane. When the panel is set to auto-hide, it rolls away when you click outside it, leaving only an edge displayed. You can access the panel again by moving the cursor over the edge.

Searching with Auto Categories

Auto categories can help you search for files. This is particularly useful if you tend to take a lot of photos, or if you share your pictures with others.

You will find auto categories in the Catalog pane below Labels. Double-click or click the plus sign (+) to expand auto category groupings. Double-click or click the minus sign (-) to collapse the auto category groupings.

Some auto category information is added to images by your camera. This could include camera make and model, white balance settings, focal length, and aperture. You can supplement that with information you think is useful such as the location, keywords or copyright. To do this, you can enter information in the Properties pane.

When you click on an auto category, ACDSee Home searches for images belonging to that category. For example, if you use more than one camera, you can use auto categories to search for pictures taken using certain camera models. All images captured with that camera model will display.

Below are some tips for searching with auto categories.

Identifying Commonly Used Search Categories

If you use certain auto categories in the Photo Properties grouping frequently, you can save time by adding them to the Commonly Used grouping. Some Photo Properties groupings are available in the Commonly Used grouping by default. You can add and remove as many auto categories as you want to the Commonly Used grouping.

To Add an Auto Category Grouping to the Commonly Used Grouping:

1. Expand the Photo Properties grouping.
2. Right-click the auto categories grouping that you want to add to the Commonly Used grouping, and select **Add to Commonly Used**. The grouping is added to the Commonly Used grouping.

It remains visible in the Photo Properties grouping as well.

To Remove an Auto Category Grouping from the Commonly Used Grouping:

1. Expand the Commonly Used grouping.
2. Right-click the auto categories grouping that you want to remove from the Commonly Used grouping, and select **Remove from Commonly Used**.

The grouping is removed from the Commonly Used grouping.

Refining Your Auto Categories Search

You can refine your auto categories search by selecting more than one auto category. For example, you can find images with a certain aperture and shutter speed. If you click the Easy-Select indicator beside the f/16 aperture auto category and the 1/30 s shutter speed auto category, ACDSee Home will search for images that belong to both of those auto categories.

When you select more than one auto category you can further control the search by selecting **Match All** or **Match Any** from the Match Any/All drop-down list at the top of the Catalog pane. If you select Match Any, ACDSee Home will display any images associated with the selected auto categories. If you select Match All, ACDSee Home will display only those images that are associated with all of the selected auto categories.

You can also refine your auto categories search by selecting a category or rating. For example, imagine that you clicked on the Photographer auto category and found over 1000 images. However, you only want to see the best images by that photographer. Click the Easy-Select indicator beside 1 in the **Ratings** area of the Catalog pane. Only the images by that photographer with a rating of 1 will display.

You can also use the Selective Browsing pane to refine your auto categories search. For example, imagine that you clicked on the Camera Model auto category and ACDSee Home displayed over 1000 images. However, you only want to see the images that you took on a specific date. Display the Selective Browsing pane by clicking **View | Selective Browsing**, then select the **Calendar** pane and select the appropriate date. Only the images taken with that camera model on that day will be displayed.

Finding Duplicate Files

You can use the Duplicate Finder to find duplicate files across a variety of folders on your hard drive. Once duplicates are found, you can perform rename and delete functions to better manage your file collection.



Note that identical images saved as different formats (i.e. different extensions, such as JPEG, BMP, GIF), are not recognized as duplicates. If you have a JPEG and save a copy of it, the image is recompressed. Therefore the original JPEG and the copy are a different file internally and they are not recognized as duplicates.

To Find Duplicate Files:

1. In Manage mode, select a folder or images to search for duplicates. (Optional)
2. Click **Tools | Find Duplicates...**
3. In the Duplicate Finder dialog box, do one of the following:
 - To find duplicates within the selected folder and any added files or folders, select **Find duplicates within this single list of files**.
 - To find duplicates by comparing the contents of two separate lists, select **Find duplicates within these two lists of files**. (This will not search for duplicates within one of the two lists. It will only search the two lists against one another.)
4. Add files to your list or lists with the **Add Files...** and **Add Folder...** buttons. Remove files by selecting them in the list and pressing the **Remove** button. Switch out one file or folder for another by selecting it in the list and pressing the **Modify** button. To include the contents of any subfolders you selected, check the **Include subfolders** checkbox.
5. Below the File Lists, specify whether you want to find exact duplicates or just files with the same name. Select **Find images only** if you only want to search for image files.
6. Press **Search**.
7. If no duplicates are found, click **OK** and refine your search or click **Cancel** to exit the Duplicate Finder.
8. If duplicates are found, select sets in the list for further actions.

Deleting and Renaming Files

Once duplicates have been found, files can be renamed or deleted. If you are working with image files, a preview is available.

If multiple sets of duplicates have been found, you may want to sort them for easier viewing.

To Sort Files:

1. Right-click in the upper-left list.
2. Select one of the following:
 - **Sort by Filename**
 - **Sort by Path**
 - **Sort by File Size**
 - **Sort by File Type**
 - **Sort by Number of Duplicates**

To Delete Duplicates:

1. Select the desired file set in the upper-left list.
2. In the bottom field, do one of the following:
 - Check the checkbox next to the file name. The file name changes to **Delete File**.
 - Right-click on the file name and select **Delete** from the context menu. The file name changes to **Delete File**.
3. If you searched using two file lists, you can choose **Delete from File List 1/File List 2**. This will save you time by selecting all files from File List 1 or File List 2, as specified.
4. Click **Next** to review your changes, and then click **Finish**.

To Rename a File:

1. Select the desired file set in the upper-left list.
2. In the bottom field, right-click on the file name and select **Rename** from the context menu.
3. Type a new name for the file.
4. Click **Next** to review your changes, and then click **Finish**.

Finding Images Quickly

You can click on the name of a search preset to quickly re-run the search. You can select Special Items in the [Catalog pane](#) to locate all of the images in your [database](#), or list all of the images that you have

not yet [assigned to a category](#).

To Re-Run a Search Preset:

In Manage mode, in the Catalog pane, click the name of a search preset.

The results of the search display in the File List pane.

To Find All of Your Images at Once:

1. In Manage mode, click **Panes | Catalog** to open the Catalog pane.
2. In the Catalog pane, under Special Items, click **Image Well**.

To Locate Uncategorized Images:

1. In Manage mode, click **Panes | Catalog** to open the Catalog pane.
2. In the Catalog pane, under Special Items, click **Uncategorized**. The Image Well and Uncategorized features only display images that have been cataloged in the [database](#); they do not search your hard drive for specific file types.

To Locate Images That Haven't Been Keyworded:

1. In Manage mode, click **Panes | Catalog** to open the Catalog pane.
2. In the Catalog pane, under Special Items, click **No Keywords**.

Sharing Files with ACDSee Home

ACDSee Home makes it easy to share your images and other files with friends and family. You can email files directly from ACDSee, upload images to a website, create your own webpages with the HTML Album plug-in, or print a contact sheet. You can also create slideshows and screensavers that you can give to anyone with a computer—they do not need ACDSee Home to view them.

Taking a Screen Capture

You can use the ACDSee Home Screen Capture utility to create images from different areas of your screen. You can select what areas to capture, how you want to perform the capture, and where to store the captured image.

To Take a Screen Capture:

1. In Manage mode or View mode, click **Tools | Screen Capture...**
2. In the Source area of the Screen Capture dialog box, identify the part of the screen you want to capture. See the table below for a description of the Source options.
3. If you want to include your cursor in the output image, check the **Include mouse cursor** checkbox.

4. In the Destination area, identify where you want to place the output image.
5. In the Initiate capture area, identify how you want to take the screen capture.
6. Click **Start** to launch the screen capture tool.

An icon appears in the Taskbar Notification area.

7. Prepare your screen to show the area you want to capture, and then follow the steps that appear in the bubble above the Screen Capture icon.
8. To exit the Screen Capture utility without taking a screen capture, right-click the Screen Capture icon, and then select **Exit Screen Capture**.

Screen Capture Options

Desktop	
Current monitor	Captures an image of the entire area displayed on the screen.
Window	
Entire window	Captures an image of the entire active window.
Content only	Captures an image of the window contents (does not include the frame or title bar).
Region	
Fixed size	<p>Captures an image of a fixed area on the screen.</p> <p>Click the drop-down button and select a dimension setting or select Custom, and enter the dimension in pixels.</p>
Selected region	Captures a selected area of the screen. Click and drag your cursor to surround the area you want to capture.
Object	
Child window	Captures an image of sections of the window. For example, a toolbar or button.
Menu under cursor	Captures selected menu commands.
Include mouse cursor	
Include mouse cursor	Includes the cursor in the screen capture.
Destination options	
Clipboard	Places a copy of the image on the Clipboard. From the Clipboard you can paste the image in a new location.
File	Displays the Save dialog box to save the file; you can specify location, format, and file name.
Editor	Opens the captured image in the default editor.
Initiate Capture options	
Hot key	<p>Designates a keystroke combination to trigger the screen capture.</p> <p>To set the Hot Key, press a key or combination of keys (e.g., Ctrl + S) on the keyboard; do not type in the box.</p>

Timer

Takes a screen capture after a designated period. Choose enough time to set up your desktop or window for the screen capture. The maximum setting is 60 seconds.

Emailing Images

You can use the Send Email wizard to send images directly from ACDSee Home without opening an external email application. To use the Send Email wizard, you will need an active email account, and have a default email application set up on your computer, or have access to an SMTP server.

To Email Your Images:

1. In the File List pane, select the images you want to email, and then click **File | Send | Email Images**.
 - If you want to add other images, click **Add**. When you have finished adding images, click **OK**.
 - If you want to delete images, select an image and click **Remove**. The image is removed from the wizard, but not deleted from ACDSee.
 - If you want to set email and image options, such as the maximum size for emails or the conversion of images to JPEG, click **Options**. When you have finished selecting options, click **Apply**.
 - If you want to change the email account settings, to use either your default email client or an SMTP server, click **Change**. When you have finished changing your email account settings, click **OK**.
2. In the Send Email wizard, click **Next**.
 - If you selected **Send using your default email client**, the wizard adds your images and email information to a new email message. You can edit the message and then send it as you normally would.
 - If you selected **Send through an SMTP server**, in the wizard, enter the email address you want to send the email to, a subject for the email, and a message. Click **Next**.
3. When the images have been sent, click **Finish** to close the wizard.



Some Internet-based email applications such as Hotmail and Yahoo (free accounts) do not support SMTP and cannot be used with the Send Email wizard. For others, such as Gmail, Yahoo (upgraded accounts), and AOL, you must configure the account for POP/SMTP. To learn how to configure these types of email accounts, visit their specific websites and search for SMTP.

See also:

Share/Email Using ACDSee 365

Once you have activated your account with ACDSee 365, you can share your images through seedrive.acdsee.com.

To Email Your Images:

1. In the File List pane, select the images you want to share, and then click **File | Send | Share/Email using ACDSee 365**.
2. In the Share/Email with ACDSee 365 dialog box, enter a Name for your album of photos and select a Location from your existing online folders.
3. Enter one or more email addresses to send the images to.



You can click the **Share with** button to pull names from your address book.

4. Select an upload size from the drop-down list.
5. Click **Upload**.
6. A new window opens providing the option to enter a message, enable download of full sized JPG, and create an access password.
7. Click **OK**.

Viewing and Configuring a Slideshow

You can view a slideshow of images and/or videos from Manage mode or from View mode. You can also configure your slideshow to start automatically whenever you run it, and set the slideshow options to adjust how long each image is displayed, set the background color, apply transition effects, and add header or footer text.

To Start a Slideshow in Manage Mode:

1. Do one of the following:
 - In the File List pane, select a group of images.
 - In the Folders pane, select a folder.
 - Use the [Easy-Select bar](#) to select multiple folders that contain images.
2. Click **Tools | Slideshow**. (Ctrl + S)

To Start a Slideshow in View Mode:

Click **Tools | Slideshow**.

To Configure a Slideshow:

1. In Manage mode, do one of the following:
 - In the File List pane, select a group of images.
 - In the Folders pane, select a folder or use the Easy-Select bar to select multiple folders that contain images.
2. Click **Tools | Configure Slideshow**.
3. In the Slideshow Properties dialog box, select or change the slideshow options as described below.
4. To save your settings as the default slideshow behavior, check the **Save current settings as default** checkbox.
5. Click **OK**.

Slideshow Options

File Selection

Slideshow contents

Specifies which of the following media to include in the slideshow:

- **All media in current folder:** displays all the files (images or video) in the folder you have selected.
- **All media in current folder and subfolders:** displays all the files in the currently selected folder and its subfolders.
- **Selected media:** displays only the files that you selected before opening the Slideshow Properties dialog box.

Always use these contents for this selection type and start slideshow automatically

Retains the current **Slideshow contents** setting and starts automatically the next time you launch the slideshow.

Basic

Select transitions

Displays a list of transitions for you to select and plays each transition, variation, or effect in the Preview as you select it.

- **Select all:** selects all the transitions and displays them randomly.
- **Clear all:** clears any selected transitions.



These transitions do not work with the 2-up, 4-up and Collage variations.

Variations

Click the drop-down list to select from the following:

- **None:** uses no variations.
- **Pan and Zoom:** zooms in and pans across each slide during the time it is displayed.
- **2-up:** displays two images at a time.
- **4-up:** displays four images at a time.
- **Collage:** displays images as a collage where images overlap each other.

Effects

Click the drop-down list to select from the following:

	<ul style="list-style-type: none">• None: uses no effects.• Black & White: displays all images in grayscale.• Sepia: displays all images in sepia.• Vivid: increases the saturation of the images to make colors brighter.• Soft: blurs images slightly for a softening effect.
Background color	Specifies the background color. Click the color picker to select or change the color. Click Other to set a custom color in the Color dialog .
Slide duration (sec)	Specifies how long you want the slideshow to display each image.
Advanced	
General settings	Select or clear any of the following options: <ul style="list-style-type: none">• Stretch images to fit screen: enlarges small images to fill the entire screen.• Play embedded audio: plays any audio clips embedded in the images.• Stretch video to fit screen: enlarges video files to fill the entire screen.• Autohide control bar: hides the slideshow controls whenever the cursor stops moving for more than a few seconds.• Loop: repeats the slideshow after displaying the last image.
Slide order	Select one of the following options to specify the order to display your images: <ul style="list-style-type: none">• Forward• Shuffle
Music directory	Displays music from the previously-selected folders, or you can click Browse to find a new folder.
Text	
Display header text	Displays a text caption at the top of each image. Set the

	options to specify the text you want to display.
Display footer text	Displays a text caption at the bottom of each image. Set the options to specify the text you want to display.
Save current settings as default	
Save current settings as default	Retains the current settings on all of the tabbed pages and applies them the next time you view a slideshow.

Slideshow Text Options

Alignment	Specifies the alignment of the text captions.
Background color	Specifies a background color for the caption text.
Text	Specifies the text to display as a caption.
Font	Opens the Font dialog box where you can select or change the font options for your text.
Insert Metadata Tag	<p>Inserts file-specific information called metadata into the caption.</p> <p>Click to open the Choose Properties dialog box and select the metadata you want to insert.</p>

Sharing Slideshows and Screensavers

You can view a slideshow of your images from Manage or View mode at anytime by clicking **Tools | Slideshow** (keyboard shortcut **Ctrl + S** in Manage mode). With ACDSee, you can also create slideshows and screensavers of your favorite photos, and send them to friends and family, or display them on your website. You can even save your slideshow or screensaver project to edit at a later time.

To Create a Slideshow:

1. In Manage mode, click **Tools | Create | Slideshow File**.
2. On the Welcome page, to create a new slideshow, select the **Create a new slideshow** radio button. To specify what type of slideshow you want to create, select one of the following options:
 - **Standalone slideshow:** creates a single executable file (.exe) containing all of your images and everything needed to view them. You can share this type of file with anyone who has a computer, even if they do not own ACDSee.
 - **Windows screensaver:** creates a standard Windows screensaver file (.scr) that can be stored and used on any Windows system.

- **Adobe Flash Player® slideshow:** creates a compact Adobe Flash file (.swf) that you can display on a website.
3. To edit an existing slideshow or screensaver project, select the **Load an existing slideshow project** radio button, and then click **Browse** to locate your project (.asw file).
 4. Click **Next** to continue.
 5. On the Choose your images page, you can view the images included in your slideshow, in the default order they will be displayed. Click **Add** or **Remove** to change the images, and use the arrow buttons to reorder them. Click **Next** when you are ready to continue.
 6. On the Set file specific options page, click the underlined words beside each thumbnail to set the individual options for each image. These include transitions between photos, the duration of the transition and slide, text captions, and audio files to play when the image is displayed. Note that the options available depend on your choice of output file format, and not all formats support all options. Click **Next** when you are ready to continue.
 7. On the Set slideshow options page, set the timing for each slide to automatic or manual, the order to display slides, and whether or not to hide the controls. You can also add audio files to play in the background, and adjust the quality, or speed, of the transitions. Click **Next** when you are ready to continue.
 8. On the following pages, set the options for image size, location of your slideshow file and the project file.
 9. Finally, click **Next**, and wait a few moments while ACDSee Home generates your slideshow. When complete, you can launch your slideshow and exit the wizard.



If you assign an audio file to an individual image, as well as to the whole slideshow on the Set slideshow options page, then both audio files will play simultaneously when that slide displays.

Creating a Desktop Slideshow

You can use ACDSee Showroom to create a slideshow of your photos and display that slideshow in a small window on your computer desktop. You can run up to 16 different slideshows on your computer at once.

You can configure the ACDSee Showroom window to always stay on top of other application windows. You can also configure it to open when you start your computer. You do not have to open ACDSee Home to use ACDSee Showroom.

To Create a Desktop Slideshow with ACDSee Showroom:

1. In Manage mode, navigate to a folder containing images that you want to add to the desktop slideshow.
2. Do one of the following:
 - Click **Tools | Create | ACDSee Showroom**.
 - Click **Start | Programs | ACD Systems | ACDSee Showroom**.

The slideshow starts immediately and the ACDSee Showroom icon appears in the taskbar.

Using the ACDSee Showroom Slideshow Controls

There are a number of slideshow controls in the ACDSee Showroom window.

- Click the **Back** or **Forward** buttons to display the previous or next photos in the slideshow.
- Click the **Pause** button to pause the slideshow while a particular photo is displayed.



If you cannot see these slideshow controls in the ACDSee Showroom window, click anywhere in the window. The controls disappear while the slideshow is playing so you can fully enjoy your photos.

To Create More Than One ACDSee Showroom:

With ACDSee Showroom open, do one of the following:

- Right-click in the ACDSee Showroom window and select **New Showroom**.
- Click the ACDSee Showroom icon in the taskbar and select **New Showroom**.

To Close ACDSee Showroom:

Do one of the following:

- Click **Close** in the ACDSee Showroom window.
- Click the ACDSee Showroom icon in the taskbar and select **Exit ACDSee Showroom**.



If you have configured ACDSee Showroom to open when you start your computer, it will automatically open the next time you start your computer.

Creating a PDF

You can use ACDSee Home to combine your images into PDF (portable document format) files. The Create PDF wizard will guide you through the process of creating one or more PDF files from your images, or adding images to a PDF slideshow.

To Create a PDF:

1. In Manage mode, in the File List pane, select the images you want to share.
2. Click **Tools | Create | PDF**.
3. On the Welcome page of the Create PDF wizard, select one of the following options, and then click **Next**:
 - **Create a PDF slideshow**: combines all of your images into a single PDF file that you can view as a slideshow.
 - **Create one PDF file containing all images**: combines all of the selected images into a single PDF file with multiple pages.
 - **Create one PDF file for each image**: converts each image into a separate PDF file.
4. On the Choose images page, you can change the selected images, and use the arrow buttons to reorder them. Click **Next** to continue.
5. Do one of the following:
 - If you selected to create a PDF slideshow, set or change the transition options by clicking the hyperlink next to each image. Click **Next** to set the order, color, and file name options for your slideshow. Click **Next** when you are ready to continue.
 - If you selected to create one or more PDF files, specify a file name and location, and then click **Next**.
6. Click **Finish** to close the wizard and return to ACDSee.

Creating a PowerPoint Presentation

You can create a PowerPoint presentation quickly from inside ACDSee Home using the Create PPT wizard. The wizard walks you through the process of creating or editing a presentation using your photos. You can set slide duration, the location of the file, number of images per slide and whether or not to use a design template as a background. You can also add captions, a title, or notes to each slide.



This feature only works if you have Microsoft PowerPoint® installed on your computer. The feature does not support RAW files, so you will need to convert RAW files to another format. Your version of Microsoft PowerPoint® must be 64-bit.

To Create a PowerPoint Presentation:

1. In Manage mode, in the File List pane, select the images you want to share.
2. Click **Tools | Create | PPT**.
3. On the Choose images page of the Create PPT wizard, click **Add** if you want to add more images.

4. Click **Next**.
5. On the Presentation Options page, do one or all of the following:
 - In the **Presentation Options** area, if this is a new presentation, set the duration that you want each slide to display.
 - If you are editing a presentation, select **Existing presentation** to activate the **Path** field, and browse to your presentation. Select whether you want to **Insert slides** at the beginning or end of the presentation.
 - Select the **Number of images per slide** from the drop-down list. (If you select more than one, the Title and Notes options on the next page do not appear.)
 - Select **Link to Image file** if you want your images to stay linked to ACDSee Home rather than be embedded in the presentation.
 - Click **Use a design template** if you want to use a background template and browse to the folder on your computer to select it. (PowerPoint templates are usually under Microsoft Office | Templates | Presentation Designs.)
6. Click **Next**.
7. On the Text Options page, do one or all of the following:
 - On the **Caption** tab, type in a caption and select its background color and alignment. You can also select a different font, or insert metadata like file name or picture dimensions. Captions appear at the bottom of the slide.
 - On the **Title** tab, type in a title for the slide and select its background color and alignment. You can also select a different font, or insert metadata.
 - On the **Notes** tab, type in any notes that you want to appear in the Notes section attached to each slide. These notes do not appear on the slide itself.
8. Click **Create**.

The presentation opens in PowerPoint where you can edit it like any other presentation.

Creating an HTML Album

You can use the HTML Album wizard to prepare photo collections for posting online. The HTML album includes slideshow controls and a thumbnail display. You can select from a list of gallery style templates and then customize the gallery by adding your own logo as an image or text to the header or footer. You can also change the fonts and colors used in the gallery.

To Create an HTML Album:

1. In Manage mode, in the File List pane, select the images you want to share.
2. Click **Tools | Create | HTML Album**.

3. On the Style Settings page of the Create HTML Album wizard, select a Gallery Style from the webpage styles box.



After you select a Gallery Style and other settings, you can click **Preview Gallery** to see how those selections affect the appearance of your HTML album. You can also generate your HTML album from any page in the HTML Album wizard by clicking **Generate Album**.

4. Click **Next**.
5. On the Gallery Customization page, do one or all of the following:
 - In the **Gallery Title** text box, type the title that you want to display at the top of the webpage.
 - Check **Include header** to display a header at the top of the webpage, or uncheck the **Include header** checkbox to remove the header.
 - Check **Include footer** to display a footer at the bottom of the webpage, or uncheck the **Include footer** checkbox to remove the footer.
 - If you want to display an image in the header or footer, select **Use image** and click **Browse** and select a company logo, a photo of yourself, or another image to display in the header.
 - If you want to display text in the header or footer, select **Use information** and click **Set Information** and add enter the text that you would like to display.
 - In the **Folder settings** section, click **Browse** and select the folder where you would like to save the HTML album files.
6. Click **Next**.
7. On the Thumbnail and Image page, do one or all of the following:
 - In the **Thumbnail settings** section, adjust the appearance and format of the thumbnails in the album.
 - In the **Image settings** section, adjust the appearance and format of full size images in the album.
 - In the **Slideshow duration** section, specify how long to display full size images during a slideshow.
 - In the **Color and font settings** section, click **Color and font**, adjust the colors and fonts used in the webpage, and then click **OK**.



Click **Save Settings** to save the settings that you select for specific webpage styles. If you save the settings, you can quickly reapply them to a webpage style from the Style Settings page of the Create HTML Album wizard.

8. Click **Next** to create your HTML album. You may need to wait a few moments while ACDSee Home generates the thumbnails and creates the webpage.
9. Click **Create Another Album** to create another album, or click **Finish** to exit the wizard and return to ACDSee.



You will need to use FTP or another method to post the HTML album files to your website.

Uploading Images to Photo Websites

You can upload your photos or images directly from ACDSee to sites like [Flickr](#), SmugMug, Zenfolio, and FTP sites. You will need an account before you can upload pictures to these sites but if you do not have one, you can create an account as part of the first upload process.



You can select almost any image file type, including RAW and TIFF, and ACDSee will convert the file to JPG automatically before uploading.

To Upload Photos to a Photo Website:

You can quickly upload your photos to photo sharing websites without having to leave ACDSee.

1. In Manage mode, select one or more images and click **File | Send | To <Photo Website>...**
2. In the <Photo Website> Uploader dialog box, press the Help button in the lower right corner and follow the instructions.

Welcome to the Flickr Uploader Plug-in

This plug-in makes it possible for you to upload your images directly to Flickr from ACDSee.

Authorizing

Before you can upload to Flickr, you need to authorize the ACDSee Flickr Uploader with the Flickr website. Of course, you also need a Flickr account. Once that is done, you can upload your files quickly and easily from within ACDSee.

Flickr uses Yahoo IDs as part of their registration process. If you do not have a Yahoo ID, you need to create one too.

Summary of the Process:

1. Create a Yahoo ID if you do not have one.
2. Create a Flickr account if you do not have one.
3. Authorize ACDSee Flickr Uploader.
4. Upload photos.



Flickr only accepts certain file formats. If you try to upload files that Flickr does not support, those files won't upload.

Authorizing ACDSee with Flickr

Before you can upload to Flickr, you need to authorize ACDSee with the Flickr website.

You can authorize and upload your first set of pictures at the same time.

(The following procedure assumes that you already have a Flickr account. If you do not have an account, see [Creating a Flickr account.](#))

To Authorize the Uploader:

1. In Manage mode, in the File List pane, select the images you want to upload.
2. Click **File | Send | Upload to**.
3. In the Upload Manager dialog, select **Flickr**, and then click **Next**.
4. Click **Remember me** if you want this computer to keep a record of your authorization.
5. In the Flickr Uploader dialog, click **Authorize**.



The Flickr website opens.

6. Enter your Yahoo ID and password and click **Sign In**.



A message on a yellow background tells you that the uploader wants to link to your Flickr account.

7. Click the **Ok, I'll Allow it** button.



A message tells you that you have authorized the ACDSee Flickr Uploader.

8. Close the web page by clicking the red **X** in the top right-hand corner.



Behind the web page is a small dialog.

9. Click **Continue** to begin uploading the photos you selected.



The ACDSee Flickr Uploader Settings dialog opens. You can adjust the settings to resize your photos, select where you would like the title, description, and tags, for each photo to come from, as well as privacy, safety, and content type. (See [Editing default settings](#) for details.)

10. Adjust the settings and click **Save Settings**.
11. You can type in and add the tags for this set of photos.
12. When you are ready, click **Next** and then **Upload now!**.



A progress bar shows your photos uploading.

Creating a Flickr Account

If you do not have a Flickr account, you need to create one before you use the Uploader. Once you have created a Flickr account, you then [authorize](#) the ACDSee Flickr Uploader, and upload your pictures.

(Flickr uses Yahoo IDs for their registration process. If you do not have a Yahoo ID, you need to create one first. To create a Yahoo ID, click [here](#).)

To go directly to Flickr, click [here](#).

Uploading Images

To Authorize and Upload Images to Flickr for the First Time:

1. In Manage mode, in the File List pane, select the images you want to upload.
2. Click **File | Send | Upload to**.
3. In the Upload Manager dialog, in the **Select a service to upload to** box, select **Flickr** and then click **Next**.



The Flickr Uploader dialog opens.

4. Click **Authorize**.



You are asked if you have a Yahoo ID and Password.

5. Do one of the following:
 - If you have a Flickr ID and password, enter the information, and then click **Sign In**.
 - If you don't have a Flickr username and password, click on Register and create a Yahoo username and Flickr account.



A Flickr page opens with a yellow banner asking if you want to authorize the ACDSee Flickr Uploader.

6. Click **Ok, I'll Allow It**.



A check mark appears to tell you that you have authorized the ACDSee Flickr Uploader.

7. Close the web page by clicking the red **X** in the top right-hand corner.



Behind the web page is a small dialog.

8. Click **Continue** to begin uploading the photos you selected.
9. You can type in, and add the tags for this set of photos.
10. If you want to see your images in Flickr, ensure that the **View images in Flickr** checkbox is selected.

11. When you are ready, click **Next** and then **Upload now!**.



The ACDSee Flickr Uploader Settings dialog opens. You can adjust the settings to resize your photos, select where you would like the title, description, and tags, for each photo to come from, as well as privacy, safety, and content type. (See [Editing default settings](#) for details.)



A progress bar shows your photos uploading.

12. Click **Finish**.



Flickr opens showing a message: "Your photos were uploaded successfully."

13. Click **OK**.



Your photos display on the Flickr site.

To Upload Images to Flickr Once You are Authorized:

1. In ACDSee, select the images you want to upload.
2. In the Browser, do one of the following:
 - On the menu bar, click **File | Upload to**.
 - On the toolbar, click **Upload to**.
 - Right-click and select **Upload to**.
3. In the Upload Manager dialog, in the **Select a service to upload to** box, select **Flickr** and then click **Next**.
4. To select a set for your photos, click the down arrow and select the set you want. To create a new set, click, **Create Set**, type in a name and description, then click **Create**.
5. To apply a tag to this group of photos, type in the tag, and click **Add Tag**.



These tags are applied to ALL the selected photos. You can apply tags to individual photos in the next dialog.

6. When you are ready, click **Next**.



In this dialog, you can add individual titles, descriptions and tags to each photo, rotate the photos, or apply batch information and resizing.

7. To rotate a photo, click the arrows to select it and then click **Rotate**.
8. To create individual titles, descriptions, and tags, click the arrows to select the picture, and then click the **Title/Description/Tags** icon.
9. To [rotate, resize or add information](#) to the photos, adjust the settings.

10. Click **Upload Now!**
11. If you want to see your images in Flickr, ensure that the **View images in Flickr** checkbox is selected.



A progress bar shows your photos uploading.

12. Click **Finish**.



Flickr opens showing a list of your photos. You can add titles and descriptions or notes about each photo.

To Upload Images to Flickr Privately:

To make uploaded photos visible only to yourself, ensure that your **Flickr** account has its privacy settings set to **Private**, and then set your **Privacy** setting within ACDSee to **Follow your Flickr account settings**. This will ensure your photos are uploaded privately. For more information, see [Editing Default Settings](#).

Tagging Images

Tagging makes it easier to find your photos or images as you can search for them by the tags. You can tag batches of photos as you upload them to Flickr while you are in the Flickr Uploader dialog.

To Tag Photos:


1. In the Flickr Uploader dialog, type a tag into the box below **Apply these tags to this batch**.
2. Click **Add Tag** and the new tag appears in the box below.
3. To delete a tag, click the red **[X]** beside it.

Editing Default Settings

You can change many of the default settings in the uploader, including whether or not to resize your photos as you upload, giving them a title, or changing the privacy, safety, and content type settings. These settings are based on Flickr settings, which you can read about [here](#).

Flickr Uploader Settings

Revoke Authorization	Click to revoke your authorization on the Flickr site.	
Resizing	Do not resize	Select to upload your images as they are. (If a photo exceeds the limit allowed by your account, you need to resize it to below this limit. If you do not, a warning displays to ask if you want to resize the file.)
	Set max horizontal or vertical size (pixels)	Select to resize your images to the following sizes: <ul style="list-style-type: none"> • 800 pixels (suitable for web viewing) • 1280 pixels (suitable for small prints) • 1600 pixels (suitable for larger prints) • 2400 pixels (suitable for archiving)
Title Description, and Tags	Get title from:	Select to take the title of each picture from one of the following: <ul style="list-style-type: none"> • Filename (default) • IPTC Headline • ACDSee Caption (works only if you have created these in the ACDSee database.)
	Get description from:	Select to take the description of each picture from one of the following: <ul style="list-style-type: none"> • IPTC Caption (default) • ACDSee Notes (works only if you have written descriptions in the Notes field in ACDSee.) • ACDSee Caption (works only if you have created these in the ACDSee database.) • EXIF Image Description
	Get tags from:	Select to include additional tags from the following: <ul style="list-style-type: none"> • IPTC Keyword (always added) • ACDSee Keywords • IPTC Category • IPTC Supplemental categories
Photo Privacy Settings	Follow your Flickr account settings	Sets your privacy setting to follow your Flickr account's settings.
	Visible to you and friends	Sets your privacy setting to display your photos only to yourself and friends.


	Visible to you and family	Sets your privacy setting to display your photos only to yourself and family.
	Visible to you, friends and family	Sets your privacy setting to display your photos only to yourself, friends, and family.
	Visible to anyone (Public)	Sets your privacy setting to display your photos to the public, allowing anyone to view your photos.
	 To make uploaded photos visible only to yourself, ensure that your Flickr account has its privacy settings set to Private , and then set your Privacy setting within ACDSee to Follow your Flickr account settings .	
Safety Level	Safe	Select if your images suitable for the general public.
	Moderate	Select if you are not sure if your images are suitable for the public, but do not need to be actively restricted.
	Restricted	Select if your images should not be seen by children.
Content Type	Photos	Select to upload photos. This allows other users to filter their searches, making it easier to find the content they need.
	Screen shots	Select to upload screen shots. This allows others to filter their searches on screen shots specifically.
	Art, Illustration, CGI, or other non-photographic images	Select to upload other types of images. This allows others to filter their searches and find specific images types.
Hide my uploaded images from public searches	Select if you do not want your photos to be included in public searches.	

Adjusting and Adding Information to Your Photos


On the final screen of the uploader, there are several different adjustments that you can make to your photos. These include:

- Rotating photos.
- Adding a title, description and tags.
- Adding batch information.
- Resizing photos.

To rotate photos:

1. Use the arrows on the far right to find the photo you want to rotate.
2. Click the photo to select it.
3. Click the left or right **Rotate** arrows .

To add a title, description, and tags:

1. Use the arrows on the far right to move to the photo you want to adjust.
2. Click the photo to select it.
3. Click the **Title/Description/Tags** icon .
4. In the **Title** field, type in the title for this photo.
5. In the **Description** field, type in a short description.
6. In the **Tags** field, type in a tag and click **Add**. (Click the red **[X]** to delete a tag.)

Batch information and resizing

You can set up batch information by editing the default settings, or selecting settings in the final dialog before you upload your photos. When you select these settings, the information for each photo is taken from the file and displayed on Flickr. In most cases, you need to create the file information on the Properties pane in ACDSee first.

You can also set batch resize information for your images in both the settings and the uploader dialogs. As you upload, the images are resized.

To set batch information for each photo:

1. To set the source for the title of each image, click the **Get title** drop-down list and select from the following:
 - **Filename** - the title of each photo is taken from the filename.
 - **IPTC Headline** - the title for each photo is taken from the IPTC Headline field on the IPTC tab of the Properties pane. If you have not created this information, the title will be blank.
 - **ACDSee Caption** - the title for each photo is taken from the Caption field on the Metadata tab of the Properties pane. If you have not created the captions in ACDSee, the title will be blank.
2. To set the source for the description of each photo, click the **Get description** drop-down list and select from the following:
 - **IPTC Caption** - the title for each photo is taken from the Caption field in the Properties pane. If you have not created the captions, the description will be blank.
 - **ACDSee Notes** - the title for each photo is taken from the Notes field on the Metadata tab of the Properties pane. If you have not created notes in ACDSee, the description will be blank.

- **ACDSee Caption** - the title for each photo is taken from the Caption field on the Metadata tab of the Properties pane. If you have not created the captions in ACDSee, the description will be blank.
 - **Exif Image Description** - the title for each photo is taken from the Image Description field on the EXIF tab of the Properties pane. If you have not created the EXIF Image Description in ACDSee, the description will be blank.
3. To include tags from the ACDSee Keywords, IPTC Category, and IPTC Supplementary categories, click the checkboxes.

To set batch resizing:

1. In the Batch Resize box, select **Set max horizontal or vertical size (pixels)**.
2. Select the size you want your photos to be.

Creating a Contact Sheet

You can create contact sheets—thumbnail previews of your images arranged on pages — that you can use to organize and share your images. You can use the Create Contact Sheet utility to save your contact sheets in multiple image formats, and as HTML image maps. You can save your options as a [preset](#) for future use.

The size of the thumbnails depends on how many columns and rows the contact sheet displays, and how much space is displayed between them.

To Create a Contact Sheet:

1. In Manage mode, in the File List pane, select the images you want to include.
2. Click **Tools | Create | Contact Sheet**.
3. In the Contact sheet format area, set the Contact sheet format options.
4. In the Output Settings area, set the Output Settings options.
5. If desired, add or change the text on the page.
6. Click **OK**.



If you do not specify an output file path, the Create Contact Sheet utility places a file named **Contact Sheet.<ext>** in your default image folder. For multiple-page contact sheets, the utility adds a number to the file name; for example, **Contact Sheet3.bmp**.

Contact Sheet Format Options

Thumbnail settings

Size	Specifies the number of columns and rows to create on each page.
Spacing	Creates a frame around each thumbnail. Specifies the amount of space between rows or columns. In the Horizontal and Vertical spin boxes, type a value to indicate the amount of space to display.

Frame options

Use thumbnail frame	Creates a frame around each thumbnail.
Margin	Specifies the width of the frame.
Solid color	Specifies the frame's color. Click the color picker to define a color.
Tiled image	Specifies an image to use as a frame. Click Browse to locate the image you want to use.

Thumbnail options

Colored drop shadow	Creates a drop shadow effect around each thumbnail. Click the color picker to define a color.
Colored edge fade	Creates a fading frame effect around the image. Click the color picker to define a color.
Colored matte	Uses a solid color as a background for the page. Click the color picker to define a color.
Beveled edges	Creates a beveled edge effect on each thumbnail. This effect is not displayed in the Preview window.

Page background options

Solid color	Uses a solid color as a background for the page. Click the color picker to define a color.
Tiled image	Uses a tiled image as the background for the page. Click Browse to locate the picture you want to use.

Creating Archives of Your Files

You can use the Archive Creator plug-in to create archives of your images, documents, and media files. Archive Creator supports multiple archive formats, and helps you manage your files using

compression, encryption, and password protection tools.

To Create an Archive:

1. In Manage mode, in the File List pane, select a folder or group of files.
2. Click **Tools | Create | Archive**.
3. In the Create Archive dialog box, in the Options area, click the **Archive Type** drop-down list and select the archive format you want to create.

Some archive formats have additional settings that you can adjust by clicking the **Settings** button.

4. Do any of the following:
 - To include the contents of any subfolders you selected, check the **Include subfolders** checkbox.
 - To include any hidden files in your archive, check the **Include hidden files** checkbox.
 - To remove the selected files and folders from your hard drive once they have been added to the archive, check the **Delete files after archiving** checkbox.
 - To protect the contents of your archive with a password, check the **Password Protect Archive** checkbox, and type a password into the field beside it. Note that not all archive types support passwords, and some formats require them.
5. Type a path and file name into the **Output File** field, or click **Browse** to locate a folder on your hard drive.
6. Select one of the following:
 - **Add to existing archive:** adds your files to an existing archive. This option is only available if the archive specified in the Output File field already exists.
 - **Overwrite existing archive:** replaces any existing archive with the archive you are creating. This option is only available if the archive specified in the Output File field already exists.
7. When you are satisfied with your choices, click **Create** to begin archiving your files.

Extracting Archives

You can extract archives very quickly and easily without leaving ACDSee. You can either extract the files to a folder or simply double-click and view them.

To Extract an Archive to a Folder:

1. In Manage mode, navigate to the folder containing the archive, [using the Folders pane](#).
2. Click the archive in the File List.
3. Click **Edit | Extract to Folder**.

4. In the Extract to Folder dialog, navigate to, and select the folder where you want to keep the files.
5. To create a new folder, click **Create Folder**, type in the name of the folder and then press **Enter**.
6. Use the **Overwriting duplicate files** drop-down list if you want to specify what do so with files in the folder that have the same name as those you are extracting. You can select any of the following:
 - **Ask**: to be asked what to do about each individual file.
 - **Rename**: duplicates are given a new name.
 - **Replace**: duplicate files are overwritten.
 - **Skip**: no duplicates are extracted.
7. Click **OK**.

To View Files Inside an Archive:

1. In Manage mode, navigate to the folder containing the archive.
2. Double-click the archive.

Thumbnails of the contents of the archive open in the File List pane.

Printing Images

With the ACDSee Home print utility, you can print your files on any size of paper, in any orientation, and at any resolution your printer can support. You can also use the print utility to create and print contact sheets, complete with headers, footers, and captions specific to each image.

As you change the options in the Print dialog box, you can view a dynamically updated preview of the file and its position on the page. You can adjust the output size, print multiple copies of each file or image, and change the orientation of images and documents on each page.



You can use the shortcut **Ctrl + P** to launch the print dialog.

To Print Your Images:

1. Select the images you want to print.
2. Do one of the following:
 - In Manage mode, click **File | Print**.
 - In View mode, click **File | Print All Images**. (If you want to [print a single image in View mode](#), select **Print Image**.)

3. Under Print layout, do one of the following:
 - Select **Full page** and then choose a print size from the **Format** list.
 - Select **Contact sheet** and then set the **Contact sheet format** options to define the appearance of your [contact sheet](#).
 - Select **Layout** and then choose one of the available layout options.
4. On the **Printer Options** tab, [specify the printer](#) you want to use, the paper size, the orientation, the number of copies you want, the range of pages that you want to print, and image resolution.
5. On the **Page Settings** tab, [specify the image position](#) on the paper and the margin widths.
6. On the **Adjustments** tab, [specify any adjustments](#) you want to apply.
7. Specify the number of prints of each photo. If you are printing a **Full page** or a **Contact sheet** this option is available on the **Page Settings** tab. If you are printing a **Layout** this option is available below the list of layouts.
8. Add [captions, headers, or footers](#). You can only add captions, headers, or footers if you are printing a **Full page** or a **Contact sheet**.
9. Click **Print**.

Setting Printer Options

When printing your images with ACDSee, you can specify which printer you want to use, and set the printer options on the **Printer Options** tab in the Print dialog box.

Printer Options

Printer	Specifies the printer you want to use. Select a printer from the drop-down list and click the Properties button to set its options. Refer to the printer manufacturer's Help file or manual for more information.
Paper size	Specifies the size of the paper, e.g. Letter, Legal, A4.
Orientation	Specifies Portrait or Landscape page orientation.
Copies	Specifies the number of copies you want to print.
Print range	<p>Select one of the following options:</p> <ul style="list-style-type: none"> • All: prints all of the pages in the document. • Pages from: prints a range of pages. Specify the first and last pages of the range in the fields.
Resolution	Specifies a resolution in pixels-per-inch (PPI) for the image. The higher the value, the more dots per inch, and the higher the resolution of the printed image. For example, 600 PPI is 360,000 (600 x 600) pixels per square inch.
Filter	<p>Specifies the resampling filter to use when printing images. Click the drop-down list and select one of the following:</p> <ul style="list-style-type: none"> • Box: displays considerable tiling or jaggies when you resize an image. • Triangle: produces good results for image reduction and enlargement, but displays sharp transition lines. • Bicubic: produces good results with photo-realistic images and with images that are irregular or complex. Uses interpolation to minimize the raggedness normally associated with image expansion. • Bell: smoothes the image. • B-Spline: produces smooth transitions, but may cause excessive blurring. • Lanczos: produces the sharpest images, but may also introduce some ringing artifacts. • Mitchell: produces smooth transitions when enlarging photo-realistic images. This filter is good compromise between the ringing effect of Lanczos and the blurring effect of other filters.
Gamma	Applies gamma correction to the printed images. Type a number from 0.10 to 3.00 in the Gamma value field to adjust the gamma of the image. Higher values make the image appear brighter, while lower values make the image appear darker.
Use EXIF 2.2 printing when available	Your camera may capture EXIF information that, when shared with your printer, will optimize printing results. Select this option if your camera and printer support EXIF 2.2 printing.

Creating Custom Print Layouts

You can create your own custom print layouts and store them as print options.

To Create a Custom Print Format:

1. In the Print dialog box, select **Full page**.
2. In the Print format area, click **Add**.
3. In the Add Custom Format dialog box, select a measurement unit from the **Measurement units** drop-down list.
4. Enter the dimensions for the new format in the **Format width** and **Format height** fields.
5. Click **Add**.

Setting Image Size and Positioning



You can use the Page Settings tab in the Print dialog box to adjust and control the size of the images you are printing, and the positioning of images on each page.

Page Settings Options

Page position	Specifies where to place the image on each page.
Margins	Specifies the size of the margins. Type a value or click the arrows in the Top , Bottom , Left , and Right spin boxes.
Number of prints	Specifies how many copies of each image to print. The print utility adds pages as required.
Automatically rotate picture based on print format	Specifies whether you want the print utility to determine automatically which orientation to use for each image. If you check the checkbox, the print utility changes each page's orientation to best suit the image you are printing.
Maintain aspect ratio	<p>Specifies whether you want the print utility to maintain the original image's aspect ratio. Select one of the following options to indicate how the print utility should handle the aspect ratio for oversized images:</p> <ul style="list-style-type: none"> • Crop image to fit print format: prints only the part of the image that fits within the print format. • Shrink image to fit print format: prints the entire image, reduced to fit inside the print format.

Setting Print Adjustments

You can use the settings on the Adjustments tab of the Print dialog to compensate for quirks specific to your printer, such as the way your printer handles exposure.

-  It is recommended that you adjust these settings only after printing initially, when you know what corrections your printer may require.
-  Please note that any adjustments made on the Adjustments tab will not be reflected in the Preview window.

To Apply Adjustments to Images Prior to Printing:

1. Select the image or images you want to print.
2. Do one of the following:
 - In Manage mode, click **File | Print**.
 - In View mode, click **File | Print Image** or **File | Print All Images**.
3. In the Print dialog, on the Adjustments tab, adjust the Exposure, Contrast, or Sharpness sliders as desired.
4. Click **Print**.

Adding Text to Pages

You can add headers and footers to pages, and captions beneath your images.

To Add Captions to Your Printed Images:

1. In the [Print](#) dialog box, click the **Caption** tab.
2. Select **Use caption text**.
3. Click **Font** to open the Font dialog box and set the font options.
4. In the text box, type the text you want the caption to display.
5. Click **Insert Metadata** to insert file-specific information into the caption for each image.
6. In the **Text alignment** drop-down list, select the caption positioning.
7. To set the maximum number of text lines for each caption to display, check the **Number of lines** checkbox, and then specify a number in the field.

To Add Headers and Footers to Your Printed Pages:

1. Do one of the following:
 - Click the **Header** tab and select **Use header text**.
 - Click the **Footer** tab and select **Use footer text**.
2. Click **Font** to open the Font dialog box and set the font options.
3. In the text box, type the text you want the header or footer to display.
4. To insert the current page number or the total number of pages into the text, click **Insert Page Number**, and then select an option from the menu.
5. In the **Text alignment** drop-down list, select the header or footer positioning.
6. To set a maximum number of text lines, check the **Number of lines** checkbox, and then specify a number in the field.

Setting Contact Sheet Printing Options

The Contact sheet format area of the print utility contains settings you can adjust to control the appearance, layout, and size of your thumbnails. If you saved your format options as a [preset](#) you can select the preset.

Contact Sheet Format Options

Thumbnail settings

Size	Specifies the number of columns and rows to create on each page.
Spacing	Specifies the amount of space between rows or columns. In the Horizontal and Vertical spin boxes, type a number to indicate the amount of space to display.

Frame options

Use thumbnail frame	Creates a frame around each thumbnail.
Margin	Specifies the width of the frame.
Solid color	Specifies the frame's color. Click the color picker to define a color.
Tiled image	Specifies an image to use as a frame. Click Browse to locate the image you want to use.

Thumbnail options

Colored drop shadow	Creates a drop shadow effect around each thumbnail. Click the color picker to define a color.
Colored edge fade	Creates a fading frame effect around the image. Click the color picker to define a color.
Colored matte	Creates a matte effect around each thumbnail. Click the color picker to define a color.
Beveled edges	Creates a beveled edge effect on each thumbnail. This effect is not displayed in the Preview window.

Page background options

Solid color	Prints a solid color as a background for the page. Click the color picker to define a color.
Tiled image	Prints a tiled image as the background for the page. Click Browse to locate the image you want to use.

About Batch Editing

In ACDSee you can make one type of edit to many images. For example, if you need to resize multiple images you can use the Batch Resize tool. Or, if you need to rotate multiple photos by 90 degrees you can use the Batch Rotate/Flip tool.

You can speed up the batch editing workflow by tagging your files. For example, you can quickly tag the files you want to change, then click **Tagged** in the Catalog pane to display all the tagged files in the File List pane. Then you can select the files and choose a batch tool.

Using AI Super-Resolution

AI Super-Resolution enhances the quality of your images by using advanced algorithms to intelligently upscale lower-resolution photos. This feature increases the resolution and detail of your images, making them sharper and more defined without compromising quality. Whether you're enlarging a small photo or improving the clarity of a digital image, AI Super-Resolution helps you achieve professional results with ease.

! DirectX 12 feature level 12_0 or higher is required for AI Features to run on your GPU. You can check your GPU's support level by running the dxdiag.exe tool and reviewing the Display tab or by looking up your device's official specifications. If your GPU doesn't meet the requirements, AI Features will still run using your CPU instead. A minimum of 4GB VRAM is required for GPU acceleration for AI Super-Resolution.

How AI Super-Resolution Works:

AI Super-Resolution enhances image quality by analyzing patterns, textures, and colors in the image. It then applies a complex algorithm to upscale the image, reducing noise and blurriness, removing artifacts, and adding pixels where necessary to maintain clarity and detail. This feature is especially useful for enlarging small images or zooming into cropped photos.


Examples of when to use AI Super-Resolution:

- Enlarging low-resolution images for large prints or displays
- Enhancing cropped images to improve their quality
- Increasing the size of older photos taken with lower-resolution cameras

How to apply AI Super-Resolution:

To enhance your images with **AI Super-Resolution**, perform the following:

1. Find the image you want to enhance in **Manage mode** or **View mode** and do one of the following:
 - Right-click it and select **AI Features | AI Super-Resolution**.
 - Press **Shift + Alt + S**.
2. In the **AI Super-Resolution** dialog, choose your preferred settings. The preview will automatically generate a new preview whenever parameters are changed so you can always see what it looks like in real-time.
3. Click **Enhance** to apply Super Resolution to your image. The enhanced image will be saved by default into the same folder as the original. You can adjust this setting within **Options** at the bottom of the **AI Super-Resolution** dialog.



How to apply Batch AI Super-Resolution:

To enhance multiple images at once with **AI Super-Resolution**, perform the following:

1. Find the images you want to enhance in **Manage mode** and do one of the following:
 - Select the images you want, right-click one of them and select **Batch | AI Super-Resolution | AI Super-Resolution**.
 - Select **Tools | Batch | AI Super-Resolution | AI Super-Resolution**.
 - Right-click on an image and select **Batch | AI Super-Resolution | AI Super-Resolution**.
 - Press **Shift + S**.

- In the **Batch AI Super-Resolution** dialog, choose your preferred settings. The preview will automatically generate a new preview whenever parameters are changed so you can always see what it looks like in real-time.



Only the first image selected will display in the **Preview** when applying **AI Super-Resolution** to multiple images.

- Click **Enhance** to apply Super Resolution to your images. The enhanced images will be saved by default into the same folder as the originals. You can adjust this setting within **Options** at the bottom of the **Batch AI Super-Resolution** dialog.

Settings:

There are five option settings that are available no matter which measurement mode you use:

Show Original	Shows the original image before any modifications for quick comparison.
AI Strength	Adjust the slider to increase or decrease the amount of influence the AI has in the enhancement.
Zoom	Adjust the zoom of the current preview display.
Actual Size	Sets the preview display to show the Actual Size of the image.
Fit Image	Sets the preview display to fit the image within the preview window.

Resize Options:

There are five different resize options you can use to determine how big your image will become. For more information, see [Setting the AI Super-Resolution Options](#).

Percentage	Includes Width (%), Height (%), and Preserve Original Aspect Ratio.
Size in Pixels	Includes Width (px), Height (px), Preserve Original Aspect Ratio, and Fit Within. Fit Within includes: Width and Height, Width Only, Height Only, Width or Height (largest image).
Print Size	Includes Width, Height, Units, Resolution (pixels per inch), Preserve Original Aspect Ratio, and Fit Within. Fit Within includes: Width and Height, Width Only, Height Only, Width or Height (largest image).
Long Edge	Includes Size (Pixels, Inch, cm, mm), and Resolution (pixels per inch).
Short Edge	Includes Size (Pixels, inch, cm, mm), and Resolution (pixels per inch).

Converting Multiple Images to Another File Format

You can convert multiple images to any supported file format. You can set the options for each format individually, specify how to handle multiple-page images, and apply the conversion defaults automatically.


Conversion Status

When converting assets in ACDSee Photo Studio Home 2026, you can track their status, pause, or cancel them from the Activity Manager. For more information see [ACDSee Activity Manager](#).


To Convert Images to Another File Format:

1. Do one of the following:
 - In Manage mode, select one or more images, and click **Tools | Batch | Convert File Format | Convert...**
 - In View mode, click **Tools | Modify | Convert File Format | Convert...**
 - In Manage mode, select one or more images, and click **Batch | Convert File Format | Convert...**
 - In Manage or View mode, select one or more images and press **Ctrl + Alt + F**.
2. In the Convert File Format dialog, select a new format for your image or images from the Output File Format drop-down list. To configure format-specific options, select the file format and then press the **Settings** button.
3. In the Output Location section, identify where you want to place the converted images.
4. In the File Options section, specify how you want the tool to handle any file name conflicts by selecting one of the following options from the **Overwrite existing files** drop-down list:
 - **Ask:** prompts you when overwriting a file.
 - **Skip:** cancels the operation if there is a file with the same file name and extension.
 - **Replace:** overwrites the file without prompting for confirmation.
 - **Rename:** prompts you to rename the file.
5. You can set additional options in the File Options section:
 - **Preserve last-modified dates:** Preserves the last-modified dates in the new files after conversion.

- **Delete original files:** Deletes the original files after conversion.
 - **Do not delete original files when output files cannot preserve metadata:** Does not delete the original files if the output is unable to preserve the metadata.

 Metadata and color profiles can be permanently lost when converting to a file format that does not support them if **Do not delete original files when output files cannot preserve metadata** is disabled.

- **Preserve metadata:** Ensures the metadata from the original files remain in the converted files.
 - **Preserve database information:** Ensures the database information from the original files remain in the converted files.
6. To configure vector settings and how you want to handle any multi-page images, press the **Advanced Settings** button. If you did not select any multi-page images to convert, and did not specify a multiple-page image format as your output file format, you can skip the options in the Multi-Page Source section.
 7. Click **Convert**.

 You can save your settings as a preset for future use. After configuring the Convert File Format dialog settings, press the **Save** icon next to the Preset field. You will be prompted to enter a name for your preset. It is recommended that you give your preset an intuitive name. Saved presets will be listed in the Convert File Format fly-out menu.

 You can give your saved presets custom shortcuts for quick conversions. In the [Customize Shortcuts](#) dialog, you can find your presets under the Preset - Convert File Format category.

Rotating or Flipping Multiple Images

You can rotate or flip multiple images at preset angles.

To Rotate or Flip an Image:

1. In Manage mode, select one or more images, and then click **Tools | Batch | Rotate/Flip**.
2. In the Batch Rotate/Flip Images dialog box, select the angle of rotation you want to apply. See below for an explanation of each angle.
3. If you select an image with multiple pages and want to apply the selected angle of rotation to all of the pages, check the **Apply to all pages of the current image** checkbox.
4. Do one of the following:
 - Click **Next Image** to move on to the next selected image. The **Next Image** button is not available if the **Apply to all selected images** box is checked.

- If you select multiple images and you want to apply the same angle of rotation to all of them, check the **Apply to all selected images** checkbox.
- Click **Options** to specify how you want to save and store the images.

5. When you are ready to apply the rotations to your images, click **Start Rotate**.

Rotate / Flip Angles



Rotates the image counter-clockwise 90 degrees.



Rotates the image 180 degrees.



Rotates the image clockwise 90 degrees.



Rotates the image according to any EXIF data contained within the image (based on what the camera thinks the orientation should be).



Flips the image along the vertical axis.



Flips the image along the horizontal axis.



Flips the image along the vertical axis, and then rotates it counter-clockwise 90 degrees.



Flips the image along the vertical axis, and then rotates it clockwise 90 degrees.



You can also use the Rotate tool in Edit mode to rotate an image using a custom angle of rotation.

Setting Rotated and Flipped File Options

You can change the settings in the Batch Image Rotate/Flip Options dialog box to control where ACDSee Home places modified images, how to handle file duplication conflicts, and specify whether you want to preserve the last-modified date of the file when you use the Batch Rotate/Flip Images tool.

To Set the Rotate and Flip Options:

1. In Manage mode, select one or more images, and then click **Tools | Batch | Rotate/Flip**.
2. In the Batch Rotate/Flip Images dialog box, click the **Options** button.
3. Set the options as described below.
4. Click **OK**.

Rotate and Flip Options

Force lossless JPEG operations	Rotates JPEG images without decompressing and re-compressing the JPEG information. As a result, the image does not lose quality when rotated or flipped.
File options	<p>Specifies where to place the new images. Select one of the following options:</p> <ul style="list-style-type: none"> • Remove/replace original files: overwrites the original file with the new image. • Rename modified images and place in source folder: adds identifying labels to the image names and places them in the same folder as the originals. • Place modified images in the following folder: places the converted image in a folder that you can specify. Click the Browse button and select a folder.
Overwrite existing files	<p>Determines how ACDSee Home should handle overwriting files. Select one of the following options from the drop-down list:</p> <ul style="list-style-type: none"> • Ask: prompts you when overwriting a file. • Skip: cancels the operation if there is a file with the same file name and extension. • Replace: overwrites the file. • Rename: prompts you to rename the file.
Preserve last-modified dates	Retains the date and time properties of the file.
Remember and apply the last rotation performed	Automatically applies the same settings the next time you rotate an image.
Auto-close progress dialog if all operations succeed	Automatically closes the dialog box after all images have been adjusted.
Save current settings as default	Stores the current settings and applies them the next time you use the Rotate/Flip Images wizard.

Resizing Multiple Images

You can resize multiple images at once using the batch resize tool.

Resize Status

When resizing files in ACDSee Photo Studio Home 2026, you can track their status, pause, or cancel them from the Activity Manager. For more information see [ACDSee Activity Manager](#).

To Resize Multiple Images:

1. Do one of the following:
2. In Manage mode, select one or more images, and then click **Tools | Batch | Resize | Resize...**
3. In the Resize dialog box, you can choose from multiple ways to resize your images. Choose either Size in Pixels, Percentage, Print Size, Long Edge, or Short Edge. Follow the directions in the table below.
4. Click **Options** to specify how you want to save and store the images.
5. Click **Resize**.



You can save your resize settings as a preset by clicking the save icon beside the preset drop-down. From there, enter a name and press **OK**. To delete a preset, press the trash icon.



You can assign shortcuts to speed up your process of resizing multiple images by following the directions in the [Customizing Keyboard Shortcuts](#) topic.

Resize Options

Resize Method	Setting	Explanation
Size in Pixels		
	Width	Enter a new width for the images in pixels.
	Height	Enter a new height for the images in pixels.
	Resize	<p>Choose how to scale the images. Select one of the following options:</p> <ul style="list-style-type: none"> • Enlarge or Reduce: resizes all images to the specified height and width. • Enlarge only: resizes only those images that are smaller than the specified height and width. • Reduce only: resizes only those images that are larger than the specified height and width.
	Preserve original aspect ratio	Check this box to keep the width-to-height ratio of the original images.
	Fit within	Specifies whether the aspect ratio is maintained based on the specified width. For more information about how the different combinations affect the images, see Pixel resize options and resulting action .
Percentage		
	Width	Enter a new width for the images as a percentage of the original image.
	Height	Enter a new height for the images as a percentage of the original image.
	Preserve original aspect ratio	Check this box to keep the width-to-height ratio of the original images.
Print Size		
	Units	Choose from inches, cm (centimeters), mm (millimeters), or pixels.

Resize Method	Setting	Explanation
	Width	Enter a new width for the images in pixels.
	Height	Enter a new height for the images in pixels.
	Resolution	Enter a resolution for the images in pixels per inch.
	Resize	<p>Choose how to scale the images. Select one of the following options:</p> <ul style="list-style-type: none"> • Enlarge only: resizes only those images that are smaller than the specified height and width. • Reduce only: resizes only those images that are larger than the specified height and width. • Enlarge or reduce: resizes all images to the specified height and width.
	Preserve original aspect ratio	Check this box to keep the width-to-height ratio of the original images.
	Fit within	Specifies whether the aspect ratio is maintained based on the specified width. For more information about how the different combinations affect the images, see Pixel resize options and resulting action .
Long Edge		
	Size	Enter a size in units, and choose the units from the drop-down menu. There, you can choose from inches, cm (centimeters), mm (millimeters), or pixels.
	Resolution	Enter a resolution for the images in pixels per inch.
	Resize	<p>Choose how to scale the images. Select one of the following options:</p> <ul style="list-style-type: none"> • Enlarge only: resizes only those images that are smaller than the specified height and width. • Reduce only: resizes only those images that are larger than the specified height and

Resize Method	Setting	Explanation
		width.
		<ul style="list-style-type: none"> • Enlarge or reduce: resizes all images to the specified height and width.
Short Edge		
	Size	Enter a size in units, and choose the units from the drop-down menu. There, you can choose from inches, cm (centimeters), mm (millimeters), or pixels.
	Resolution	Enter a resolution for the images in pixels per inch.
	Resize	<p>Choose how to scale the images. Select one of the following options:</p> <ul style="list-style-type: none"> • Enlarge only: resizes only those images that are smaller than the specified height and width. • Reduce only: resizes only those images that are larger than the specified height and width. • Enlarge or reduce: resizes all images to the specified height and width.
Options		
	Output Location	<p>Choose an output location from the options:</p> <ul style="list-style-type: none"> • Remove/replace original files: this option overwrites your original files. • Same as source folder: pastes the resized files in the folder they originated. • Specific folder: use the folder icon to navigate to a specific folder for the output files. • Create subfolder: with an output location selected, check this checkbox to create a subfolder for your resized images. Enter a name in the box. This is useful if you are making multiple batch resizes to specific

Resize Method	Setting	Explanation
		dimensions. You can save your resized files in separate folders.
	File options	<p>Choose your file options for overwriting existing files.</p> <p>Choose whether to preserve certain file information when resizing.</p> <p>Choose your JPEG Compression options, find out more in the JPEG Options topic.</p> <p>Choose your resample type from the following options:</p> <ul style="list-style-type: none"> • Lanczos: produces the sharpest images, but may also introduce some ringing artifacts. • Bell: smoothes the image. • Bicubic: produces good results with photo-realistic images and with images that are irregular or complex. Uses interpolation to minimize the raggedness normally associated with image expansion. • Box: displays considerable tiling or jaggies (jagged edges) when you resize an image. • B-spline: produces smooth transitions, but may cause excessive blurring. • ClearIQZ: slower than Bicubic and Lanczos, but produces the best results when enlarging photos, especially those of people. • Mitchell: produces smooth transitions when enlarging photo-realistic images. This filter is good compromise between the ringing effect of Lanczos and the blurring effect of other filters. • Triangle: produces good results for image reduction and enlargement, but displays sharp transition lines.

Setting File Options

You can change the settings in the Options dialog box to control where ACDSee Home places modified images, how to handle file duplication conflicts, and specify whether you want to preserve the last-modified date of the file.

File Options

File options	<p>Specifies where to place the new images. Select one of the following three options:</p> <ul style="list-style-type: none"> • Remove/replace original files: overwrites the original file with the new image. • Rename modified images and place in source folder: adds identifying labels to the image names and places them in the same folder as the originals. • Place modified images in the following folder: places the converted image in a folder that you can specify. Click the Browse button and select a folder.
Overwrite existing files	<p>Determines how ACDSee Home should handle overwriting files. Select one of the following options from the drop-down list:</p> <ul style="list-style-type: none"> • Ask: prompts you when overwriting a file. • Skip: cancels the operation if there is a file with the same file name and extension. • Replace: overwrites the file. • Rename: prompts you to rename the file.
Preserve last-modified dates	Retains the date and time properties of the file.
Auto-close progress dialog if all operations succeed	Automatically closes the dialog box after all images have been adjusted.
Save current settings as default	Stores the current settings and applies them the next time you use the Resize Images wizard.
JPEG Compression Options	Opens the JPEG Options dialog where you can specify detailed compression options to apply to the resized files.

 [Organizing and Managing Files in ACDSee](#)

Adjusting Exposure For Multiple Images

In ACDSee, you can lighten or darken the colors of an image or a group of images with the Batch Adjust Exposure wizard. You can adjust each image individually and preview the changes before applying, or make adjustments to an image and automatically apply the same changes to all of the images you selected.



You can also [save your settings as a preset](#) for future use.

To Adjust Image Exposure:

1. In Manage mode, select one or more images, and then click **Tools | Batch | Adjust Exposure**.
2. In the Batch Adjust Exposure dialog box, do one or more of the following:
 - To adjust image exposure, contrast, and fill light level, select the **Exposure** tab and adjust the options.
 - To precisely adjust the contrast and light levels in your images, select the **Levels** tab and set the options.
 - To adjust image exposure automatically, select the **Auto Levels** tab and set the options.
 - To precisely adjust the RGB color channels in your image, select the **Tone Curves** tab and set the options.
3. Do one of the following:
 - Check the **Apply settings to all selected images** checkbox to apply the current settings to all of the images you selected.
 - Uncheck **Apply settings to all selected images** and click **Next Image** to move to the next image, and then repeat step 2 for each image you want to adjust.
4. Click **Options** to specify how you want to save and store the images.
5. Click **Filter All Images**.



You can also adjust image exposure and color levels in Edit mode.

Adjusting Batch Exposure Options

You can use the options in the Batch Adjust Exposure dialog to correct the exposure of your images. There are four tabs in the Exposure section: Exposure, Levels, Auto Levels, and Tone Curves.

To Use the Exposure Options:

In the Batch Adjust Exposure dialog box, use the following options:

Exposure Options

Exposure	Specifies the amount of light to add to all areas of the image.
Auto	Automatically corrects the exposure based upon the brightness of the image.
Contrast	Specifies the amount of difference between color and brightness in an image. Moving the slider to the right darkens the shadowed areas in an image, while moving the slider to the left brightens them.
Fill Light	Specifies the amount of light to add to the darkest areas of the image.

Levels Options

Channel	Specifies the brightness or color channel you want to adjust.
Shadows	<p>Specifies the black point of an image.</p> <p>Move the slider or type a number from 0 to 255 into the spin box to define the blackest area of an image. As the value increases, the dark colored areas of the image become darker.</p>
Midtones	<p>Specifies the gamma correction in an image.</p> <p>Move the slider or type a number from 0.00 to 2.00 into the spin box to set the amount of gamma correction. Higher values make the image appear brighter, while lower values make the image appear darker.</p>
Highlights	<p>Specifies the white point of an image.</p> <p>Move the slider or type a number from 0 to 255 into the spin box to define the whitest area of an image. As the value increases, the light colored areas of the image become lighter.</p>
Clipped %	Indicates how much of the image detail is lost due to black point and white point correction.
Black Point Eyedropper	Click the button with the black eyedropper icon to adjust the black point. Select the area in the Before image that you want to set as the black point for the After image.
Mid Point Eyedropper	Click the button with the gray eyedropper icon to adjust the gamma correction value. Select the area in the Before image that you want to set as the gamma correction value.
White Point Eyedropper	Click the button with the white eyedropper icon to adjust the white point. Select the area in the Before image that you want to set as the white point for the After image.

Auto Levels Options

Strength	Adjusts the amount of exposure applied to the image.
Auto Contrast and Color	Adjusts color differences, brightness, and image color channels.
Auto Contrast	Adjusts the color differences and brightness only.
Auto Color	Balances color within the whole image.

Tone Curves Options

Channel	Specifies the color channels to adjust.
Show Histogram	Toggles the histogram display.
Histogram	Displays a visual representation of the color information levels in the image, based on the selected channel. Click and drag the line to manipulate the curve.


Renaming Multiple Files


You can use the Batch Rename tool to rename multiple files. You can specify a template with a numerical or alphabetical sequence, save your template for future use, replace specific characters or phrases, change cases, and insert or remove text or spaces. This can be particularly useful if you deal with large quantities of images, or you organize your images by file name.

To Rename Multiple Files:

1. In Manage mode, select one or more files, and then click **Tools | Batch | Rename File | Rename...** If selecting two or more files, you can alternatively press **F2**.
2. In the Rename dialog box, you will see a list of operations. Click any operation to view or change it's settings. You can use the checkboxes to select or deselect which operations to run when batch renaming. The following operations enable you to perform the following actions:
 - **Template** - create a renaming template to apply to all selected files.
 - **Search and Replace** - search for and replace parts of your file name.
 - **Case Change** - change the case of text in your file name.
 - **Insert Text** - add text to your file name.
 - **Remove Text** - remove text from your file name.
 - **Strip Spaces** - remove spaces from your file name.

3. Review changes you have made to file names in the Preview field.
4. Click **Rename**.

 You can save your rename settings as a preset by clicking the save icon beside the preset drop-down. From there, enter a name and press **OK**. You can also access your Last Used Settings in the preset menu, if you wish to repeat an action. To delete a preset, press the trash icon.

 You can assign shortcuts to speed up your process of renaming multiple files by following the directions in the [Customizing Keyboard Shortcuts](#) topic.

Rename Settings

Template

Template:	<p>Type a file name format to set as a template. You can type any text into this box, including hyphens and underscores.</p> <p>Use the * symbol to insert the original file name, so renaming IMG-9359.jpg using the template "Summer Wedding*" will rename the file "Summer WeddingIMG-9359.jpg".</p> <p>Use the # symbol to begin a sequence, either numerical or alphabetical.</p>
Insert Metadata...	Choose one or more metadata properties to include in the renaming template by checking the relevant checkboxes. Press OK.
Clear Templates	Select this option to clear the existing templates to create a new one, or change the existing template.
Use numbers to replace #'s	Select this option to replace #s in the rename template with sequential numbers.
Use letters to replace #'s	Select this option to replace #s in the rename template with sequential letters.
Start at:	Select either Fixed value or Auto detect. If you select Fixed value, choose a number to start the sequence with. Select Auto detect to identify an existing numerical system and continue it.

Search and Replace

Search for:	Enter a term to search for.
Replace with:	Enter a term to replace the searched term with.
Insert Metadata...	Choose one or more metadata properties to include in the renaming template by checking the relevant checkboxes. Press OK.
Case sensitive	Check this checkbox to search only for results that match the case of your search term. You can use this to remove all capitals in your file names, or all lowercase terms.
Include extension	Check this checkbox to include file extensions in your search and replace.

Case Change

Name	Choose from Lowercase, Uppercase, or Title case to make a change to the case in your file name, or select No change to keep as is.
Extension	Choose from Lowercase, Uppercase, or No change. This can be

useful to unify case differences in file names, for example .JPG and .jpg

Insert Text

Insert:	Type the text you want to insert into the file name.
Insert Metadata...	Choose one or more metadata properties to include in the renaming template by checking the relevant checkboxes. Press OK.
At location	Choose from Prefix, Suffix, Position (meaning how many characters into the name), After text:, or Before text:. After and before text lets you enter text to prelude or follow.
Add from right to left	Check this box to add the text from right to left, rather than from left to right.
Overwrite existing name	Check this box to rename the file by overwriting the existing file name.
Include extension	Check this checkbox to include file extensions in your renaming process.
Case sensitive	Check this checkbox to search only for results that match the case of your search term.

Remove Text

Start From	Choose a Position or a Delimiter. <ul style="list-style-type: none">• Enter a position, meaning how many characters into the name to start removing text.• Enter a Delimiter, which is where you start removing text from.
Remove Until	Choose Count equals, Delimiter, or The end. <ul style="list-style-type: none">• Enter a Count equals, this is how many characters of text to remove.• Type a Delimiter, which is where to stop removing text from.• When you choose The end, text is removed until the end of the file name.
Remove from right to left	Check this box to remove text from right to left, rather than from left to right.

Remove delimiters	Check this box to remove the delimiters when renaming, else they will remain.
Include extension	Check this box to include the file extension in the text you remove.
Case sensitive	Check this box to make text in the delimiter fields case sensitive.
Strip Spaces	
Type of space removal	<p>Choose Remove all, Remove trailing, Remove consecutive, or Replace with.</p> <ul style="list-style-type: none">• Remove all removes all spaces in the file name.• Remove trailing removes spaces following the file name.• Remove consecutive removes multiple spaces in the file name.• Replace with gives you the option to enter alternatives, such as a letter, number, or dash.
Advanced...	
Handle name conflicts	<p>Choose from the following options:</p> <ul style="list-style-type: none">• Ask: produce a prompt when a name conflict occurs.• Skip: skip names that include conflicts.• Rename: rename files with conflicts.
Handle extension changes	<p>Choose from the following options:</p> <ul style="list-style-type: none">• Ask: produce a prompt when a rename affects an extension.• Skip: skip changes that affect extensions.• Rename: rename extensions where required by the rename.



As well as editing the options listed in the table, you can also reorder how these operations run. To reorder operations, use either the up or down arrows at the bottom of the list, or click and drag the name of the operation to its new location.



You can add additional operations, up to 10 in total. To do this, press the plus button at the bottom of the list.



To remove an operation, press the trash icon.

About the ACDSee Home Database

The ACDSee Home database stores image, document, and media file information automatically when you browse your folders. This process is called cataloging. The database increases the speed with which you can browse your computer, and you can use the information stored in the database to sort, organize, search, and filter your images and media files. You can also backup, restore, and share database information.

You can store cached thumbnail previews, and add or edit the following information for each image or media file on your computer:

- Categories
- Notes
- Keywords
- Color Labels
- Authors
- Dates
- Ratings
- Captions
- Face Data

You can also choose to exclude folders from the database, and keep the contents of those folders separate from your other images and media files.

ACDSee Metadata can be embedded directly into your files. See [Embedding ACDSee Metadata in Files](#) for more information.



When you add ACDSee Metadata to a file in ACDSee, the file is linked to the database. If you then copy, move, or rename your files using programs other than ACDSee, such as Windows Explorer, the link to the database is broken and this can cause the loss of ACDSee Metadata.

Embedding ACDSee Metadata in Files

If you edit or add ACDSee Metadata to your files, ACDSee Home automatically adds the new data to its database. If you have the **Display embed ACDSee metadata reminder** checkbox checked in the Options dialog box, (click **Tools** | **Options** | **Embed ACDSee Metadata**), next time you close ACDSee, the Embed ACDSee Metadata dialog box opens and offers to embed the new data into the changed files themselves. You can also set how often you would like this reminder displayed. Embedding

ACDSee Metadata in the files as well, is a safe way to back up this data and make it easier to retrieve if you should need to.

For example, once you have assigned ACDSee Metadata to a file, the file is linked to the database. If the file is moved using Windows Explorer, or any application other than ACDSee, the link will be broken. However if you have embedded this data in the file and the link is broken, you can still retrieve the ACDSee Metadata using the embedded data in the files.

You can use ACDSee Home to rename, move, or copy the file—even to another computer—and the embedded ACDSee Metadata will transfer with the file.

To Embed ACDSee Metadata in a File When You Are Prompted:

1. In the Embed ACDSee Metadata dialog, select either or both of the following:
 - **ACDSee Metadata will be embedded into X file(s):** indicates the number of files that you selected that have metadata to be embedded.
 - **ACDSee Face Data will be embedded into Y file(s):** indicates the number of files that you selected that have face data to be embedded.

2. Click **Embed**.



Click Options to open the Embed ACDSee Metadata Options. Click [here](#) for more information.

To Embed ACDSee Metadata at Any Time:

You can embed data in files at any time.

1. Click **Tools | Metadata | Embed ACDSee Metadata**, and then select one of the following:
 - **Embed in All Files:** embeds data for all files.
 - **Embed in Selected Files:** embeds data for any files that you have selected.
2. In the Embed ACDSee Metadata dialog, select either or both of the following:
 - **ACDSee Metadata will be embedded into X file(s):** indicates the number of files that you selected that have metadata to be embedded.
 - **ACDSee Face Data will be embedded into Y file(s):** indicates the number of files that you selected that have face data to be embedded.

3. Click **Embed**.



Click Options to open the Embed ACDSee Metadata Options. Click [here](#) for more information.



ACDSee uses XMP to embed ACDSee Metadata into each file. Only some file formats and file extensions support XMP. These include GIF, JPEG, DNG, PNG, PSD, TIF, AVIF, and JPEG-XL. In

- ! the case of these file formats, the ACDSee Metadata is embedded inside the file and so you can rename or move the file outside of ACDSee and still be able to retrieve the ACDSee Metadata. For formats that currently do not support XMP, including RAW and ABR, the ACDSee Metadata is written to a sidecar file that is stored in the same folder as its file. Because a sidecar file is separate from the file itself, you need to rename or move them together, or you could lose the ACDSee Metadata permanently.

Embedding ACDSee Categories and Keywords into IPTC Metadata

There are quick commands to embed your ACDSee keywords and categories into IPTC metadata.

To Embed ACDSee Keywords and Categories to IPTC Keywords and Supplemental Categories

Select a file, Right-Click and choose **Metadata | Embed to IPTC | Embed Keywords to IPTC** or **Embed Categories to IPTC**.

or


Select a file, and choose **Tools | Metadata | Embed to IPTC | Embed Keywords to IPTC** or **Embed Categories to IPTC**.

Merging or Overwriting IPTC Metadata

When embedding **ACDSee Metadata** into **IPTC metadata**, you can choose how the data is saved alongside previously saved metadata.

- Merge: **ACDSee Metadata** will be added to any existing **IPTC Keywords** and/or **IPTC Supplemental Categories**.
- Overwrite: **ACDSee Metadata** will replace any existing **IPTC Keywords** and/or **IPTC Supplemental Categories**.

The Embed Pending Icon

In Manage mode, in the File List pane, the following overlay icon appears on top of files that have ACDSee Metadata and Face Data stored in the ACDSee Home database that has not yet been written to the file: 

Right-click and choose either:

- **Embed ACDSee Metadata**: writes the metadata to the file.
- **Clear Embed Pending Icon...**: clears this overlay icon, but does not write the metadata to the file.

Viewing Files That Have Data to Embed

If you want to see the files that have data that needs to be embedded, there is a quick way to list them using the Embed Pending option.

To View Files That Have Data to Embed:

In the Catalog pane, under Special Items, click **Embed Pending**.

All the files that have data to embed are displayed in the File List.

Retrieving ACDSee Metadata That is Embedded in Files

If you simply browse to the folder where the files are located, some of the ACDSee Metadata is retrieved and written to the database. Categories and keywords, however, are not.

The safest way to retrieve all the ACDSee Metadata, (including categories and keywords), is to click **Tools | Database | Catalog Files**. Then the following applies:

- If the files are GIF, JPEG, DNG, PNG, and TIF formats, all the data will be retrieved and written to the database.
- If the files still have their sidecar files in the folder, and they still have the same file name, the database information is retrieved and written to the database.
- If the files have become separated from their sidecar files or renamed, their ACDSee Metadata cannot be retrieved and will be lost.

Excluding Folders From the Database

You can choose to exclude folders from the database, and keep the contents separate from your other images and media files. By default, the Program Files and Windows folders on your hard drive are automatically excluded from the database.

To Manage Your Excluded Folders Settings:

1. In Manage mode, click **Tools | Database | Excluded Folder Settings**.
2. In the Excluded Folders dialog box, do one of the following:
 - To exclude a folder from the database, click **Add**. Browse to a folder on your hard drive, and then click **OK**.
 - To remove a folder from the excluded folders list, select a folder in the list, and then click **Remove**.
 - To reset your excluded folders list to the default settings, click **Reset to Defaults**.
3. When you are satisfied with your choices, click **Close** to return to ACDSee.

Cataloging Files in the Database

ACDSee Home automatically adds file information and thumbnails to the database as you browse. You can use the Catalog dialog box to add groups of files to the database without having to first browse the folders. This can be particularly useful when using ACDSee Home for the first time, and when browsing or managing large collections of images, as it reduces the loading time required for these folders.

The first time you run ACDSee, you are prompted to catalog your files.

To Catalog Your Files:

1. In Manage mode, click **Tools | Database | Catalog Files...**
2. Select the files to be cataloged. For more information see the **Catalog Options** table below.
3. Click **Start**.

A progress bar shows your files as they are cataloged.

4. Click **Finish**.

Catalog Options

Catalog**Add Folder...**

Click the Add Folder... button to browse for folders to be added to the database.

Remove Folder

Select a folder in the Folders to Catalog table and click the Remove folder button to remove the folder from the table.

Import from Cataloged Files

Catalog

EXIF and IPTC metadata

Enable to import EXIF and IPTC metadata.

Catalog

IPTC Keywords to ACDSee Keywords

Enable to import IPTC keywords into ACDSee Keywords. IPTC keywords can also be imported by right-clicking on the image, and selecting **Metadata | Import IPTC Keywords**.



Files with ACDSee Keywords assigned will import IPTC Keywords without overwriting or removing existing ACDSee Keywords.

IPTC Supplemental Categories to ACDSee Categories

Enable to import IPTC supplemental categories to ACDSee Categories. IPTC supplemental categories can also be imported by right-clicking on the image and selecting **Metadata | Import IPTC supplemental categories**.



Files with ACDSee Categories assigned will import IPTC Supplemental Categories without overwriting or removing existing ACDSee Categories.

ACDSee Metadata, including categories, keywords, tagged, and collections

Enable to import ACDSee metadata, including categories, keywords, tagged, and collections.



If a file's Embed Pending flag is set, it will not import ACDSee Categories and Keywords.



If a file's Embed Pending flag is not set and it has embedded ACDSee Categories and Keywords, it will unassign the file's existing categories and keywords and import those values from the embedded data.

Catalog

Face Data, including face outlines and names

Enable to import **Face Data, including face outlines and names**. Enabling the Face Data checkbox activates the **ACDSee Face Data** radio button and the **Lightroom or Picasa Face Data** radio button.

ACDSee Face Data

Enable to import **ACDSee Face Data**. The **ACDSee Face Data** radio button is only activated if the **Face Data, including face outlines and names** checkbox is enabled. Enabling the **ACDSee Face Data** radio button disables the **Lightroom or Picasa Face Data** radio button.

Lightroom or Picasa Face Data

Enable to import **Lightroom or Picasa Face Data**. The **Lightroom or Picasa Face Data** radio button is only activated if the **Face Data, including face outlines and names** checkbox is enabled. Enabling the **Lightroom or Picasa Face Data** radio button disables the **ACDSee Face Data** radio button.

File Formats

Catalog Images

Only image file types will be cataloged

Catalog Images and videos

Both image and video file types will be imported.

Catalog all files

All files in the selected folder will be imported.

Options

Build and include thumbnails in database

Enable to build thumbnails of the image or video files and include the thumbnails in the database.

Include contents of archive files

Enable to include the contents of archived files.

Create preview files for RAW images

Enable to create preview files for RAW images.

Catalog**Other****Help**

Opens the help file related to cataloging files in **Media** mode.

Start

Starts the process of adding thumbnails and file information to the database.

Cancel

Closes the window.



If you are cataloging a large collection of files, do not disrupt the process, or use other software while it is running. For large file collections, it is best to run cataloging overnight.

About the ACDSee Indexer

Cataloging and the Database.

The ACDSee database stores file information when you browse your folders. This process is called cataloging. Cataloging and using the database can help you sort, organize, search, and filter your files, as well as speeding up browsing. The ACDSee Indexer is a tool that helps you catalog your images without browsing through them.

You can use the Catalog dialog box to add files to the database without having to first browse the folders. During this time, you will not be able to use ACDSee.

The ACDSee Indexer allows you to catalog files while your computer is idle and ACDSee is not running. This saves you from having to browse all folders or experience your computer slowing down while processing. If you have edited any files in the selected folders, the ACDSee Indexer will update the database.

You can set folders to be cataloged and how long you would like your computer to be idle before the ACDSee Indexer begins to catalog your files. To configure these options, see [Setting the ACDSee Indexer Options](#).

Creating and Switching Between Multiple Databases

ACDSee allows you to create multiple databases and switch between them at any time, giving you complete organizational control over your file collections.


When you open ACDSee for the first time, (and up until you create additional databases), you will be using the original database called Default.dbin. It is located in: C:\Users\<Your Name>\AppData\Local\ACD Systems\Catalogs\<Version #>. All additional databases that you create will be stored in this same location, unless you specify otherwise.



You can configure ACDSee to display the database it is currently running in the title bar of the application.

To Create a New Database:

1. In Manage mode, open **File | Database | New...**
2. In the New Database dialog box, enter a name for your new database.
3. Browse to choose the location where the database will be stored, or leave it set to the existing location to store the new database with your existing database, Default.dbin.

 The database file will be stored with a folder of the same name. The database file and folder must always share exactly the same name, or ACDSee will not be able to connect to the database.
4. If you would like to have the name of your database displayed in the title bar of the application, check the **Show database filename in title bar** checkbox.
5. Click **OK**.
6. A dialog will appear asking you if you would like to switch to your newly created database. Select **Yes** or **No**. If you select **Yes**, ACDSee will restart and run with the new database.

To Switch from One Database to Another:

In Manage mode, do one of the following:

Open File Database Open...	In the Open Database dialog, browse to the database file (*.dbin) you want to use and click Open .
Open File Database Recent	Select one of your recently used databases.


To Quickly Launch ACDSee in a Specific Database Using Command Line Switch:

1. Create a shortcut to ACDSee. It is recommended that you name this shortcut something that corresponds to the name of the database you want to open.
2. In the shortcut properties, set the target to **C:\Program Files\ACD Systems\ACDSee\<Version #>\ACDSee<Version #>.exe" /db "C:\Users\<Your Name>\AppData\Local\ACD Systems\Catalogs\<Version #>\<Name of Your Database>.dbin"**.

Converting an Older Database

You can use the ACD Database Convert wizard to take database information from previous versions of ACDSee Home and add it to your current database. This ensures that any information associated with

your files using a previous version of ACDSee Home is referenced properly in the current database.


 If you have already added information to your current ACDSee Home database, it is recommended that you create a backup of your database before converting an older ACDSee Home database.

To Convert an Older Database:

1. In Manage mode, click **Tools | Database | Convert Database**.
2. On the Welcome page, click **Next** to select your conversion options.
3. On the Database Convert Options page, specify the version of the database files you want to convert, as well as the folder where the database files are located on your hard drive. Click **Next**.
4. To automatically rebuild image thumbnails, IPTC and EXIF information after the conversion process is complete, check the **Rebuild thumbnails, EXIF and IPTC data for local images** checkbox.
5. To automatically update your database after converting, check the **Optimize database files after convert** checkbox.
6. Click **Next**.
7. On the Summary page, review your selections, and then click **Next** to convert your database.

Importing Database Information

You can use the ACD Database Import wizard to import archived database information, or to import database information that was sent to you with images from another ACDSee Home user. After you import the information, ACDSee Home associates it with the appropriate images.


 If you have already added information to your current ACDSee Home database, it is recommended that you create a backup of your database before converting an older ACDSee Home database.

To Use the ACD Database Import Wizard:

1. In Manage mode, click **Tools | Database | Import**, and then select **Database**.
2. Click **Next** to start the wizard.
3. On the Import Options page, select the type of exported database information you want to import.

You can import image information from a compressed database version, or information from an XML-based text file.
4. Click the **Browse** button to locate the database you want to import, and then click **OK**.
5. Check the **Optimize database files after import** checkbox to optimize the database after exiting the wizard, and then click **Next**.

6. On the Summary page, review your selections. Click **Back** to make changes, or click **Next** to begin importing the database information.
7. Click **Finish** to close the ACD Database Import wizard.

 If you are importing database information sent to you by another ACDSee Home user, ensure that the images to which the information applies are in an identical location and folder structure on your hard drive.

Importing File Information from Other Sources

You can import file information into your database from other sources, including [ACDSee Photo Discs](#) and files from previous versions of ACDSee.

Importing Photo Discs

Previous versions of ACDSee (versions 4.0 and 5.0) created separate database files with a .ddf file extension for Photo Discs. You can import the Photo Disc database files into your ACDSee Home database.

To Import a Photo Disc:

1. In Manage mode, click **Tools | Database | Import**, and then select **Photo Disc**.
2. In the Open dialog box, locate and select the photo disc file you want to import.
3. Click **Open**.

 To import the information from Photo Discs created with ACDSee 6.0 or later, you must convert and import the entire database.

Importing Albums

In previous versions of ACDSee, you could create albums in an .ais file format that consisted of organized shortcuts to your images. Now you can use categories to create albums of images that do not require a separate file extension. You can, however, import your albums from previous versions of ACDSee, and add the information from the albums to the database. ACDSee Home creates a new category for each album you import.

To Import Album Information into the Database:

1. In Manage mode, click **Tools | Database | Import**, and then select **Album**.
2. In the Open dialog box, locate and select the .ais file you want to import.
3. Click **Open**.

Working with Descript.ion Files

In previous versions of ACDSee, file descriptions were stored in a separate descript.ion file in each folder that contained images. ACDSee Home now stores file descriptions as captions in the database, along with other file information such as notes and keywords.

You can use the Descript.ion tools to import your old descript.ion files and add the information to the database, or export your existing file captions to a descript.ion file.

To Import a Descript.ion File:

1. In Manage mode, click **Tools | Database | Import**, and then select **Descript.ion File**.
2. In the Open dialog box, locate and select the descript.ion file you want to import.
3. Click **Open**.

To Export Captions to a Descript.ion File:

1. In Manage mode, click **Tools | Database | Export**, and then select **Descript.ion File**.
2. In the Save As dialog box, type a name for the descript.ion file in the File name field.
3. Click **Save**.

Exporting Database Information

You can use the ACD Database Export wizard to save selected database information in a compressed format, and then store it as a backup, or share it with other ACDSee Home users. You can also choose to export your category and keyword definitions to a text file.

Exporting your database information differs from creating a backup in that you can choose to export only the parts of your database that you want to share or store with specific files, such as those on a CD. Other ACDSee Home users can import your information without affecting their existing database.

To create a backup of your entire database, including image or media files, use the [ACD Database Backup wizard](#).

To back up the contents of a local folder to a remote location, such as a network drive, use the [ACD Sync wizard](#).

To Use the ACD Database Export Wizard:

1. If you want to export your database information for a specific group of images or media files, select the files in the [File List](#) pane in Manage mode.
2. Click **Tools | Database | Export | Database**.
3. Click **Next** to begin using the wizard.
4. On the Content and Format Options page, specify how you want to export your database information by selecting one of the following options, and then clicking **Next**:

- **Export entire ACDSee database to a read-only, compressed version:** exports the entire contents of your ACDSee Home database to a compressed version that can be shared with other ACDSee Home users.
 - **Export database information for selected items to a read-only, compressed version:** exports all of your database information for the images selected in the File List pane.
 - **Export database information to a text file:** exports the selected information to an XML-based text file. Check the checkboxes next to the information you want to include.
5. On the Location Options page, specify a location for the exported information, and a name for the text file, if necessary, and then click **Next**.
 6. On the Summary page, review your choices. You can click **Back** to make changes, or click **Next** to begin exporting your database information.
 7. Click **Finish** to close the wizard and return to ACDSee.

Generating File Lists

You can generate a text file that lists all of the files in the folder currently displayed in the File List pane. The text file places the file name, size, image file format, modified date, image properties, caption, and rating for all of the files in the folder into a table, and creates a single text file.

To Generate a List of Your Files:

In Manage mode, click **Tools | Database | Export**, and then select **Generate File Listing**.

ACDSee Home automatically generates the file listing and opens it as a text file in your default text editor. You can then edit or save the text file.

Backing Up Your Database

You can use the ACDSee Backup wizard to back up all of your database information, which you can then restore in the case of a system failure or other event. You can also choose to back up your image, media, or archive files along with the relevant database information.

The ACDSee Backup wizard creates a series of files in a specified location that contain your entire database. The backup is generated using your folder structure and is unique to your computer. To back up portions of your database, or to share database information with another ACDSee Home user, use the ACDSee Database Export wizard.

For some suggestions about managing your database backups, see [Database Backup Tips and Strategies](#).

To Back Up Your Database Information:

1. In Manage mode, click **Tools | Database | Back Up Database**.
2. On the Welcome page, select whether you would like to create a new backup, or update an existing backup. Click **Next**.

If you choose to update an existing backup, please go to step #5.

3. On the New Backup page, select the information you would like to back up. Click **Next**.
4. On the Backup Location page, click **Browse** and specify a location for your backup, and type a name for the backup file. Click **Next**.
5. On the Backup Summary page, review your settings. If you chose to update an existing backup, click the **Backup to update** drop-down list, and then select the existing backup. Click **Next**.

Backup Information Options

Do not include thumbnails	Excludes thumbnails from the backup, saving a substantial amount of storage space on your hard drive.
Include thumbnails for offline files	Includes only thumbnails for files that do not reside on your hard drive, such as PhotoDiscs.
Include thumbnails	Includes all thumbnails in the database. This will require more space on your hard drive to store the backup.
Backup files of type	<p>Backs up the specified file types with the database information. Select from the following file types:</p> <ul style="list-style-type: none"> • Image: includes image files in the backup. • Media: includes audio and video files in the backup. • Archive: includes archive files in the backup.
All files of specified types on your local hard drives	Backs up all specified files on your hard drive.
All files of specified types on local and network hard drives	Backs up all specified files on your hard drive and network drives.
All files of specified types in a folder (including subfolders)	Backs up all specified files in a specified folder. Click the Browse button and select the folder to back up.

Database Backup Tips and Strategies

The ACDSee Home database stores information about your files, including EXIF information, file name and folder location, thumbnails, categories, ratings, and any other information you add using the Properties pane. The more information you store in the database, and the more time you spend entering that information, the more important it is to back up your database, and to have a good strategy for managing your backups. Losing hours of work to a system crash or other uncontrollable event is something that should, and can, be avoided.

Backup Schedule

How often you need to back up depends on how often you add or change information in the database. A good rule to use would be to back up your data as often as you want to avoid retyping it. You can use the backup reminder settings on the Database page of the Options dialog box to set a regular reminder for yourself to back up your data as often as you think appropriate. Business environments and professional users should back up every day.

It is also recommended that you back up your database before performing any major adjustments to it, such as importing information from another ACDSee Home user, or converting a database from a previous version of ACDSee.

Backup Location

It's a good idea to consider where you back up your data, as well as how often. If you're backing up to your hard drive, ACDSee Home creates a new folder for each day. This helps to avoid overwriting your backup, and gives you several increments from which you can restore. Also helpful is a monthly backup that is stored in a different physical location than your computer, such as a network drive.

Backup Size

To keep the size of the backup small, choose to back up database information only, and back up your images separately, also on a regular basis.


Restoring Database Information From a Backup

You can use the ACD Database Restore wizard to restore previously backed up database information.

To Restore Database Information:

1. In Manage mode, click **Tools | Database | Restore Database**.
2. On the Welcome page, click **Next** to select the backup.

3. On the Restore Options page, select the backup and date from which you want to restore, or browse to the location of your backup and select a .bkup file.
4. Click **Next** when you are ready to restore your database.

 When restoring a backup from a series of backup files, ACDSee Home will only restore the information included in and prior to the selected backup file. Therefore, unless required, it is recommended that you select the last file in the backup sequence.

Maintaining the Database

It is recommended that you regularly perform database maintenance and optimization to increase hard drive space, remove redundant or extraneous information, and increase overall ACDSee Home performance.

You can use the tools in the Database Maintenance dialog box to update folders, or to identify folders whose thumbnails and database information you would like to delete. The Database Maintenance dialog box displays a list of the folders on your system, and uses icons to indicate the status of database information within specific folders.

Database Content Icons



Folder contains files with cached thumbnails stored in the database.



Folder contains files that were changed without a database update. For example, a folder or file was renamed or moved outside of ACDSee.

To Perform Database Maintenance:

1. In Manage mode, click **Tools | Database | Database Maintenance**.
2. In the Database Maintenance dialog box, browse for folders marked with the database content icons. If there are no marked folders, you do not need to perform database maintenance and can exit the Database Maintenance dialog box.
3. Select a folder and click one of the following buttons to identify the maintenance you want to perform on that folder:
 - **Remove Thumbnails:** removes all thumbnail information for the selected folder.
 - **Remove All DB Info:** deletes all database and thumbnail information for the selected folder.
 - **Remove Orphan Folders:** deletes any out-of-date or broken references to missing files or information for the selected folder. It is only possible to check for orphans in folders located on your computer. This option will not be visible if the folder is located on a network.

- **Change Binding:** changes all location references for the selected orphaned folder to another folder, and retains all database information. The default binding folder is My Pictures.
4. The Database Maintenance tool will delete records, creating unused space in your database. To reclaim the unused space, click **Optimize Database**, and follow the instructions in the wizard.
 5. Click **Close**.

Optimizing the Database

You can use the Optimize Database wizard to quickly remove redundant or outdated database records. Optimizing your database, along with performing regular [database maintenance](#), helps regain hard drive space and improves the overall performance of ACDSee.



If you are cataloging large numbers of files regularly, it is helpful to optimize weekly, or after an extended cataloging session. This is also a good time to backup the database.

To Optimize Your Database:

1. In Manage mode, click **Tools | Database | Optimize Database**.
2. In the Database Optimization wizard, click **Next**.
3. Select one or both of the following:
 - **Optimize the database tables and fields:** removes obsolete information from the database, reduces the space used by database fields, and re-indexes the tables.
 - **Remove orphans from database:** removes any orphan database entries, caused by files or folders deleted by other programs.
4. Click **Next**.
5. When the wizard has finished, click **Finish** to return to ACDSee.

Mapping Drives for an Incoming Database

If you are upgrading to ACDSee Home or are importing or restoring your ACDSee Home database, the Database Drive Mapping dialog displays how drive mappings (in the incoming database) will be re-established in the ACDSee Home database. You can use this dialog to change how each drive will be mapped in the database.

To Select New Drive Mappings:

1. In the Database Drive Mapping dialog, select a drive and do one of the following:
 - To create a new drive map, select **Create new database entry**.
 - To map the drive to a local drive, select a drive from the **Local Drive** drop-down list.
2. Click **Done**.

Rebuilding Thumbnails and Metadata

Situations can develop in which your images will be out of sync with the thumbnail images displayed in the File List pane and the embedded metadata. You can use the Rebuild Thumbnails and Metadata tool to immediately regenerate the thumbnails for selected images and rebuild the metadata.

To Rebuild Thumbnails:

1. In Manage mode, do one of the following:
 - Select one or more thumbnails in the [File List](#) pane.
 - Select a folder in the [Folders](#) pane.
2. Click **Tools | Metadata | Rebuild Thumbnails and Metadata**.

Quarantined Files

If ACDSee Home has trouble reading a corrupted or incomplete image or media file, or a file causes a plug-in to generate an error, ACDSee Home will quarantine that file. You can view a list of quarantined files, and remove a file from the list.

To View Quarantined Files:


1. In Manage mode, click **Tools | Database | Quarantine Files**.
2. To remove a file, select it in the list, and then click **Remove**.
3. To disable the Quarantine feature, uncheck the **Enable Quarantine** checkbox.
4. Click **OK** to close the Quarantine Files dialog box and return to ACDSee.

Working with Plug-Ins

A plug-in is a software module that adds functionality to a larger program. ACDSee Home comes as standard with many different plug-ins.

Types of Plug-Ins

- **Image Decode:** converts a file from a binary format to the image displayed in ACDSee. Decode plug-ins allow ACDSee Home to display images of many different file formats. The files that you can view with ACDSee Home depend on which decoding plug-ins are installed on your computer.
- **Image Encode:** converts the image displayed in ACDSee Home to a binary file format. Encode plug-ins allow ACDSee Home to save (or convert) images to many different file formats. The files that you can edit and save with ACDSee Home depend on which encoding plug-ins are installed on your computer.
- **Archive:** allows ACDSee Home to display and save archives of many different file formats. The archives that you can view and create with ACDSee Home depend on which archive plug-ins are installed on your computer.
- **Camera:** allows ACDSee Home to browse images on your digital camera and transfer them to a folder on your hard drive.
- **Command Extension:** adds functionality to ACDSee. For example, there is a plug-in that you can use to share your images over the Internet.
- **Pane Extension:** adds a pane to ACDSee Home where you can perform tasks like order prints of your digital images.

 We cannot ensure the quality of plug-ins that are not certified by ACD Systems. As with any other piece of software, you are trusting that the plug-in is free of viruses and that the company that produced the plug-in is trustworthy.

Managing Plug-Ins

The Plug-in Settings dialog box displays a list of all the ACDSee plug-ins installed on your computer. You can also use the Plug-in Settings dialog box to control which plug-ins ACDSee Home uses.

To Access the Plug-In Settings Dialog Box:

In Manage mode, click **Tools | Plug-in Settings**.

Disabling a Plug-In

You can disable a plug-in in the Plug-in Settings dialog box so that ACDSee Home no longer uses it.

To Disable a Plug-In:

1. In the Plug-in Settings dialog box, select one of the Plug-in tabs.
2. Uncheck the checkbox beside the name of the plug-in that you do not want ACDSee Home to use.
3. Click **OK**.

Changing the Plug-In Order

Some file formats can be supported by more than one plug-in. However, when this happens, you can control which plug-in is used to read or write a file format. The order that plug-ins appear in the Plug-in Settings dialog box is the order that ACDSee Home uses the plug-ins to read or write a file.

To Change the Plug-In Order:

1. In the Plug-in Settings dialog box, select one of the Plug-in tabs.
2. Select a plug-in in the **Plug-ins** list.
3. Do one of the following:
 - Click the **Move up** button to move the plug-in higher in the list.
 - Click the **Move down** button to move the plug-in lower in the list.
4. Click **OK**.

Viewing Plug-In Properties and Getting Help

You can view and set properties for certain plug-ins.

To View Plug-In Properties:

1. In the [Plug-in Settings dialog box](#), select one of the Plug-in tabs.
2. Select a plug-in in the Plug-ins list.
3. Click the **Properties** button.


To View a Plug-In's Help File:

1. In the [Plug-in Settings dialog box](#), select one of the Plug-in tabs.
2. Select a plug-in in the **Plug-ins** list.
3. Click the **Plug-in Help** button.

ACDSee SeeDrive™

The ACDSee SeeDrive™ pane provides direct access to your ACDSee 365 account. You can use the ACDSee SeeDrive™ to manage your ACDSee 365 images, and monitor your uploads and downloads to seedrive.acdsee.com, an image sharing and storage service. An ACDSee 365 account requires a membership or the purchase of additional storage, which you can obtain at seedrive.acdsee.com.

ACDSee SeeDrive™ allows you to browse through your online images without having to launch an Internet browser. Alternatively, you can go to seedrive.acdsee.com with an Internet browser. To view the SeeDrive™ pane, go to **Panes | SeeDrive**.



To Use ACDSee SeeDrive™:

In the ACDSee SeeDrive™ pane, press **Connect** and enter your ACDSee 365 login credentials. If you do not have an [ACDSee 365 account](#), select **Create an account**.

Alternatively, you can log in through [365 mode](#).

Managing Your ACDSee 365 Files with SeeDrive™

You can create, rename, and delete ACDSee 365 folders directly from ACDSee SeeDrive™ in Manage mode.

To Create a New Folder:

1. In the ACDSee SeeDrive™ pane in Manage mode, right-click your username and select **New Online Folder...**
2. In the New Online Folder dialog, enter a name for your folder and press **OK**.



To add a newly created folder to an existing folder hierarchy, drag the new folder to your desired location inside of it.

To Create a New Folder Inside an Existing Folder:

1. In the ACDSee SeeDrive™ pane in Manage mode, expose your folders by clicking the arrow next to your username.
2. Right-click your desired folder and select **New Online Folder...**
3. In the New Online Folder dialog, enter a name for your folder and press **OK**.

To Rename a Folder:

In the ACDSee SeeDrive™ pane in Manage mode, right-click the folder and select **Rename**.

To Delete a Folder:

In the ACDSee SeeDrive™ pane in Manage mode, right-click the folder and select **Delete**.

To Rename a File:

1. In the ACDSee SeeDrive™ pane in Manage mode, navigate to and open your desired folder.
2. In the File List pane, right-click the file and select **Rename**.

To Delete a File:

1. In the ACDSee SeeDrive™ pane in Manage mode, navigate to and open your desired folder.
2. In the File List pane, right-click the file and select **Delete**.

Uploading

Uploading Files to ACDSee 365 with SeeDrive™:

- **To upload a folder:** select a folder from the Folders pane and drag it into your desired folder in ACDSee SeeDrive™.
- **To upload individual files:** select your desired files in the File List pane and drag them into your desired folder in ACDSee SeeDrive™.
- Manage your uploads by right-clicking any folder in ACDSee SeeDrive™ and selecting **Transfer Manager...** Use the Transfer Manager controls as described in the table below.

Downloading

Downloading Files from ACDSee 365 with SeeDrive™:

1. Select your destination folder in the Folders pane.
2. Select the folder you would like to download in ACDSee SeeDrive™, right-click and choose **Download**.

Manage your downloads by right-clicking any folder in ACDSee SeeDrive™ and selecting **Transfer Manager...** Use the Transfer Manager controls as described in the table below.

Transfer Manager Options

Choose the Uploads or Downloads tab.



Restarts paused transfer



Pauses transfer



Cancels transfer



Retry transfer



Select all



Clear finished

Making Folders Private or Public

You can set folders to private or public in the ACDSee SeeDrive™ pane in Manage mode. When you make a folder public, anyone can find and see the images in that folder when they browse or search seedrive.acdsee.com.



New folders are set to private by default.

To Change an ACDSee 365 Folder to Public Using ACDSee SeeDrive™:

1. In the ACDSee SeeDrive™ pane, expose your folders by clicking the arrow next to your username.
2. Right-click the folder you want to make public, and select **Make Public**.

To Change an ACDSee 365 Folder Back to Private Using ACDSee SeeDrive™:

1. In the ACDSee SeeDrive™ pane, expose your folders by clicking the arrow next to your username.
2. Right-click the folder you want to make private, and select **Make Private**.

Sharing and Downloading with ACDSee SeeDrive™

You can perform sharing and downloading actions on your online content from right within ACDSee SeeDrive™. You can also view and manage the progress of your uploads and downloads with the Transfer Manager.

Sharing a Folder with ACDSee SeeDrive™

You can share your ACDSee 365 folders with others right from your ACDSee SeeDrive™ pane. You can share using Email, post to a social networking site, or create a widget.

To Share Your Folders Using ACDSee SeeDrive™:

1. In the ACDSee SeeDrive™ pane in Manage mode, expose your folders by clicking the arrow next to your username.
2. **Right-click** the folder you want to share and select **Share Folder**.
3. In the Share window, select your sharing method and enter your information, as described below.

Share Options

Email

Scroll through your images at the bottom of the window and uncheck any photos you do not wish to include. After you have entered the information below, press **OK**.

Recipient Email Addresses	Enter your recipients' email addresses. Separate multiple email addresses with commas.
Your Message	Enter a message for your recipients.
Allow download of largest available JPG	Allow your recipients to download the largest available versions of your images.
Email me too	Check this checkbox to receive a copy of your email.
Optional private access password	If you would like your album to be password protected, enter the password here. The password will be available to your recipients in the body of your email, which they can then enter to gain access to your album.

X™

Scroll through your images at the bottom of the window and uncheck any photos you do not wish to include. After you have completed the steps listed below, press **Upload**.

X™	Press this button to launch X™ in a browser and enter your login credentials.
Shorten URL with bit.ly	Shortens the length of your album's URL, allowing you more characters for your message.
Preview	Displays a preview of your post.
Characters left	Displays how many characters you have left of your message.
Allow download of largest available JPG	Allows viewers to download the largest available versions of your images.

Widget

A photo widget is an image viewer or slideshow that can be placed on a website or blog. This option generates a piece of html code that you can copy and paste onto your website or blog. Scroll through your images at the bottom of the window and uncheck any photos you do not wish to include.

Orientation	Select the orientation of your photo widget from the drop-down menu.
Theme	Select the color theme of your photo widget from the drop-down menu.

Size	Select the size of your photo widget from the drop-down menu.
-------------	---

Sharing Your Folders by Copying and Pasting its URL Using ACDSee SeeDrive™

You can copy the URL of a folder from ACDSee SeeDrive™ and paste it in a browser, email, or anywhere else.

 You can only copy a URL from a [public](#) folder.

Copying and Pasting a Folder's URL:

1. In the ACDSee SeeDrive™ pane in Manage mode, expose your folders by clicking the arrow next to your username.
2. Right-click the folder you want to share and select **Copy URL**.
3. Right-click and select **Paste**, or press **Ctrl + V**, wherever you would like to paste the URL.


Chapter 4: Media Mode

Using Media Mode

Media mode offers a streamlined, database-driven approach to Digital Asset Management. Only the folders browsed in **Manage** mode and that have been cataloged into the ACDSee database will be displayed in **Media** mode, offering a clutter-free view of photographs and videos managed by ACDSee.

The **Media** mode interface is divided into four separate functional areas:

1. [Header Button Bar](#)
2. [My Folders](#)
3. [Display Area](#)
4. [Group By and Properties](#)



Header Button Bar

Located directly below the main menu, the Header Button Bar contains three buttons described below:


- Refresh
- Catalog
- Show Orphan Files

Header Button Bar Options

Refresh	Refreshes the My Folder pane's folder tree and the Display Area pane.
Catalog	For more about cataloging files, please see Cataloging Files in the Database .
Show Orphan Files	Displays missing files flagged as orphans. Orphans will be displayed in sepia.

My Folders

Located along the left side of the screen, the **My Folders** pane is a simple folder tree populated with all folders browsed while in **Manage** mode. To add additional folders to the **My Folders** pane without leaving **Media** mode, use the [Catalog Files tool](#).

The **My Folders** pane is hidden by default. To display the **My Folders** pane, click the Hide/Show icon  in the lower left of the Display Area.

Clicking a folder containing media in the **My Folder** pane will filter the Display Area's contents to display the selected folder's media.

Display Area

The **Display Area** pane occupies the large central portion of the screen and is used primarily to display images and videos that can be filtered, sorted, or grouped.

Double-click any image or video to display them in full screen. Videos displayed in full screen can be played without leaving **Media** mode. Double click the full screen image or video to return to the grid view.

Right-click individual media assets to produce a context-sensitive help menu containing the following options:

- **View:** Opens media asset in **View** mode.
- **Edit:** Opens media asset in **Edit** mode.
- **Rotate Left:** Press **Ctrl + L** to rotate left.
- **Rotate Right:** Press **Ctrl + R** to rotate right.
- **Show in File Explorer:** Opens to the media asset file's location in File Explorer.

Toggle Between Grid and Full Screen View

You can swap between **Grid** and **Full Screen** view by selecting the toggle button in the top left of the display, found directly to the left of the **Filter** option.

Filter By

When enabled, the tools in the **Filter By** toolbar are very powerful for tailoring the results displayed in the **Display Area** pane by filtering the results based on specific metadata.

To filter media assets in the **Display Area** pane, choose from a combination of any of the following:

- Enable the Tagged checkbox to display only those images with a tag.
- Make a selection from the ratings to display media with a specific rating. The button to the left of the ratings lets you choose whether the results will include media with a Rating less than or equal, greater than or equal, or matching the chosen rating.
- Make a selection from the color labels to display media tagged with a specific label.



Changes made to the **Filter By** tools will affect the results displayed in the **Group By** pane.


Sort and Group

Located directly above the media asset and to the right-side of the **Display Area** pane, the **Sort** and **Group** drop-downs are used to alter how the contents of the **Display Area** pane are presented. Unlike the **Filter By** field which refines the number of media assets displayed, the **Sort** and **Group** drop-downs do not change the number of media assets displayed. Both the **Sort** and **Group** drop-down results can be sorted forwards or backwards.



Selections made in the **Group** field will affect the results displayed in the **Group By** pane.

Group By and Properties Panes

Located along the right side of the screen, the **Group By** pane lists groups of media assets based on the selection made in the **Filter By** drop-down and the **Group** drop-down. The **Properties** pane displays key details such as IPTC, EXIF, and important ACDSee metadata. To display the **Group By** and **Properties** pane, click the Hide/Show icon  in the lower right of the Display Area.

The **Group By** pane results can be grouped forward and backwards.

The blue bar within each group tab is representative of the number of media assets in the group.

Clicking a tab in the **Group By** pane changes the display in the **Display Area** pane to reflect the group selected.

Navigation Buttons in Media Mode

When viewing an image in full screen, you can navigate between images by hovering over to the left or right side of the window and clicking on the navigational arrow that appears.

Deleting Images in Media Mode

There are three ways of deleting images in Media Mode:

- Right click on an image and select delete from the context menu
- Click on the Edit dropdown at the top of the screen and select Delete
- Click once on the image and press the Delete key

Chapter 5: View Mode

View mode is the main viewing component of the ACDSee user interface.


In View mode, you can:

- **Click + hold + drag** to pan around large images.
- Press the keyboard shortcut **F** to toggle in and out of [full screen view](#).
- [Zoom in or out](#) on your images.
- [View images in a slideshow](#).
- [Play video and audio files](#) and [add audio](#) to your image files.
- [Add captions](#) to your images.
- [Catalog files](#) by tagging them, adding categories, keywords, and other metadata.
- Automatically [advance](#) to the next image in the Filmstrip when you apply metadata.
- [Detect faces](#) in images and assign them names.

Previewing Your Images with Auto Lens


You can use Auto Lens to preview your images with a number of filters without actually applying them to the file.

To View Your Image with an Auto Lens:

1. Open an image in View mode.
2. On the Toolbar, press the **Auto Lens** button. 
3. Select a filter to preview your image in.
4. Use the Filmstrip or Previous/Next button to preview more images with your selected filter.



The Lens will remain turned on in View mode until you turn it off.



To Turn Off Your Selected Auto Lens:

1. On the Toolbar, press the **Auto Lens** button.
2. Select **None**.

Light EQ™

You can view your image with an instant exposure adjustment in View mode with Light EQ™. You will need to select Light EQ™ for each image you view.

To View Your Image with Light EQ™:

1. Open an image in View mode.
2. On the Toolbar, press the **Light EQ™** button.



Using Face Detection and Recognition in View Mode

You can use Face Detection to detect people in images you browse in View mode. You can also import face data from other programs in View mode.



This process will be expedited if you have allowed Face Detection to finish scanning in [Manage mode](#) on the folder you are currently viewing.

You can assign names to the detected faces in View mode using the Face Detection pane or Face tool. Naming faces will assist ACDSee with recognizing individuals in future images. This is referred to as facial recognition. The more often a person is named, the more likely they will be recognized, saving you time in the future. You can also improve your results by correcting names mistakenly assigned to faces by ACDSee. The sooner the correction is made, the less likely it will reoccur. Once you have named a face one or more times, ACDSee may suggest this name in future faces. See the [Suggestions](#) section below.



Faces can only be auto named if the [Enable Auto Naming](#) option is enabled.

Assigned names will allow you to search for images using the names of the people in them. You can do this using the Search functions in Manage mode, as well as the People group in the [Catalog](#) pane. You can also manage the names assigned to faces using [People mode](#).

Face Detection is enabled by default. Face Detection is only available on supported image file types.



You cannot run Face Detection on files in unsupported locations, such as archives, phones, and photo disks, or on files excluded from the database.

To Enable or Disable Face Detection:

Choose **Tools | Options | Face Detection** and check/uncheck the **Enable Face Detection** checkbox.

When you browse images in View mode, Face Detection will scan each image for faces as you open it.

To Open the Face Detection Pane:


Choose **Panes | Face Detection**.


Detected faces will appear in the Face Detection pane.

To Show Face Outlines:


In the Bottom Toolbar, click the **Show Face Outlines** button or press **Shift + B**. 

To Name Detected Faces:


1. In the Bottom Toolbar, click the **Face Tool** button or press **Shift + F**. 
2. In the field below the face outline, enter the name of the detected face.
3. Press **Enter**.

 You can use **Tab** to move your cursor between name fields on the image, as well as on the Face Detection pane.

To Edit Face Outlines:

1. In the Bottom Toolbar, click the **Face Tool** button or press **Shift + F**. 
2. Use your cursor to move, expand, or contract the outline.

To Draw Outlines Around and Name Undetected Faces:

1. In the Bottom Toolbar, click the **Face Tool** button or press **Shift + F**. 
2. Click and drag to draw a face outline on the image.
3. In the field below the face outline, enter a name for the face.

 Outlining and naming undetected faces will not improve ACDSee's recognition of the individual.

To Import Embedded Face Data From Lightroom or Picasa:

1. In View Mode, select **AI | AI Face Detection | Import Lightroom or Picasa Face Data**.
2. Your face data will import and the face data will be added to your database.

! When you import Lightroom or Picasa face data, it will overwrite any existing face data on the image.

Suggestions

Once you have assigned a name one or more times, ACDSee may suggest this name for faces in future images. Suggestions can improve themselves over time, and even assign themselves based on similarity.

 Faces can only be auto named if the **Enable Auto Naming** option is enabled.

 You must select the **Face tool** in order to interact with suggestions in the main viewer. 

To Deny or Confirm Suggestions:

Click the green checkmark to confirm the suggested name, or the red deny symbol to reject the suggested name.




You can ignore incorrect suggestions without negative consequences. Denying a suggestion will not affect suggestions on other photos. You can also edit suggestions in the name field and press **Enter**.

Using ACDSee AI Super-Resolution

AI Super-Resolution enhances the quality of your images by using advanced algorithms to intelligently upscale lower-resolution photos. This feature increases the resolution and detail of your images, making them sharper and more defined without compromising quality. Whether you're enlarging a small photo or improving the clarity of a digital image, AI Super-Resolution helps you achieve professional results with ease.

! DirectX 12 feature level 12_0 or higher is required for AI Features to run on your GPU. You can check your GPU's support level by running the dxdiag.exe tool and reviewing the Display tab

-  or by looking up your device's official specifications. If your GPU doesn't meet the requirements, AI Features will still run using your CPU instead. A minimum of 4GB VRAM is required for GPU acceleration for AI Super-Resolution.

How AI Super-Resolution Works:

AI Super-Resolution enhances image quality by analyzing patterns, textures, and colors in the image. It then applies a complex algorithm to upscale the image, reducing noise and blurriness, removing artifacts, and adding pixels where necessary to maintain clarity and detail. This feature is especially useful for enlarging small images or zooming into cropped photos.


Examples of when to use AI Super-Resolution:

- Enlarging low-resolution images for large prints or displays
- Enhancing cropped images to improve their quality
- Increasing the size of older photos taken with lower-resolution cameras

How to apply AI Super-Resolution:

To enhance your images with **AI Super-Resolution**, perform the following:

1. Find the image you want to enhance in **Manage mode** or **View mode** and do one of the following:
 - Right-click it and select **AI Features | AI Super-Resolution**.
 - Press **Shift + Alt + S**.
2. In the **AI Super-Resolution** dialog, choose your preferred settings. The preview will automatically generate a new preview whenever parameters are changed so you can always see what it looks like in real-time.
3. Click **Enhance** to apply Super Resolution to your image. The enhanced image will be saved by default into the same folder as the original. You can adjust this setting within **Options** at the bottom of the **AI Super-Resolution** dialog.



How to apply Batch AI Super-Resolution:

To enhance multiple images at once with **AI Super-Resolution**, perform the following:

1. Find the images you want to enhance in **Manage mode** and do one of the following:
 - Select the images you want, right-click one of them and select **Batch | AI Super-Resolution | AI Super-Resolution**.
 - Select **Tools | Batch | AI Super-Resolution | AI Super-Resolution**.
 - Right-click on an image and select **Batch | AI Super-Resolution | AI Super-Resolution**.
 - Press **Shift + S**.

2. In the **Batch AI Super-Resolution** dialog, choose your preferred settings. The preview will automatically generate a new preview whenever parameters are changed so you can always see what it looks like in real-time.



Only the first image selected will display in the **Preview** when using multiple images in **Batch AI Super-Resolution**.

3. Click **Enhance** to apply Super Resolution to your images. The enhanced images will be saved by default into the same folder as the originals. You can adjust this setting within **Options** at the bottom of the **Batch AI Super-Resolution** dialog.

Settings:

There are five option settings that are available no matter which measurement mode you use:

Show Original	Shows the original image before any modifications for quick comparison.
AI Strength	Adjust the slider to increase or decrease the amount of influence the AI has in the enhancement.
Zoom	Adjust the zoom of the current preview display.
Actual Size	Sets the preview display to show the Actual Size of the image.
Fit Image	Sets the preview display to fit the image within the preview window.

Resize Options:

There are five different resize options you can use to determine how big your image will become. For more information, see [Setting the AI Super-Resolution Options](#).

Percentage	Includes Width (%), Height (%), and Preserve Original Aspect Ratio.
Size in Pixels	Includes Width (px), Height (px), Preserve Original Aspect Ratio, and Fit Within. Fit Within includes: Width and Height, Width Only, Height Only, Width or Height (largest image).
Print Size	Includes Width, Height, Units, Resolution (pixels per inch), Preserve Original Aspect Ratio, and Fit Within. Fit Within includes: Width and Height, Width Only, Height Only, Width or Height (largest image).
Long Edge	Includes Size (Pixels, Inch, cm, mm), and Resolution (pixels per inch).
Short Edge	Includes Size (Pixels, inch, cm, mm), and Resolution (pixels per inch).

Rotating Images

You can rotate images in Manage and View modes using the Rotate icons in the bottom toolbar.



When you rotate unedited JPEG images, ACDSee performs a lossless rotation, meaning no information is lost.

To Rotate Images:

1. In Manage mode or View mode, select one or more images.
2. Click the **Rotate Left** or **Rotate Right** icon in the bottom toolbar.

Rotate Icons

	Rotate Left	Rotates the image 90° to the left.
	Rotate Right	Rotates the image 90° to the right.

Using the Histogram

The Histogram is a graph that represents the distribution of color intensity for each color channel in an image.

To Display and Use the Histogram:

1. In View mode, click **Panes | Histogram**, or **View | Histogram** in Edit mode.
2. On the Histogram, check or uncheck the following checkboxes:
 - **R**: shows or hides the red color channel.
 - **G**: shows or hides the green color channel.
 - **B**: shows or hides the blue color channel.
 - **L**: shows or hides the lightness of the image.

Viewing Images with Image Advance

Image Advance allows you to create a quick slideshow preview of a group of images, or of all the images in a folder.

To Start Image Advance:

1. Open a group of images in View mode.
2. Click **View | Image Advance | Options**.
3. In the Image Advance dialog box, set the options as described below.
4. Click **Start**.
5. To advance to the next image, press **Space**.
6. To return to the previous image, press **Backspace**.
7. To stop or restart Image Advance, press **Pause**.

Image Advance Options

Sequence	Determines the order that you want to display your images. Select one of the following options: <ul style="list-style-type: none"> • Forward • Reverse • Random
Repeat	Automatically restarts the slideshow after the last image has been displayed.
Delay	Specifies how long to display each image. Drag the slider or type a time in milliseconds.
Sound	Check the Play audio clips checkbox to play any audio embedded in the selected images.

Displaying Text on Images in View Mode

You can use the Header/Footer tool to display text with your images in View mode. The text is displayed while you are viewing the image, but does not modify the original image. You can also hide the headers and footers without changing the settings.

To add text directly to your photos and save it as part of the image, see [Adding text to an image](#).

To Edit Image Headers and Footers:

1. In View mode, click **View | Edit Header/Footer**.
2. Do one or both of the following:
 - Check the **Header** checkbox to add text at the top of the image.
 - Check the **Footer** checkbox to add text at the bottom of the image.
3. Select or change the text options as described below.
4. Click **OK**.

Text Options

Alignment	Specifies the justification of the captions.
Background	Adds a background color to the text. Click Color to specify a color.
Description	Displays the text you want to see on your images. Type the text you want to appear, or click inside the field to set an insertion point for inserting metadata.
Insert Metadata	Inserts file-specific information into the text for each image.
Font	Sets the font, size, and color of the caption text.

To Insert Metadata in Image Text:

1. Position the cursor in the **Description** text box where you want to display the file information and click **Insert Metadata**.
2. In the Choose Properties dialog box, select the file information you want to include.
3. Click **OK**.

The information you added is inserted as a placeholder that will be replaced by the specific text for each image.

Hiding Image Text

You can hide either the header or footer, or disable both at once without changing or deleting the information in the header and footer fields.

To Hide the Image Text:

1. In View mode, click **View | Edit Header/Footer**.
2. Do one or both of the following:
 - Uncheck the **Header** checkbox to remove text from the top of the image.
 - Uncheck the **Footer** checkbox to remove text from the bottom of the image.
3. Click **OK**.



To show or hide both headers and footers simultaneously, click **View | Show Header/Footer**.

Selecting Part of an Image

You can use the Select tool in View mode to select a rectangular area of an image. You can then zoom in on the selection, copy the selection, save the selection as a new image, print the selection, and use the selection as the desktop wallpaper.

To Select Part of an Image:

1. Click the **Select Tool** icon.
2. Drag the cursor across the image to create a marquee.
3. Right-click inside the marquee and select one of the options described below.
4. To cancel the selection, click an area of the image outside of the marquee.

Selection Options

Zoom To	Zooms in on the selected area.
Copy	Copies the selected area to the Clipboard.
Save Crop As	Saves the selected area as a new image.
Print	Prints the selected area.
Wallpaper Centered	Creates desktop wallpaper using the selected area and centers it on your desktop, shrinking it to fit if necessary.
Wallpaper Tiled	Creates a tiled desktop wallpaper pattern using the selected area.

Viewing File Properties in View Mode

You can view an image's properties in View mode and edit the information in the Properties pane.

To View an Image's Properties:

In View mode, click **Panes | Properties**.

For more information about the Properties pane, and adding or editing ACDSee Home Metadata, see [Using the Properties Pane](#).

Viewing and Using Brush Files

You can view brush files in Manage mode just like fonts or other files. This means that you can assign ratings or organize them just like any other file in ACDSee. Because many .abr files are actually groups of images in one file, you need to open them in View mode to see the individual images.



This icon indicates an .abr brush file in ACDSee.

To View Brush Files:

In Manage mode, navigate to the folder containing your brush files.

- To see just the top image in any .abr file, hover over the thumbnail to activate the pop-up, or click it to see the image in the Preview pane.
- To view the other images in the .abr file, double-click it to open it in View mode. The file opens in View mode showing the individual images in a pane on the left-hand side.
- To see the number of images, and select them by number, click the down-arrow at the top of the sidebar, and then select the number of the image.
- To scroll through the images, click the right and left arrows at the top of the sidebar, or on each image.

To Use Brush Files in Adobe Photoshop®:

With both Adobe Photoshop® and ACDSee Home open, drag the file from the File List (in Manage mode) onto the Photoshop® window.

Even though nothing appears to happen, the brush is loaded into the Photoshop® brush library. To view the new brushes, open the library and scroll to the bottom of the pane.



To make it even easier to use brushes in Photoshop®, you can [configure it to be your default editor](#). Then you can use **Ctrl + Alt + X** to open Photoshop® and use the brush right away.

Playing Video and Audio Files

You can play video or audio files in many formats in ACDSee. You can control playback volume, and create an image from a video frame.

To Play Video or Audio Files:

In Manage mode, in the File List pane, do one of the following:

1. Double-click a video or audio file.
2. Select one or more files and press **Enter**.
3. Select one or more files, right-click a selected file, and then select **View**.
4. Use the Media toolbar to adjust the volume, pause, loop, or extract frames from playback.

Automatically Playing Audio and Video Files

You can configure your settings to play audio and video files automatically, as soon as you open them in View mode, or as you view them in the [Preview pane](#) in Manage mode.






To Start Playing Media Files Automatically:

1. In Manage mode or View mode, click **Tools | Options | Preview**.
2. Check the **Autoplay audio or video clips** checkbox.
3. Click **OK**.

The Media Toolbar

You can use the Media toolbar to quickly access common media viewing and editing tools.


Media Toolbar Buttons

	Play	Plays the media file or selection. Changes into the Pause button when a media file or selection is playing.
	Extract Frames	<p>Opens a menu you can use to copy, save, and extract video frames.</p> <p> Frames are extracted at the resolution you viewed them at, (your screen resolution).</p>
	Loop	Continuously plays the media file or selection.
	Volume Mute	Click to mute the playback volume, click again to play the volume.

Saving Video Frames as Images

You can extract an individual frame from a video and save it as a still image.

To Extract and Save a Single Video Frame as an Image:


1. Do one of the following:
 - Find the frame you want to capture and press **Pause**.
 - Skip to step 2 as the exact frame you want to extract is playing.
2. On the [Selection and media controls](#) toolbar, click the **Extract Current Frame** button. 
3. In the Extract Current Frame dialog box, select a folder in which to save your file.
4. In the **File name** field, type a filename.
5. Click the **Save as type** drop-down list and select a file format. You can click the **Options** button to select or change any options associated with the file format.
6. Click **Save**.

Adding or Editing Image Audio

ACDSee Home supports images with embedded audio and images with associated audio files.

Images with embedded audio are TIFF or JPEG images with audio saved inside the image file. You can embed audio inside an image file by adding audio to the image.

Images with associated audio are image files paired with separate WAV audio files. Image files and their associated audio files contain the same file name and are located in the same folder. You can associate any WAV file with an image file by giving them the same name and placing them in the same folder, or by adding audio to the image.

 If you move or rename either an image file or the audio file associated with it, both files must be renamed and in the same folder or they will no longer be associated. This does not apply to images with embedded audio.

To Add Audio to an Image:

1. Do one of the following:
 - Select an image in Manage mode.
 - Open an image in View mode.
2. Click **Tools | Image Audio | Edit**.
3. In the Edit Audio dialog box, click the **Browse** button.
4. Select a WAV file and click **Save**.
5. If you would like to truncate or clip the audio file, check the **Use markers** checkbox, and drag the **Start marker** and **End marker** sliders. Do one of the following:
 - Click the **Truncate** button to remove the beginning and end of the audio file (the sections outside of the start and end markers).
 - Click the **Clip** button to remove the section of the audio file inside the start and end markers.
6. To hear a preview of the file, click the **Play** button.
7. Click **OK**.

Recording Audio to an Image

You can record your own audio files and add them to your images. When you add audio to a JPEG or TIFF image, the audio is embedded in the image. With other file formats, the audio file is associated with the image; the audio file is saved in the same folder and is played when the image is viewed.

To Record and Add an Audio File to an Image:

1. Do one of the following:
 - Select an image in Manage mode.
 - Open an image in View mode.
2. Click **Tools | Image Audio | Edit**.
3. In the Edit Audio dialog box, select or change the **Record sound settings** options as described below.
4. Click **Record** and do one of the following:
 - Use a microphone and record a sound.
 - Play audio from an audio player on your computer.
5. Click **Record** to stop the recording.
6. Click **Save As** to save the audio file.
7. In the Save Sound File dialog box, type a name in the **File name** field, and then click **Save**.
8. Click **OK**.

Record Sound Settings Options

Capture device	Specifies which of your computer's devices you want to record the audio.
Input format	Determines which sample rate and audio type are used to record the sound. The formats displayed depend on the sound card you have installed on your computer.
Overwrite	Replaces the recorded audio from the Start marker slider location.
Mix	Combines the recording with the existing audio file.
Insert using start marker	Inserts the recording at the start marker location. Drag the Start marker slider to select a position.
Append to sound file	Adds the recording to the existing audio file.
Replace sound file	Replaces the entire audio file with the new recording.

Printing Images in View Mode

With the ACDSee Home print utility, you can print your images and files on any size of paper, in any orientation, and at any resolution your printer can support. You can also use the print utility to create and print contact sheets, complete with headers, footers, and captions specific to each image.

As you change the options in the Print dialog box, you can view a dynamically updated preview of the image or file and its position on the page. You can adjust the output size, print multiple copies, and change the orientation on each page.

To Print a Single Image:

1. In View mode, select the image you want to print.
2. Click **File** | **Print...**
3. Under **Format**, choose a print size.
4. On the **Printer Options** tab, [specify the printer](#) you want to use, the paper size, the number of copies you want, the range of pages that you want to print, and image resolution.
5. On the **Page Settings** tab, [specify the image position](#) on the paper and the margin widths, and specify the number of prints of each photo.
6. On the **Adjustments** tab, [adjust the settings](#) to compensate for the way your printer handles exposure, contrast, and sharpness.
7. Add [captions, headers, or footers](#).
8. Click **Print**.

To Print All Images:

1. In View mode, click **File** | **Print All...**
2. Under **Print layout**, do one of the following:
 - Select **Full page** and then choose a print size from the **Format** list.
 - Select **Contact sheet** and then set the **Contact sheet format** options to define the appearance of your [contact sheet](#).
 - Select **Layout** and then choose one of the available layout options.
3. On the **Printer Options** tab, [specify the printer](#) you want to use, the paper size, the number of copies you want, the range of pages that you want to print, and image resolution.
4. On the **Page Settings** tab, [specify the image position](#) on the paper and the margin widths.
5. On the **Adjustments** tab, [adjust the settings](#) to compensate for the way your printer handles exposure, contrast, and sharpness.
6. Specify the number of prints of each photo. If you are printing a **Full page** or a **Contact sheet** this option is available on the **Page Settings** tab. If you are printing a **Layout** this option is available below the list of layouts.
7. Add [captions, headers, or footers](#). You can only add captions, headers, or footers if you are printing a **Full page** or a **Contact sheet**.
8. Click **Print**.

Setting an Image as the Desktop Wallpaper

You can select any image and set it as the Windows desktop wallpaper. You can also automatically stretch a wallpapered image to fill the screen, or restore your previous wallpaper.

To Set an Image as the Desktop Wallpaper:

1. Do one of the following:
 - In Manage mode, select an image, and then click **Tools | Set Wallpaper**.
 - In View mode, click **Tools | Set Wallpaper**.
2. Select one of the following:
 - **Centered**: places the image in the center of the screen. If the image is larger than the screen, it is shrunk to fit.
 - **Tiled**: places the image in a tiled pattern that fills the entire desktop.
 - **Stretched**: stretches the image to fit the screen.

The selected image is saved as ACD Wallpaper.bmp in the Windows folder. ACDSee Home automatically changes the wallpaper settings in the Control Panel Display properties to display the image.

To Automatically Stretch Wallpapered Images to Fit the Screen:

1. Click **Tools | Options**.
2. In the Options dialog box, click **General**.
3. On the General page, check the **Automatically stretch wallpaper to fit screen** checkbox.
4. Click **OK**.

To Display the Previous Wallpaper:

Click **Tools | Set Wallpaper | Restore**.

Synchronizing View Mode to a Folder

You can use the Sync to Folder option to change the images being displayed in View mode.

To Synchronize to a Folder:

1. In View mode, click **File | Sync To Folder...**
2. Type the path to the folder you want to synchronize, or click the **Browse** button to locate the folder.

3. Select or change the New Images options as described below.
4. Click **OK**.

New Images Options

Show new images immediately	Displays images as soon as they appear in the folder. If this option is cleared, new images are added to the end of the slideshow.
Ignore open files	Delays adding a new file to the slideshow until the transferring application has finished moving or downloading the file.
Sort by name	Sorts the images displayed in the slideshow by their file name.

To Stop Synchronizing to a Folder:

In View mode, click **File | Sync To Folder...**

Viewing Offline Images

ACDSee Home stores thumbnails and database information for images contained on CDs or other removable media as Photo Discs. You can then browse the thumbnails and view the information for those images even when the disc is not in your CD-ROM drive.

To Add a Photo Disc:

1. Place a disc containing images into your CD-ROM drive.
2. In Manage mode, click **File | New | Photo Disc**.
3. In the New Disc dialog box, type a name for your disc in the **Title** field, and then click **OK**.

You can then browse the contents of the Photo Disc in the Offline Media section of the Folders pane.



If you add or remove images from a disc that you have already added to ACDSee Home as a Photo Disc, you can update the information stored in the database. Insert the disc in your CD-ROM drive, and then right-click the name of the disc in the Folders pane and select **Update Photo Disc**.

By default, ACDSee Home identifies Photo Discs by their serial numbers. This is the most reliable setting to use when working with Photo Discs, particularly if you are importing or converting Photo Discs from previous versions of ACDSee.

However, if you are working with, or planning to work with, multi-session discs, the serial number may be regenerated or changed each time you change the contents of a disc. Therefore, the volume label is the required method of identification for multi-session Photo Discs.

Rebinding Photo Discs

Depending on the method used to identify Photo Discs, ACDSee Home may encounter a Photo Disc that it does not recognize. This is most common when you are using the serial number method to identify Photo Discs and you insert a multi-session disc. ACDSee Home may not recognize the disc, as serial numbers are likely to change when updating a multi-session disc.

You can use the Rebind option to update the identification information, and associate the correct database information with your disc.

To Rebind a Photo Disc to its ACDSee Home Database Information:

1. In the Rebind Photo Disc dialog box, carefully review the Current disc information to be sure that the correct disc is in the drive.
2. Select the Photo Disc record that you want to rebind to the current disc from the **Photo Disc Name** list.
3. Click **Rebind**.

Viewing Images in Another Application

You can open a file in another program from within ACDSee. For example, you can open documents in the application used to create them.

To Use the Shell Open and Edit Commands:

1. In Manage mode, click **File | Shell**.
2. Select one of the following options:
 - **Open**: opens the file using the application that Windows associates with its file extension.
 - **Edit**: opens the file using the default system application, or opens a dialog box where you can select an application.

Showing Originals

When you make changes to your images, the original image is saved so that you can restore the image to its original settings.

To Show the Original Image:

1. In View mode, select an image that has been edited.
2. Click and hold the **Show Original** button in the bottom toolbar.

When you release the mouse button, the edited image is displayed.

Committing Changes

When you make changes to your images, the original image is saved so that you can restore the image to its original settings. If you decide that you want to keep your edited image and save that as your original image, you can commit the changes to the image. This deletes any sidecar files or originals that have been saved, and removes the Edited overlay icon that indicates the image has been edited.

To Commit Changes to an Image:

1. In Manage mode or View mode, select an image that has been edited.
2. Click **Tools | Commit Changes**.

Changing Image Color Depth

You can modify an image's color depth in View mode. Color depth refers to the range of colors an image contains.

To Change the Color Depth of an Image:

In View mode, click **Tools | Modify | Change Color Depth**, and select one of the options described below.

Color Depth Options

Black and White	Two-color black and white palette
16 Grays	16-color grayscale palette
256 Grays	256-color grayscale palette
16 Colors	16-color palette
256 Colors	256-color palette (GIF format uses 256 colors by default)
Hicolor	32,768-color palette
Truecolor	16,777,216-color palette of all colors visible to humans

You can use ACDSee Home to convert an image to any of these color depths. However, to use certain image enhancement tools, filters, blends, and adjustment options, the image must be Hicolor or Truecolor. To edit an image that is not originally Hicolor or Truecolor, you can convert it, edit the image, and then convert it back to its original color depth.

Zooming In and Out

In View mode you can use the Zoom tools to enlarge or reduce the size of the image you are viewing. When an image is zoomed to a larger size than the View mode window, you can use the Scroll tool (hand icon) to pan or scroll the image.

To Zoom an Image In or Out:

- Click once on the image to toggle between your default view and Actual Size view.
- Click **Tools | Zoom**, and then select one of the Zoom menu options.

Zoom Menu Options

Zoom In	Increases the magnification of the image.
Zoom Out	Decreases the magnification of the image.
Actual Size	Displays the image at its original dimensions (100%).
Fit Image	Displays the image at the largest magnification that fits in View mode window.
Fit Width	Fits the image within the left and right sides of the View mode window.
Fit Height	Fits the image within the top and bottom of the View mode window.
Zoom Lock	Displays all images at the zoom option of the current image. If the zoom level is adjusted, the new zoom level is applied to all images that you view.
Zoom To	Opens a dialog box where you can select a zoom level .
Pan Lock	Locks the panned area of an image.



If you select **Fit Image** you can display the previous or next image by pressing the left and right arrow keys on your keyboard.



To change your default image view, click **Tools | Zoom** and select Actual Size, Fit Image (standard), Fit Width, or Fit Height.



You can also quickly access the Zoom Lock on the Toolbar by toggling the Zoom Lock button.

Setting the Zoom Level

You can use the Set Zoom Level dialog box to set a specific zoom level in View mode.

To Set a Specific Zoom Level:

1. Click **Tools | Zoom | Zoom To...**
2. In the Set Zoom Level dialog, select one of the following:
 - **Fit whole image:** zooms the image to fit entirely within the window.
 - **Fit width:** zooms the image to fit the width of the window.
 - **Fit height:** zooms the image to fit the height of the window.
 - **Specify:** specifies a zoom percentage. Type a number in the field or click the drop-down list and select a zoom level.
3. To use this setting as the default View mode zoom level, check the **Lock at this zoom level** checkbox. View mode displays all images based on the specified zoom level.
4. Click **OK**.



If you select **Fit whole image** you can display the previous or next image by pressing the left and right arrow keys on your keyboard.

Automatically Shrinking or Enlarging Images

You can use the settings on the Display page of the Options dialog box to automatically enlarge or shrink images to fit the size of the ACDSee Home window. For information about how the combination of the choices affects the display of images, see the Zoom mode and Resize results table below.

To Automatically Shrink or Enlarge Images:

1. In Manage mode or View mode, click **Tools | Options**.
2. In the Options dialog box, click **View mode | Display**.
3. In the Zoom options area, select one of the following options from the **Default zoom mode** drop-down list:
 - **Actual Size:** keeps images at their original size.
 - **Fit Width:** resizes images to fit the width of the View mode window.
 - **Fit Height:** resizes images to fit the height of the View mode window.
 - **Fit Image:** resizes images to fit the size of the View mode window.
4. Select one of the following options from the **Resize** drop-down list:
 - **Reduce Only:** reduces large images to fit the size of the View mode window.
 - **Enlarge Only:** enlarges smaller images to fit the size of the View mode window.

- **Reduce or Enlarge:** reduces large images, and enlarges smaller images to fit the size of the View mode window.

5. Click **OK**.

Zoom Mode and Resize Results

	Fit Image	Fit Width	Fit Height
Reduce Only	Reduces large images to fit the size of the View mode window. Images that are smaller than the View mode window are displayed at their original size.	Reduces large images to fit between the left and right sides of the View mode window. Images that are smaller than the View mode window are displayed at their original size.	Reduces large images to fit between the top and bottom of the View mode window. Images that are smaller than the View mode window are displayed at their original size.
Enlarge Only	Enlarges small images to fit the size of the Viewer. Images that are larger than the View mode window are displayed at their original size.	Enlarges small images to fit between the left and right sides of the View mode window. Images that are larger than the View mode window are displayed at their original size.	Enlarges small images to fit between the top and bottom of the View mode window. Images that are larger than the View mode window are displayed at their original size.
Reduce and Enlarge	Reduces large images and enlarges small images to fit the size of the View mode window.	Reduces large images and enlarges small images to fit between the left and right sides of the View mode window.	Reduces large images and enlarges small images to fit between the top and bottom of the View mode window.



If you select **Fit Image** you can display the previous or next image by pressing the left- and right-arrow keys on your keyboard.

Using the Navigator to View Select Areas of an Image

Use the Navigator pane to display a thumbnail overview of images that are larger than the View mode display area. In the Navigator, a marquee indicates the area of the image that is visible.

To Display and Use the Navigator Pane:

1. In View mode, click **Panes | Navigator**.
2. Drag the slider to increase or decrease the magnification of the image in View mode.
3. Drag the marquee to the area of the image you would like to display in View mode.

To Use the Quick Navigator Pane:

1. In View mode, click and hold the **Navigator** button in the bottom toolbar.
2. Drag the marquee to the area of the image you would like to display in View mode.

Panning a Magnified Image

In View mode, you can pan large images by moving them vertically, horizontally, and diagonally across the display area to view specific areas of the image. When an image is larger than the ACDSee Home window and you use the Scroll tool, the cursor changes to a hand.

To Pan an Image:

Do one of the following:

- Drag the image to center the area you want to view.
- Press an arrow key. You can hold the **Ctrl** key to pan quickly, or hold the **Shift** key to pan more slowly.

Using Pan Lock

You can use the Pan Lock setting to automatically center the same area of a series of larger images in View mode.

To Use Pan Lock:

1. In View mode, pan over a large image to a specific area you want to view.
2. Using the [Zoom](#) menu, zoom in on the image until you reach the magnification you want to use for all of your images.
3. Click **Tools | Zoom | Zoom Lock** to keep the current zoom level.
4. Click **Tools | Zoom | Pan Lock**.

As you move through your images, each one will be automatically zoomed and panned to the same area.

Magnifying Specific Areas of an Image

You can view specific areas of an image at a higher magnification in the Magnifying Glass pane.

To Use the Magnifying Glass Pane:

1. In View mode, click **Panes | Magnifying Glass**.
2. Move the cursor over an area of the image to view that area in the Magnifying Glass pane.
3. Change the Magnifying Glass pane settings by doing any of the following:
 - Move the slider at the bottom of the Magnifying Glass pane to increase or decrease the magnification.
 - Check the **Fixed** checkbox to apply the slider setting to the original size of the image. Uncheck the **Fixed** checkbox to apply the slider setting to the magnification of the zoomed image in View mode.
 - Check the **Smooth** checkbox to apply anti-aliasing to the magnified portion of the image, or uncheck the **Smooth** checkbox to view the individual pixels. Anti-aliasing reduces jagged-lines, also known as 'jaggies'.

Chapter 6: Edit Mode

Make your final edits in Edit mode, where you can apply fine-tuned adjustments on the more limited RGB image data. Use the tools in Edit mode for any touch-ups to specific areas of your images.

In Edit Mode You Can:

- [Use the Selection tools](#) to select and apply edits to a specific part of the image.
- [Use the Edit Brush](#)
- [Remove flaws](#), [red eye](#), [adjust skin tone](#).
- Add [text](#), [watermark](#), [borders](#), [vignettes](#), [a tilt-shift](#), [special effects](#), and [drawing tools](#).
- [Crop](#), [flip](#), [resize](#), and [rotate](#).
- Adjust lighting using the [Exposure](#), [Levels](#), [Auto Levels](#), [Tone Curves](#), and [Light EQ™](#) filters.
- Adjust color using the [White Balance](#), [Color EQ](#), [Convert to Black & White](#), [Split Tone](#), and [Color LUTs](#) filters.
- Add details to your image using [Sharpen](#), [Blur](#), [Remove Noise](#), [Add Noise](#) or [Clarity](#) filters.

Using Edit Mode

In Edit mode, you can use the editing tools to fine tune your image, remove red eye, and apply special effects.

Editing an Image

To Edit an Image:

1. Select **Edit** mode.
2. Do any one or more of the following:
 - At the top of the panel, use the [Selections](#) or [Drawing tools](#).
 - In the Enhance group, click [Red Eye Reduction](#), [Skin Tune](#) or [Repair Tool](#).
 - In the Add group, click [Text](#), [Watermark](#), [Borders](#), [Vignette](#), [Drawing tools](#), [Tilt-Shift](#), [Grain](#), or click [Special Effect](#) and select an effect.
 - In the Geometry group, click [Rotate](#), [Flip](#), [Crop](#), or [Resize](#).
 - In the Exposure/Lighting group, click [Exposure](#), [Levels](#), [Auto Levels](#), [Tone Curves](#), [Light EQ™](#) or [Dehaze](#).







- In the Color group, click [White Balance](#), [Color EQ](#), [Convert to Black & White](#), and [Color LUTs](#).
 - In the Detail group, click [Sharpen](#), [Blur](#), [Clarity](#), or click Noise to [remove](#) or [add](#) noise.
3. You have several options in saving your images. See [Saving images in Edit](#) for more information.

Reverting to Original Settings

You can discard your Edit settings and revert to the original settings for your image. For steps to revert your image, see [Restoring originals](#).




Histogram and Image Viewing Controls

While editing an image, you can adjust the magnification with the zoom controls, located in the bottom right corner.

Histogram		<p>Displays the histogram preview for the current image. The histogram provides a graphical representation of the intensity level of pixels within each color channel. Spikes at either end of the graph indicate clipped colors. Keeping the histogram open is particularly useful when adjusting exposure, as the histogram reflects all adjustments as you make them.</p> <p>You can also display the Histogram by selecting View Histogram.</p>
Undo/Redo		<p>Undo to discard all changes made on the current tab. Redo to return to the options that you had selected prior to clicking Undo. In Edit, Undo and Redo buttons display the changes you can undo or redo.</p>
Reset		<p>Click on the Reset button to reset the image to its default settings.</p>
Display Full Screen		<p>Displays the image on a full screen. Press F to view full screen and to return to Edit mode.</p>
Actual Size		<p>Returns the current image to its actual size.</p>
Navigator Pane		<p>Automatic Window: when Automatic Window is enabled, the Navigator pane appears as soon as you zoom in on a photo. Drag your cursor to the section of the image you would like to see magnified. Release the cursor to settle on an area of the image.</p> <p> Right-click on the Navigator pane to switch from Automatic to Manual.</p> <p>Manual Window: when Manual Window is enabled, you can view the Navigator pane by selecting the Navigator icon.  The Navigator icon only appears when the image is magnified or if the Actual Size icon has been clicked. Click and hold the Navigator icon to display a small duplicate of your image. Then drag your cursor to the section of the image you would like to see magnified. Release the cursor to settle on an area of the image.</p>



Right-click on the Navigator icon to switch from Manual to Automatic.

Fit Image		Reduces the image to fit within the Edit mode area.
Show Previous		Toggles the changes on or off, to compare the current image to the last saved version.
Zoom slider		Increases the size of the image if you drag it to the right, decreases the size if you drag to the left.
Zoom drop-down list		Displays a list of zoom sizes to select.

Using Color Pickers in Edit Mode

When you use the color pickers in Edit mode, the RGB and luminance values beside the color picker relate to the image before any new and unsaved edits. You can see the up-to-date RGB values for the image as edited in the status bar at the bottom of the screen.

Using Presets in Edit Mode


Many ACDSee Home editing tools and special effects allow you to save your settings as presets. This is convenient when you frequently use the same settings for a particular tool or effect.

For most tools, ACDSee Home automatically saves the last option settings you applied to an image when you clicked Apply or Done. This preset is called Last Used.



The Save Preset and Delete buttons are located at the top of an editing tool's panel.

To Save a Preset:


1. In Edit mode, select a tool and specify its settings.
2. Click the **Save Preset** button. 
3. In the New Preset dialog box, enter a name for your preset, and then click **OK**.

The new preset will appear in the tool's Presets drop-down list.

To Use a Previously Saved Preset:

1. In Edit mode, select the tool for which you created the preset.
2. Click the **Presets** drop-down list and select the preset you want to apply.

To Delete a Preset:

1. In Edit mode, select the tool for which you created the preset.
2. Click the **Presets** drop-down list and select the preset you want to delete.
3. Click the **Delete** button. 
4. In the Confirm Delete dialog box, click **Yes**.

Using the Undo/Redo Button

You can undo and redo your changes when editing an image.

To Undo a Change:

In Edit mode, do one of the following:

- Click the **Undo** button found at the bottom of the left pane.
- Use the keyboard shortcut **Ctrl + Z**.

To Redo a Change:

In Edit mode, do one of the following:

- Click the **Redo** button found at the bottom of the left pane.
- Use the keyboard shortcut **Ctrl + Y**.

Restoring Originals

 If you have committed changes to an image, you cannot restore the original.

You can discard all your changes and revert to the original image.

To Revert an Image Back to the Original in Edit:

In Edit mode, select **File | Restore to Original**.

To Revert an Image Back to the Original in Manage or View Mode:

1. Select the image.
2. Select **Tools | Restore to Original**.

Using the Edit Brush

While the tools in Edit mode allow you to make a variety of global adjustments, sometimes you may only want to adjust specific areas of your photos. For example, instead of blurring an entire photo, you may want to blur certain areas, such as the background. To do this, and other local adjustments, you can use the Edit Brush.


The Edit Brush allows you to selectively edit your photo by simply brushing on the effects. The Edit Brush is essentially creating a mask that is used to determine which pixels will be affected by the current settings of the chosen operation.







Edit Brush

The Edit Brush button displays at the center of the top editing panel toolbar for all applicable Edit mode tools.

To Use the Edit Brush:

1. In Edit mode, select the tool you want to use.
2. Click the **Edit Brush** button to enter Brushing mode and open the Brush controls.  Or, toggle the Brush panel open and closed with the **B** key.
3. Specify the brush settings in the panel or as you work as described in the table below.
4. Start painting the effects on your photo.
5. Adjust the sliders to get the effect you want.
6. Press **Done** to apply your brush strokes.

Edit Brush Controls

Add brush stroke	Brush while holding the left mouse button down.
Erase brush stroke	Brush while holding the right mouse button down.
Nib Width	Adjusts the size of the brush. You can use the mouse wheel to adjust nib width or adjust the Nib Width slider.
Feathering	Adjust the slider to control the softness of the transition between the brush strokes and the image. Use Ctrl + mouse wheel to adjust the amount of feathering or adjust the Feathering slider.
Pressure	Adjust the slider to control the strength of the brush.
Alternating between Brush mode and cursor-applied tools	For filters that involve drawing or clicking on the image, such as Light EQ™ and White Balance, hold down the Alt key to switch from Brush mode to using the tool.
Clear all brush strokes	 Removes all brush strokes from the image.
Invert all brush strokes	 Toggle this option to invert brushed strokes. This makes brushed areas no longer brushed and untouched areas brushed. This is useful if you want the majority of the image brushed and a small section untouched. Simply brush only the small area you don't want affected and invert the brush strokes.
Load last applied brush strokes	 Applies effects to the area most recently brushed and applied.
Show brush strokes	 <p>When this option is checked, your brush strokes will be displayed in the color shown. This is helpful when brushing a complex area with a subtle effect, as it can be difficult to tell if you have missed a spot. Alternatively, hold down the S key to see your brush strokes on the image.</p>



When you click the Edit brush and enter Brushing mode, you need to apply brush strokes in order to see any of your adjustments.



To exit Brushing mode, toggle the Edit brush button. 

Creating Straight Lines:

Hold the **Shift** key while using the **Edit Brush** to draw horizontal or vertical lines. For example, holding **Shift**, then clicking and dragging horizontally will lock the cursor into horizontal only so long as shift is being held. Release **Shift** to return to free hand brushing. You can even release **Shift** to return to free hand brushing, then press it again while still drawing the same line to unlock and re-lock the brush at will.

Creating Diagonal Lines:

Using the **Edit Brush**, you can create straight diagonal lines by placing two points on the image. Place the cursor where you want the line to begin, press and hold **Shift**, then **Left-Click** on the image to create a point. Let go of **Shift**, and move the brush to where the line will end, press and hold **Shift**, then **Left-Click** again to create a second point. A straight line will fill in between these two points.

The Edit Brush is enabled in many of the editing tools and special effects filters. When it does not make sense to have this option, it is omitted. The Edit Brush is not available in the following tools: Crop, Resize, Rotate, Flip, Text, Red Eye Reduction, Repair Tool, and Selections.

Using the Gradient Tool


While the tools in Edit mode allow you to make solid, global adjustments, sometimes you want these effects to gradually progress over your photo. For example, instead of applying a blur across an entire photo, you may want a blur that advances across the image, or advances over a section of the image. Use the Gradient tool to gradually progress an effect across an image.



Gradient Tool

The Gradient tool button displays at the center of the top Editing panel toolbar for all applicable Edit mode tools.

To Use the Gradient Tool:

1. In Edit mode, select the tool you want to use.
2. Click the **Gradient** tool button  to enter Gradient mode. Or, toggle the Gradient panel open and closed with the **G** key.
3. Specify the gradient settings in the panel or as you work, as described in the table below.
4. Position the guides on your photo. Inside the guide boxes, the gradient is transitioning. On either side of the boxes, the effect being applied by the Gradient tool is at full strength or not applied at all. To make this clearer, check the **Show gradient mask** checkbox. Move the boxes to define where the effect will begin or end. Hold down the **Shift** key while positioning the effect to lock to the nearest 45° angle, for straightness.
5. Adjust the sliders to get the effect you want.
6. Press **Apply** or **Done**.

Gradient Tool Options

Invert gradient



Toggle this option to invert the gradient. By pressing the Invert button after applying a gradient beginning at the top of the image, the gradient would now begin at the bottom, and vice versa.

Show gradient mask



When this option is checked, your gradient mask will be displayed in the color shown. Alternatively, hold down the **S** key to see the mask on the image. Click the drop-down arrow to select another display color.

Alternating between the Gradient tool and cursor-applied tools

For filters that involve drawing or clicking on the image, such as Light EQ™ and White Balance, hold down the **Alt** key to switch from Gradient mode to using the tool.



To exit Gradient mode, toggle the Gradient tool button.



To maintain your gradient mask while switching to [Edit Brush mode](#), hold down **Shift** and click the Edit Brush button. This allows you to add to the gradient mask or erase parts of it that you don't want.



The Gradient tool is enabled in many of the editing tools and special effects filters. When it does not make sense to have this option, it is omitted. The Gradient tool is not available in the following tools: Resize, Crop, Rotate, Drawing Tools, Vignette, Borders, Text, Repair Tool, Red Eye Reduction, and Selections.

Using the Radial Gradient Tool

While the Edit tools allow you to make a variety of adjustments, sometimes you want these effects to draw attention to a specific area of your photo. For example, instead of applying sharpening across an entire photo, you may want to only sharpen the center subject. Use the Radial Gradient tool to apply effects around, or directly to, a center point.




Radial Gradient Tool

The Radial Gradient tool button displays at the top of the Editing panel toolbar for all applicable Edit mode tools.

To Use the Gradient Tool:

1. In Edit mode, select the tool you want to use.

2. Click the **Radial Gradient** tool button  to enter Radial Gradient mode. Or, open and close the Radial Gradient panel with the **R** key.
3. Specify the Radial Gradient settings in the panel or as you work, as described in the table below.
4. Position the guides on your photo. Inside the circle, the image is unaltered. At the perimeter of the circle, the effect being applied by the Radial Gradient is transitioning between not applied at all (inside), and full strength (outside). To make this clearer, check the **Show gradient mask** checkbox. Hold down the **Shift** key while positioning the effect to change the radial gradient to a perfect circle.
5. Adjust the sliders to get the effect you want.
6. Press **Done**.

Gradient Tool Options

Invert gradient



Toggle this option to invert the radial gradient. By pressing the Invert button, the effects will be applied to the center of the image (inside the circular guides), and outside of the radial gradient will be unaltered.

Show gradient mask



When this option is checked, your radial gradient mask will be displayed in the color shown. Alternatively, hold down the **S** key to see the mask on the image. Click the drop-down arrow to select another display color.


Alternating between the Radial Gradient Tool and cursor-applied tools

For filters that involve drawing or clicking on the image, such as Light EQ™ and White Balance, hold down the **Alt** key to switch from Radial Gradient mode to using the tool.



To exit Radial Gradient mode, toggle the Gradient tool button. 



To maintain your radial gradient mask while switching to [Edit Brush mode](#), hold down **Shift** and click the Edit Brush button. This allows you to add to the gradient mask or erase parts of it that you don't want. 

The Radial Gradient tool is enabled in many of the editing tools and special effects filters. When it does not make sense to have this option, it is omitted. The Radial Gradient tool is not available in the following tools: Resize, Crop, Rotate, Drawing Tools, Vignette, Borders, Text, Repair Tool, Red Eye Reduction, and Selections.

Using Blend Modes and Opacity

When using a tool in Edit, there are blend mode and opacity tools. These tools give you creative control and let you combine the two to create a new image. You can apply blend modes and opacity to an entire image or to a selected part of an image.

Opacity

The Opacity slider changes the opacity of the edited image. It gives you control of how much of the edit should be visible on the image.

Blend Modes

The ability to control how the edits and the image merge means that other blend modes besides opacity can be used to affect the final image.

Normal	Pixels in the edited image are combined with those in the original. Only opacity affects this blend.
Screen	Combines the edited image color with the inverse of the original photo color, resulting in a color that is the same or lighter.
Multiply	Combines the edited image color with the original photo to produce a darker color. Multiplying any color with black produces black; multiplying any color with white leaves the color unchanged.
Dodge	Combines the edited image color with the original pixels in the photo to produce a lighter color.
Burn	Combines the edited image color with the original pixels in the photo to produce a darker color.
Overlay	Preserves the shadows and highlights of the lower layers while applying either Multiply or Screen blend mode based on the original image area's color values.
Difference	Subtracts the edited image color from the color of the original photo. Any white in the edited image produces a true negative of the color in the image, while black produces no effect.
Darken	Applies pixels in the edited image that are darker than the original image. Pixels in the edited image that are lighter than the original image disappear (based on RGB values).
Lighten	Applies pixels in the edited image that are lighter than the original image. Pixels in the edited image that are darker than the original image disappear (based on RGB values).
Hard Light	Adds strong highlights or shadows by applying Multiply or Screen based on the original image area's color values.
Soft Light	Adds soft highlights or shadows by darkening or lightening based on the original image area's color values.
Hue	Applies the hue value of colors in the edited image to the color of the original image areas.
Saturation	Applies the saturation value of colors in the edited image to the color of the original image areas.
Color	Applies the hue and saturation of the edited image to the image. This blend does not affect the luminance of the original image.
Luminosity	Applies the lightness value of colors in the edited image to the color of the original image areas.

Dissolve	Applies some pixels from the edited image layer onto the original image, resulting in specks of color. The Opacity slider controls the amount of speckling.
Exclusion	Like Difference, but with less contrast, Exclusion subtracts the blend color from the color of the underlying photo. Any white in the blend color produces a true negative of the color in the image, while black produces no effect.
Vivid Light	Combines the blend color with the underlying pixels in the photo by increasing or decreasing contrast to produce a lighter or darker color, as determined by the blend color.
Pin Light	When the light source is lighter than 50% gray, the pixels darker than the light source are replaced. Pixels lighter than the light source remain the same. When the light source is darker than 50% gray, the pixels lighter than the light source are replaced. Pixels darker than the light source remain the same.
Linear Light	Dodges or burns by lightening or darkening the brightness value, depending on the blend color.
Hard Mix	Applies red, green, and blue channel values of the blend color to the RGB values of the image.
Subtract	Subtracts the blend color from the image (base) color in each channel.
Divide	Divides the blend color from the image (base) color.
Darker Color	From the blend color and the image (base) color, the lower channel values are chosen.
Lighter Color	From the blend color and the image (base) color, the higher channel values are chosen.



You can use the [Edit Brush](#) to paint an effect onto specific areas of your image, and then set the blend mode and opacity slider to change the way the effect is applied.

The blend mode and opacity controls apply to many of the editing tools and special effects filters. When it does not make sense to have these controls, they are omitted. The blend mode and opacity controls are not on the following tools: Crop, Resize, Rotate, Flip, Text, Red Eye Reduction, Repair Tool, Selections.


Saving Images in Edit Mode

Saving Images

When you have finished editing an image, you can choose from one of the many options for saving your image, depending on what you want to do next.

To Save the Image and Return to the Mode You Were in Previously:

1. Click **Done**.
2. Select one of the following:

Save	Save your changes.
Save as	<p>Save a copy of your edited image with a new name or format.</p> <p>Depending on your file type, any of the following checkboxes appear in the bottom left corner of the Save as dialog box:</p> <ul style="list-style-type: none"> • Preserve Metadata: retains metadata with the new image. • Preserve database information: maintains your catalog information, such as ratings. • Embed Color Profile in Image: retains color profile selected in Color Management with your new image.
Discard	Discard your changes.
Cancel	Remain on the same image, with your changes intact, without saving the image.
AutoSave	<p>You can enable AutoSave in order to avoid selecting a saving option each time you finish with an image. When AutoSave is enabled, pressing Done, or selecting another image from the Filmstrip will prompt ACDSee to automatically save your changes in Edit mode. You will no longer see the Save Changes dialog. To disable AutoSave, choose Tools Options... In the Options dialog, click Edit Mode. Then uncheck the AutoSave all changes checkbox.</p> <p> AutoSave is not available for RAW images.</p>

To Save the Image and Continue Processing Other Images:

1. Click **Save**.
2. Select one of the following:
 - **Save**: save your changes.
 - **Save As**: save a version of your edited image with a new name or format and switch to the updated image.
 - **Save a Copy**: save a copy of your edited image with a new name or format, and continue to work on the original file.



Save a Copy is useful for making multiple versions of an image while continuing to work from the original file instead of a new processed copy. For example, if you take a RAW image and save a copy of it as a JPG, instead of switching to this lossy JPG image, you remain on the RAW file with the settings still intact.



Save is not available for RAW file formats because you cannot directly save changes to a RAW file.

To Discard Changes to the Image and Return to the Mode You Were in Previously:

Click **Cancel** or use the keyboard shortcut **Esc**.

Using Selections

Use Selections to isolate an area of a photo in order to apply edits or filters to only that area, rather than the whole photo. There are four different selection tools and each selects an area of a photo in a unique way. The controls available change depending on which tool you select.





To Use a Selection Tool:

1. In Edit mode, at the top of the panel, select the button for one of the following selection tools: Rectangular selection tool, Elliptical selection tool, Lasso selection tool, Magic wand selection tool. See below for more detailed steps for using these tools.

You can use Selections with the following Edit tools:

- Enhance: Skin Tune
- Add: Vignette, Special Effects, Tilt-Shift, Drawing tools, Grain
- Exposure/Lighting: Exposure, Levels, Auto Levels, Tone Curves, Light EQ™
- Color: White Balance, Color EQ
- Detail: Sharpen, Blur, Noise, Clarity, Chromatic Aberration

The Selection Tools


- 
Freehand Lasso: click the left mouse button and drag the cursor to draw around the area that you wish to select. As you draw, a line appears showing where you have drawn. When you release the mouse, the end of the line joins to the start automatically to complete the selection. The whole selection animates and looks like marching ants.
- 
Magic Wand: click on any area of the image and all the pixels the same color are included in the selection. You can choose whether to select only the same color pixels that are actually touching the one you clicked, or all the pixels in the photo that are similar. You can increase the threshold to include more pixels in the selection. The lower the threshold, the more similar a pixel has to be to the one clicked in order to be included. The greater the threshold, the more different a pixel can be and still be in the selection.
- 
Rectangular or 
Elliptical: click and drag either a rectangle or an ellipse that begins where you first click and ends when you release the mouse. Hold **Shift** when using the **Rectangular** Selection tool to make it into an equilateral **Square** shape, or while using the **Elliptical** Selection tool to make it into an equilateral **Circular** shape.

Using the Selection Tools


To Use the Lasso:

1. Select the **Lasso** button.
2. On the image, click and hold down the left mouse button as you draw around the area you want to select.
3. Release the mouse button to complete the selection.



4. To clear the selection, click anywhere on the image (for the Lasso , Rectangular, or Elliptical selection).
5. To add to an existing selection, hold down **Shift**, or press the **Add to selection** button in the Context bar, and draw a shape that includes any part of the original selection line. 


When you release the mouse, the original selection expands to include the outer edge of your addition.



6. To add multiple areas into your selection, hold down **Shift**, or press the **Add to selection** button in the Context bar and draw around any part of the image. 


As long as you do not touch the line of any other selection, you can add several separate areas to a selection.



7. To subtract from a selection, hold down **Ctrl**, or press the **Subtract from selection** button in the Context bar, and draw a shape that includes part of the original selection, or encircles it completely. 
8. If you wish to apply edits or effects to the outside areas of the image, you need to click **Select | Inverse** to reverse the selected area.

Now the selection includes all the outside areas of the image with the central area outside the selection.



 You can preview the selection mask by holding down the Preview button: 

You can select an editing tool or a special effect to [apply to the selection](#).

To Use the Magic Wand:

1. Select the **Magic Wand** button.
2. Click any color in the image.
3. Do any of the following:
 - Slide the **Threshold** slider to adjust the number of pixels to be included or excluded. The Threshold slider sets how similar a pixel needs to be to the one you clicked in order to be included in the selection.
 - Click the **Connected** checkbox if you want to include only pixels that are touching the one you clicked.
 - Hold down **Shift** and click around the selection to include more pixels.
 - Hold down **Ctrl** and click around the selection to remove pixels from the selection.
4. From the Wand type drop-down list, select one of the following:
 - **Brightness**: selects pixels similar in brightness to the area of the image you clicked.
 - **Color**: selects pixels similar in hue and brightness to the area of the image you clicked.



 **Color is generally your best option.**

- **RGB**: selects pixels with red, green, and blue combination similar to the area of the image you clicked.

 You can preview the selection mask by holding down the Preview button: 

You can select an editing tool or a special effect to [apply to the selection](#).

To Use the Rectangular or Elliptical Selection Tool:

1. Select either the **Rectangular** or **Elliptical** button.
2. Click and drag to draw the selection on the image.
3. Do any of the following:
 - To add to an existing selection, hold down **Shift**, or use the **Add to selection** button , and drag another selection that includes any part of the original selection line. Release the mouse and the selection now includes the additional area.
 - To add multiple areas to your selection, hold down **Shift** and drag as many as you want.
 - To subtract from an existing selection, hold down **Ctrl**, or use the **Subtract from selection** button , and drag another selection that intersects with the one you want to reduce. Release the mouse and any part that was inside the new selection is removed.




You can preview the selection mask by holding down the Preview button: 

You can select an editing tool or a special effect to [apply to the selection](#).

Combining the Tools

You can use the Selection tools separately or in combination. For example, you can use the Magic Wand to select most of a particular color, then switch to the Freehand Lasso to add to, or subtract from, the selection. Or you could use the Rectangular selection to select a large general area, then refine it using the Freehand Lasso.

To Combine Selection Tools:

1. Choose a tool and make a selection.
2. Switch to another tool.
3. Press the **Add to selection** button. 
4. Make another selection.

Saving Selections as Presets:

You can save your settings as a preset for future use. After you have made a selection, click **Select | Save Selection...**

To use a previously saved selection, click **Select | Load Selection...**

To delete a saved selection, click **Select | Manage Selections...**

Applying Edits or Effects to Selections

You can use the Selections tools to isolate an area of an image. Once selected, you can apply many of the editing tools, such as color and exposure, or any of the special effects filters, to the selected area.

An active selection in an image looks like a line of marching ants.




To Apply an Edit or Effect to a Selection:

1. Use the [Selections tools](#) to create a selection.
2. Select a tool to use from any of the following groups:
 - Exposure/Lighting
 - Color
 - Detail
 - Add (Special Effects)

 Ensure that the **Use Selection** button adjacent to the **Feathering** slider is toggled on.

3. Use the tool to edit the image.

Use Any of These Special Selections Options:

Use Selection		Click to use the selection or apply the edit or effect to the whole image. This control means you can edit just the selection, then deselect Use Selection and apply another edit to the whole image without clearing the selection.
Invert Selection		Click to invert the selection.
Feathering		<p>Drag to increase or decrease the blurring between the edge of the selection and the edit or effect.</p> <p>Feathering prevents an unnatural or sharp transition between the selection and the rest of the image as it blends the edges. This control also makes it unnecessary for your selection to be perfectly on the edge of the area you want to select.</p>
Show/Hide Selection		Click to show or hide the marching ants around the selection. Hiding the selection line makes it easier to judge the effect of various effects. Press Ctrl + Alt + Z to enable or disable.

Reducing Red Eye

You can use the Red Eye Reduction tool in Edit mode to correct red eye in digital photographs.

To Correct Red Eye:

1. In Edit mode, in the Enhance group, select **Red Eye Reduction**.



You can also access the Red Eye Reduction tool from the Filter drop-down menu or Filter toolbar.

2. Use the Zoom tools in the bottom right corner to enlarge and center the eye you want to correct.
3. Click within the red portion of the eye.
4. In the Red Eye Reduction group, adjust the sliders as described below.

Red Eye Reduction Options

Size	Drag the slider to the right to increase the size of the area being darkened, or to the left to decrease.
Darkening	Drag the slider to the right to intensify the fill color, or to the left to lighten.



Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.



You can right-click a slider to reset to the default value.



Scroll with your mouse to adjust the size of the area you would like to darken at anytime.



You can show or hide the outline of the darkened area by checking or unchecking the **Show Outline** checkbox.



Press **Delete** to remove the currently selected red eye adjustment.

Removing Flaws

You can use the Repair Tool to remove flaws, such as:

- Skin blemishes
- Telephone wires and other unwanted objects
- Flash flares from snowflakes or windows
- Lens scratches and water drops

There are two options available for the Repair Tool: the Healing Brush, and the Cloning Brush.

Heal: when you select the Healing Brush, the Repair Tool copies pixels from one area of a photo to another, but it analyzes the pixels in the source area before copying them. It also analyzes the pixels in the target area, and then blends the pixels of both source and target, to match the

surrounding area. This ensures that the lighting and color of the replacement pixels integrate with the surrounding area. The Healing Brush works particularly well with photos that involve complicated textures, like skin or fur.

Clone: when you select the Cloning Brush, the Repair Tool copies the exact pixels from one area of a photo to another, creating an identical image area. The Cloning Brush is more effective for photos that have strong, simple textures or uniform colors, as it is more difficult to identify the copied pixels in the finished photo.



You can [save your settings as a preset](#) for future use.

To Remove Flaws from a Photo:

1. In Edit mode, in the Enhance group, select **Repair Tool**.



You can also access the Repair Tool from the Filter drop-down menu or Filter toolbar.

2. Select one of the following:
 - **Heal:** copies the pixels from the source area to the target area, and blends pixels into the surrounding image area.
 - **Clone:** copies the pixels from the source area to the target area.
3. Drag the **Nib Width** and **Feathering** sliders as described in the table below.
4. Right-click the image to set a source location. Pixels will be copied from this location and used in the target location.
5. Click and drag over the area that you want to cover. If you selected the healing brush, ACDSee Home analyzes and replaces the pixels when you release the mouse button.
6. Do one of the following:
 - Click **Done** to apply your changes and close the tool.
 - Click **Cancel** to discard all changes and close the tool.



Click **Reset** to reset the sliders. If you saved your changes, you cannot reset your settings.



Scroll with your mouse to adjust the brush size as you work, or press the **Shift** key while you scroll to adjust feathering.

Drawing Straight Lines:

Hold the **Shift** key while using any of the repair tools to draw horizontal or vertical lines. For example, holding **Shift**, then clicking and dragging horizontally will lock the cursor into horizontal only so long as shift is being held. Release **Shift** to return to free hand brushing. You can even release **Shift** to return

to free hand brushing, then press it again while still drawing the same line to unlock and re-lock the brush at will.

Drawing Diagonal Lines:

Using the any of the repair tools, you can create straight diagonal lines by placing two points on the image. Place the cursor where you want the line to begin, press and hold **Shift**, then **Left-Click** on the image to create a point. Let go of **Shift**, and move the brush to where the line will end, press and hold **Shift**, then **Left-Click** again to create a second point. A straight line will fill in between these two points.

Repair Tool Options

Nib Width	Sets the width of the brush. The maximum brush width is relative to the size of your image.
Feathering	<p>Sets the amount to feather on the edge of the brush to prevent sharp transitions between the original and healed part of the photo.</p> <p>Feathering is set as a percentage of the nib width, not as a specific number of pixels. This means that you do not have to adjust the feathering when you reset the Nib Width, as it automatically adjusts to a percentage of the new nib width.</p>
Pressure	After setting a source point for the Clone tool, adjust the slider to control the strength of the effect being applied.
Show preview in cursor	Check this checkbox to display a preview of your selected source point in the cursor.



You can right-click a slider to reset to the default value.

Adjusting Skin Tone

You can use the Skin Tune tool to even skin tone and smooth away blemishes and flaws.

To Correct Skin Tone:

1. In Edit mode, in the Enhance group, select **Skin Tune**.



You can also access the Skin Tune tool from the Filter drop-down menu or Filter toolbar.

2. On the Skin Tune panel, adjust the settings as described below.

3. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

Skin Tune Options

Smoothing	Refines skin by suppressing texture detail.
Glow	Increases the brightness of skin while subtly smoothing.
Radius	Specifies the scale of the texture detail that is affected by the effect. A lower value enhances small details, while a large value enhances larger details.

Adding Drawings to Your Image

You can use the Drawing Tools in Edit mode to add lines and shapes, such as squares, circles, and arrows to your image. You can also adjust the width, feathering, and blending of your brush, which is useful for creating subtle and dramatic drawings.

To Draw on Your Image:

1. In Edit mode, at the top of the panel, select from the following tools:

Hand

Use the Hand tool to exit out of any other drawing or selection tool. If you have a scrollable image, the Hand tool also allows you to pan it.

Rectangle

Drag over the image to create rectangle. Press **Shift** as you draw to create a square. To fill your shape with color, ensure that the Fill checkbox is checked.

Ellipse

Drag over the image to create an ellipse. Press **Shift** as you draw to create a circle. To fill your shape with color, ensure that the Fill checkbox is checked.

Line

Drag over the image to draw a straight line. Press **Shift** as you draw to create a vertical or horizontal line.

Arrow

Drag over the image to create an arrow. Press **Shift** as you draw to create a vertical or horizontal arrow.

Polygon

Click to set the corner points of a polygon, then double-click to connect the start and end points to complete the polygon. To fill your shape with color, ensure that the Fill checkbox is checked.

Curve

Drag over the image then release. Next, move your mouse to create the curve and click to set.

Brush

Drag over the image to draw a free-flowing line. Left-click with your mouse to draw with the foreground color, and right-click to draw with the background color.

Use the Opacity slider to adjust the amount of Opacity that is applied to the canvas.



Use the **mouse wheel** to adjust nib width or use the **Size** slider at



the top of the panel.



You can undo and redo each brush stroke individually using the Undo and Redo buttons at the bottom of the Filter Menu.

Fill



Select the **Fill** button, and click on a pixel to shade every pixel of that same color value with your selected color. Your selected color is defined in the color box, as described below. Use the **Threshold** slider to adjust the number of pixels to be included or excluded. The Threshold slider sets how similar a pixel needs to be to the one you clicked in order to be included in the selection. Check the **Connected** checkbox in the Context Bar to fill all of the connected pixels of the same color.

Gradient



Use the Gradient tool to draw gradients across your image, or use the radial option to draw a gradient around an area. Select the Gradient tool, then configure your color, opacity and blend mode using the Context bar. For a radial gradient, select the Radial Gradient button in the Context bar. Then draw your gradient by dragging across the image. To discard your gradient, press the **Discard** button in the Context bar. Rearrange your gradient as desired, then press the **Commit** button in the Context bar. You can undo your commit by pressing **Ctrl + Z** or selecting **Edit | Undo**.

Eye Dropper



Use the Eye Dropper tool to select colors from your images. Click a color in the image, which will appear in the color boxes at the top right of the panel. You can then apply this color using the drawing tools, such as the Brush tool.

You can select the background color (bottom of the color boxes) by right-clicking on your image.

You can select a color from outside of the application by left-clicking on your image and dragging your cursor to the color outside of the application. When you release your mouse button, the color will be selected and shown in the color boxes at the top right of the panel.

Eye Dropper also displays the luminance value of the highlighted pixel.

2. Select from one or more of the following options (**Note:** options vary depending on the tool selected):

Color




Select a color by clicking the color boxes at the top right of the panel to open the Foreground or Background [Color dialog](#), which displays a dialog of swatches to choose from. If you are drawing a solid shape, such as a rectangle, the top (foreground) color box defines the color for the outline of the shape. The bottom (background) color box defines the color that fills the center of the shape. If you want your shape to be a solid color, set both color boxes to match.



You can reset to black and white by pressing the reset button directly next to the color boxes.

Nib Width



Drag the **Nib Width** slider to set the diameter of the brush measured in pixels. You can also adjust the nib width with the mouse wheel or by right-clicking on the image to reveal the Nib Width sliders.

Feathering

Select the **Nib Width** button to reveal the Feathering slider. Drag the **Feathering** slider to set the blurring radius of the brush. You can also right-click on the image to reveal the Nib Width and Feathering slider. Or, you can also hold down **Shift** while using the mouse wheel to adjust the feather radius, represented by the dotted circle.

Spacing

Drag the **Spacing** slider to set how far apart each brush segment will be. This slider specifies the percentage of the size of the nib width, which determines how smooth or choppy the strokes will appear.

Use Auto Spacing: check the **Use Auto Spacing** checkbox to allow ACDSee to choose a spacing percentage based on the nib width and feathering settings, which will create a smooth-looking stroke.

Fill

Check the **Fill** checkbox to fill the shapes you draw with the selected color.

Opacity

Drag the **Opacity** slider to specify the transparency of the brush strokes.

Blending

Select an option from the Blending drop-down menu to affect how your brush

strokes blend with your image as you draw.

3. Drag over the image to draw.



You can right-click a slider to reset to the default value.

Drawing Straight Lines:

Hold the **Shift** key while using any brush to draw horizontal or vertical lines. For example, holding **Shift**, then clicking and dragging horizontally will lock the cursor into horizontal only so long as shift is being held. Release **Shift** to return to free hand brushing. You can even release **Shift** to return to free hand brushing, then press it again while still drawing the same line to unlock and re-lock the brush at will.

Drawing Diagonal Lines:

Using any brush, you can create straight diagonal lines by placing two points on the image. Place the cursor where you want the line to begin, press and hold **Shift**, then **Left-Click** on the image to create a point. Let go of **Shift**, and move the brush to where the line will end, press and hold **Shift**, then **Left-Click** again to create a second point. A straight line will fill in between these two points.

Adding Text to an Image

You can use the Add Text tool in Edit mode to add formatted text to a photo, or add talk and thought bubbles to create a comic-book effect. You can also adjust the opacity of the text to create a watermark effect, which is useful for putting copyright information onto your photos.



You can save your settings as a preset for future use.

To Add Text to an Image:

1. In Edit mode, in the Add group, select **Text**.



You can also access the Text tool from the Filter drop-down menu or Filter toolbar.

2. Type the text you want to add in the **Text** field.
3. In the Font area, specify the font you want to use, the formatting options, such as italics or justification, and the color of the text. Drag the **Size** slider to specify a point size, and then drag the **Opacity** slider to specify the transparency of the text.
4. Click and drag the text marquee to reposition it anywhere on your image, or drag the marquee's handles to resize it.
5. Select an option from the Blend Mode drop-down list to specify how you want the text to blend into the underlying image.

6. Do one of the following:

- Check the **Bubble Text** checkbox, and set the Bubble Text settings as explained in the table below. Note that other text effects cannot be applied to bubble text.
- Check one or more of the **Effects**, **Drop Shadow**, and **Bevel** checkboxes to customize your text. Click the **Settings** button to adjust the settings for each of these options as explained in the table below.

7. Do one of the following:

- Click **Apply** to add the text to your image, and keep the Text tool open so you can add more text. The Text tool creates a new, empty marquee, and you can return to step 3 in the list above.
- Click **Done** to add the text to your image, and leave the tool. If you still have an empty marquee open, it will be discarded.
- Click **Cancel** to discard your changes and leave the tool.

Add Text Options

Bubble Text Settings

Talk	Encloses your text in a comic-book text bubble with a pointed stem.
Thought	Encloses your text in a comic-book text bubble with a dotted stem.
Stem Angle	Specifies the direction of the text bubble stem. Drag the arrow to adjust the angle.
Thickness	Specifies the thickness of the text bubble border.
Length	Specifies the length of the text bubble stem.
Fill	Specifies the background color of the text bubble. Click the arrow to select a color.
Border	Specifies the color of the text bubble border. Click the arrow to select a color.

Effect Settings

Effect	Specifies the effect you want to apply to your text. Each effect has different options that control its appearance. Drag the sliders to adjust the appearance of the text.
---------------	--

Drop Shadow Settings

Distance	<p>Specifies the distance between the drop shadow and the text. The higher the value, the farther the shadow and the higher the text appears.</p> <p>If a drop shadow is cut off, or has a noticeably sharp edge, you may need to increase the size of the text rectangle.</p>
Blur	Specifies the amount of blur applied to the drop shadow. Sharp shadows tend to seem less realistic than those with a slight blur.
Opacity	Specifies the darkness of the drop shadow where it falls on the image.
Angle	Specifies the direction of the imaginary light source that creates the drop shadow. Drag the arrow to adjust the angle — note that this also adjusts the shading of the text bevel.

Bevel Settings

Bevel	Specifies how much of each letter's edge is bevelled. Higher values give the text a more rounded, smoother look.
Strength	Specifies the difference between the highest and lowest points on the text. Higher values heighten the difference between the flat portions of the text and the bevelled edges.

Elevation	Specifies the height of the imaginary light source that creates the bevel's shadowed effect. Lower values produce longer shadows on the text, while a higher value produces a more direct lighting effect and shorter shadows.
Angle	Specifies the direction of the imaginary light source that creates the bevel effect. Drag the arrow to adjust the angle — note that this also adjusts the angle of the drop shadow.



You can right-click a slider to reset to the default value.

Adding a Watermark to an Image

You can use the Watermark tool to add a watermark to a photo. You can move the watermark to any position on the photo. You can also change the opacity of the watermark and blend the watermark into the image. You can add new watermarks and delete watermarks from the list that you no longer use.



You can [save your settings as a preset](#) for future use.



You will need to create a watermark image before you can add the watermark to your photos.

To Add a Watermark to an Image:

1. In Edit mode, in the Add group, select **Watermark**. A default watermark displays in the bottom right of the photo by default.



You can also access the Watermark tool from the Filter drop-down menu or Filter toolbar.

2. Choose a watermark from the drop-down list, or add a new watermark by using the + button.
3. Click and drag the watermark to reposition it anywhere on your image, or choose an Anchor Point from the Positioning settings. Ruler guidelines will appear as you move the watermark around the image to show you pixel distances from the edge. You can also change this pixel distance in the Positioning setting.
4. Drag the marquee handles to resize the watermark image.
5. Select **Maintain aspect ratio when resizing** if you want to resize the watermark image without distorting it.
6. Select **Apply Alpha Channel** to apply the alpha channel if it is present in the watermark.
(Only TIFF, PNG, and ICO watermark files can have an alpha channel.)
7. Select **Apply Transparency** to make a color in the watermark transparent.

The default color is black. You can choose a different color by clicking on the color box. In the Standard tab, you can choose a color, or select a color using the color picker. In the Custom tab, you can enter HSB values (Hue, Saturation, and Brightness), Red Green Blue values, or a hex color code. The color selected will be made transparent in the watermark image itself.

8. Select an option from the **Blending Mode** drop-down list to specify how you want the watermark to blend into the underlying image.
9. Drag the **Opacity** slider to specify the transparency of the watermark.
10. Do one of the following:
 - Click **Apply** to add the watermark to your image, and keep the Watermark tool open.
 - Click **Done** to add the watermark to your image, and leave the tool.
 - Click **Cancel** to discard your changes and leave the tool.



You can right-click a slider to reset to the default value.



Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

To Remove a Watermark From the List:

1. Choose the watermark in the drop-down list.
2. Press the minus symbol -.
3. Your watermark is removed.

Adding Borders

You can use the Borders tool to add one or more borders and edge effects to your images. You can set the size of each side of the border, change the color and texture of the border or pick up a color from within the image by clicking on that color in the image.

There are libraries of edges and textures to get you started, but you can save your own textures or edges to the ACDSee folder so that they appear in the library for you to use.

You can also use Edge blur to soften the edges or blend the image into the background texture. You can also add a third dimension to your images using the Drop Shadow and Raised edge effects.

Using combinations of multiple borders and edge effects can add to the mood and atmosphere of a photo, emphasize contrast, and enhance color.



You can [save your settings as a preset](#) for future use.

To Add a Border to an Image:

1. In Edit mode, in the Add group, select **Borders**.



You can also access the Borders tool from the Filter drop-down menu or Filter toolbar.

2. Create the border by selecting its size, color, texture, edge, or edge effects as described in the Borders options below.
3. Do one of the following:
 - Click **Done** to apply your changes and close the Border tool.
 - Click **Cancel** to discard all changes and close the tool.
4. To add another border, restart the border tool and repeat these steps.



Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

Border Options

Eyedropper



Picks up the color beneath the cursor when you click on the image. The border changes to the clicked color, which also appears in the Color box on the Borders pane so that you can adjust it if you open the Color dialog box.



The eyedropper is not available when you are using a texture.

Border

Size

Sets the size of all the sides of the border simultaneously. Drag the slider left and right to adjust the width of the border. You can also type in a different number or use the up and down arrows to change the size of the border.

The text below the Size field shows the final size of your image with the border added. The final size changes dynamically as you adjust the size of the border.



Advanced size controls

Opens a fly-out menu of advanced size controls. Use the sliders, up and down arrow keys, or type in a number to set the size of each side of the border individually. For example, you can set the bottom border to be larger to include a space for copyright information. Click on the arrow beside the Size slider to open the advanced size controls menu.



Color box


Activates when you select the **Color** radio button.

Do any of the following:

- Click on a color in the image to make the border that color. The clicked color appears in the Color

box.

- Click on the color in the middle of the Color box to open the Colors dialog, where you can adjust the color in multiple ways.
- Click the down-arrow beside the box and hover over the quick-color box until you find a color you like. When you click inside the quick color box, the picked color appears in the Color box and the border changes to the selected color.



Texture box

Activates when you select the **Texture** radio button.

Do any of the following:

- Click the side arrow to open the texture library and view thumbnails of textures to select.
- Click the forward and back arrows to browse through the textures one at a time, without opening the library.

Edge

Straight

Sets the edge of the border to be a straight line.

Irregular

Activates when you select the **Irregular** radio button.

Do any of the following:

- Click the side arrow beside the edge box to open the edge library and view thumbnails of edges to



select.

- Click the forward and back arrows to browse through the edges one at a time, without opening the library.

Edge blur

Blurs the edges of the edge of the image into the border. Drag the slider to the right to increase the blur, or to the left to decrease the blur.

Edge effects

Drop shadow

Adds a drop shadow to the image that appears to lift it off the page. The drop shadow appears behind the image, between it and the border. You can adjust the depth of the blur on the edge of the shadow, and the transparency of the shadow, which affects how much of the border shows through the shadow. You can also change the direction of the imaginary source of light by dragging the glow on the Light Source ball.

- **Blur:** adjusts the blur on the edge of the shadow when you drag the slider.
- **Opacity:** adjusts the transparency of the drop shadow when you drag the slider.

Raised

Adds a raised edge to the image that appears to raise it above the border, giving it a 3D look. The raised effect is applied to the image, between it and the border. You can change the direction of the imaginary source of light of the raised edge by dragging the glow

on the Light Source ball. You can also adjust the size, strength, and color of the raised edge in the following ways:

- **Size:** drag the slider to the right to increase the size of the raised edge so that it appears higher. The greater the size the more rounded the effect.
- **Strength:** drag the slider to the right to increase the 3D effect of the raised edge.
- **Colored:** select this option to apply the border color to the raised edge.

Light Source

Activates when you check either the Drop shadow or Raised checkboxes. Click and drag the glow on the ball to reposition the imaginary light source for the 3D effect of the Drop shadow or Raised edge effects.



You can right-click a slider to reset to the default value.

Adding Your Own Textures or Edges

It is possible to add custom textures and edges to the libraries in the Borders tool. If you make your own edges or textures, or own a collection from the Internet, you can add them to the texture and edge libraries. You can also delete existing files from the libraries to make room for others.

The textures or edges have to be in the following file formats with these extensions:

- BMP
- EMF
- GIF
- JPG
- GIF

- PNG
- TIF

Textures

As the textures are tiled, it is important to use an image that can be seamlessly repeated. The files are used at their full resolution, not scaled up or down. For example, if your texture image is 100 x 100 pixels and you are creating a bordered image that is 1000 x 1000 pixels, then your texture file will be tiled 10 times. If you use a texture file that is 1000 x 1000 pixels, then there would just be the one texture tile for the whole border.

To Add Your Own Textures to the Texture Library:

1. In ACDSee, close the Borders tool if it is open.
2. Copy and paste your texture files into this folder:
C:\Program Files\Common Files\ACD Systems\borders\textures
3. In Manage mode, select the image you want to use and then click **Tools | Edit**.
4. In the Add group, click **Borders**.
5. Select the Texture radio button and then click the arrow on the right side of the texture box to open the texture library.

Thumbnails of the textures display for you to select.

Edges

Edge files are grayscale images that are resized to fit the image. The image file shows through any areas in the edge file that are white, and does not show through any black areas. Pixels that are tones of gray in the edge file show through with relative opacity depending on how close the pixels are to black or white (in other words, the darker the gray pixel, the less it shows through).

To Add Your Own Edges to the Edges Library:

1. In ACDSee, close the Borders tool if it is open.
2. Copy and paste your edge files into this folder:
C:\Program Files\Common Files\ACD Systems\borders\edges
3. In Manage mode, select the image you want to use and then click **Tools | Edit**.
4. In the Add group, click **Borders**.
5. Select the **Irregular** radio button and then click the arrow on the right side of the edge box to open the edge library.

Thumbnails of the edges display for you to select.



If you open an image with borders already applied, another border will be applied to the image.

Adding a Vignette

You can use the Vignette effect to add a frame around a subject, such as a person or a bouquet of flowers. You can change the focal point in the portrait. You can also control the appearance of the border.



You can [save your settings as a preset](#) for future use.

To Apply a Vignette Effect:

1. In **Edit** mode, in the Add group, select **Vignette**.



You can also access the Vignette tool from the Filter drop-down menu or Filter toolbar.

2. Set the options as described below.
3. Do one of the following:
 - Click **Done** to apply your changes and close the tab.
 - Click **Cancel** to discard all changes and close the tab.



Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

Vignette Options

Horizontal	Specifies the focal point of the portrait on the horizontal axis. A value of 500 places the center in the middle of the photo.
Vertical	Specifies the focal point of the portrait on the vertical axis. A value of 500 places the center in the middle of the photo.
Clear zone	Specifies the size of the clear area around the focal point in the portrait. Drag the slider to the left to reduce the size of the clear area. Drag the slider to the right to increase the size of the clear area.
Transition zone	Specifies the width of the transition area between the clear zone and the frame. Drag the slider to the left to narrow the transition area. Drag the slider to the right to widen the transition area.
Stretch	Stretches the vignette horizontally to make the shape elliptical rather than round.
Shape	Specifies the shape of the frame: <ul style="list-style-type: none"> • Round: select Round if you want the frame to be round. • Rectangular: select Rectangular if you want the frame to be square.
Show outline	Select Show outline if you want to display an outline that shows the outside edge of the clear zone and the inside edge of the frame.
Frame	Applies the following special effects to the vignette frame area around the focal point: <ul style="list-style-type: none"> • Color: changes the color of the frame area to the color you select in the color picker. • Saturation: removes color from the people or objects in the vignette frame so they are gray scale. • Blur: blurs the vignette frame area. • Clouds: applies a Clouds effect to the frame area. • Edges: applies an Edges effect by tracing the lines and details of people or objects with neon colors. • Radial Waves: creates the appearance of waves radiating from the focal point into the frame area. • Radial Blur: creates a Radial Blur that rotates and stretches the frame area. • Zoom Blur: applies a Zoom Blur to the frame area. • Crayon Edges: applies the Crayon Edges effect by tracing the lines

and details around people or objects with crayon.

- **Dauber:** creates the impression that the people or objects around the focal point were painted with a brush.
- **Pixelate:** applies a pixel effect to the frame.
- **Old:** applies an aging effect to the frame to make it look like an old photo.
- **Glowing Edges:** applies glowing edges to all the strong lines in the frame area.
- **Ripple:** adds ripples to the frame so that it looks like liquid ripples moving outwards from the focal area.

Frame settings

The settings that display below the Frame drop-down list change depending on the frame you select. For example, if you select **Color** in the **Frame** drop-down list, a color picker displays so that you can select the color for the vignette. Similarly, if you select **Blur** in the **Frame** drop-down list, a slider appears that you can use to change the amount of blur surrounding the photo. For some choices, like Edges, there are no settings to apply.



You can right-click a slider to reset to the default value.

Adding a Tilt-Shift Effect

You can use the Tilt-Shift effect to create emphasis on specific subjects in your photos, or make your photos look like miniature landscapes.

To Use the Tilt-Shift Effect:

1. In Edit mode, in the **Add** group, select **Tilt-Shift**.



You can also access the Tilt-Shift tool from the Filter drop-down menu or Filter toolbar.

2. On the Tilt-Shift panel, set the options as described below.
3. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Tilt-Shift Options

Use the guides on the image to place the effect. The inside boxes represent the points where the focus is transitioning to blur. Complete blur occurs at the outside boxes. Move the boxes to define where the effect will begin or end. Hold down the **Shift** key while positioning the effect to lock to the nearest 45° angle, for straightness.

Blurring

Select the type of blur you want from the Blur drop-down menu.







- Lens Blur
- Gaussian Blur

See [Blur Types](#) for more information.

Amount	Specifies the amount of blur applied.
Bokeh Frequency	Specifies how often the bokeh shapes occur.
Bokeh Brightness	Specifies how bright the bokeh shapes appear.
Bokeh Sides	Defines the number of sides the bokeh shape will have.

Saturation

Drag the slider to the right to intensify the effect.

-  You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.
-  You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.
-  You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Adding a Grain Effect

You can use the Grain effect to give your images a stylized look, like old film grain. The Grain tool can also be used in combination with other effects to achieve a general vintage look.

-  You can [save your settings as a preset](#) for future use.

To Apply a Grain Effect:

1. In Edit mode, in the Add group, select **Grain**.

-  You can also access the Grain tool from the Filter drop-down menu or Filter toolbar.

2. Set the options as described below.
3. Do one of the following:
 - Click **Done** to apply your changes and close the tab.
 - Click **Cancel** to discard all changes and close the tab.

Grain Options

Amount	Specifies the strength of the grain.
Smoothing	Specifies the smoothness of the grain.
Size	Specifies the size of the grain.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

About Special Effect Filters

You can use filters to add unique effects to your images. ACDSee Home includes more than 40 special effect filters, such as Crosshatch, Pencil Drawing, and Solarize.

To Access the Special Effects Filters:

In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

For more information about each effect, click the **Help** button to view a Help file page specific to that effect.

Applying a Bathroom Window Effect

The Bathroom Window effect divides your images into bars, transforming them so they resemble the view through privacy glass often found in bathrooms. You can select or change the Bathroom Window options to apply this effect to your image.

 You can [save your settings as a preset](#) for future use.

To Apply a Bathroom Window Effect:

1. In Edit mode, in the Add group, select **Special Effect**.


 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Bathroom Window**.
3. Drag the **Bar width** slider to set the thickness of the bars. Thinner bars result in a more distorted image.
4. In the Bar direction area, select one of the following to specify the orientation of the bars in your image:

- **Vertical**
- **Horizontal**

5. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Blinds Effect

Use the Blinds effect to divide your image into bars that look like venetian or vertical window blinds. You can customize the characteristics of the blinds you would like added to your image.

 You can [save your settings as a preset](#) for future use.

To Apply a Blinds Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Blinds**.
3. On the Blinds panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Blinds Options

Width	Specifies the width of the blinds. Type a number from 1 to 1000 or drag the slider to adjust the width of each blind. As the value increases, the width of the blind also increases.
Opacity	Specifies the opacity of the blinds. Type a number from 1 to 99 or drag the slider to adjust the opacity of the blinds. The higher the opacity, the more the image is obscured.
Angle	Specifies the angle of the blinds. Type a number from 1 to 360 or drag the arrow to adjust the angle.
Blind color	Specifies the color of the blinds.



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.

Applying a Blue Steel Effect

You can use the Blue Steel effect to give your images a stylish blue tint.

To Apply the Blue Steel Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Blue Steel**.
3. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.

Applying a Bob Ross Effect

You can use the Bob Ross effect to give your images a painted look.



You can save your settings as a preset for future use.

To Give Your Photos a Bob Ross Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Bob Ross**.
3. On the Bob Ross panel, set the options as described in the table below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Bob Ross Options

Brush size	Drag the Brush size slider to specify the width of the brush strokes in the effect. The higher value, the wider the brush stroke.
Coverage	Drag the Coverage slider to specify the amount or density of paint on the "canvas" of your photo.
Paint thickness	Drag the Paint thickness slider to specify how three dimensional the paint appears.
Colorfulness	Drag the Colorfulness slider to specify the amount of color in your image.
Background color	
Image	Check the Image checkbox to use the color in the image as the background color behind the brush strokes added to the photo. To use a different color for the background, uncheck the Image checkbox and select a new color from the color drop-down menu.
Randomize	Indicates the random placement of the paint daubs. When you apply the Bob Ross effect to an image, ACDSee places the daubs randomly. This makes the paint daubs different every time you apply the filter. To generate a new random placement of the paint daubs, click Randomize.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Bulge Effect

Use the Bulge effect to stretch or shrink areas of your images horizontally and vertically. You can customize the strength, radius and position of the distortion.



You can [save your settings as a preset](#) for future use.

To Apply a Bulge Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Bulge**.
3. On the Bulge panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Bulge and Shrink Options

Horizontal position	Specifies the center of the distortion along the horizontal axis. A lower value moves the distortion towards the left side of the image, while a higher value moves it towards the right side of the image.
Vertical position	Specifies the center of the distortion along the vertical axis. A lower value moves the distortion towards the bottom of the image, while a higher value moves it towards the top of the image.
Radius	Specifies the radius of the distorted area. A lower value decreases the radius of the distortion, while a higher value increases the radius of the distortion.
Strength	Specifies the strength of the distortion. A negative value shrinks the center of the distortion, while a higher value bulges the distortion.
Background color	Specifies the background color for the filtered image. Check the Image checkbox to use the original image color, or click the color picker to select a different color.
Bulge direction	Specifies the direction of the distortion. Select one or both of the following options: <ul style="list-style-type: none"> • Horizontal: moves the distortion horizontally. • Vertical: moves the distortion vertically.



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Cartoon Effect

You can use the Cartoon Effect to give your images a sketched appearance.



You can [save your settings as a preset](#) for future use.

To Apply a Cartoon Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Cartoon**.
3. On the Cartoon panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Cartoon Options

Shading strength	Specifies the strength of the shading in the image. The higher the setting, the more intense the shading that is applied to the image.	
Shading radius	Specifies how spread out the shading is.	
Shading threshold	Specifies how sharp an edge must be in the image before shading is applied. If you specify a higher value, more edges in the photo will be shaded.	
Smoothness	Controls how smooth the transitions between similar colors are.	
Outline detail	Specifies how much the details are outlined in black.	
Outline strength	Specifies how strong the black outlines are applied.	
Artifact Suppression	Remove small details	Prevents small details from being outlined in black, allowing the image to appear more cartoon-like.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Childhood Effect

You can use the Childhood effect to give your images a dreamy, nostalgic look.

To Apply the Childhood Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Childhood**.

3. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Collage Effect

You can use the Collage effect to creatively break up a photo into a number of photos.

 You can [save your settings as a preset](#) for future use.

To Use the Collage Effect:

1. In Edit mode, in the Add group, select **Special Effect**.

 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Collage**.

3. Drag the sliders to set the Number and Size of the photos.

4. Select a background color by clicking the drop-down arrow to display gradients of colors, or click the color box to display a dialog of swatches to choose from.

5. If you would like to reshuffle the photos, click **Randomize**.

6. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

7. Click **Exit** to leave Special Effects, and return to the Filter menu.

 You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Colored Edges Effect

You can use the Colored Edges effect to trace the lines and details of people or objects in your images.



You can [save your settings as a preset](#) for future use.

To Apply a Colored Edges Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.


2. Click **Colored Edges**.
3. On the Colored Edges panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Colored Edges Options

Intensity	Specifies the amount of color added to the edges within the image. The higher the setting, the thicker the color that is applied to the image.
Edge color	Specifies the color of the edges.
Edge detection	Specifies the edge detection algorithm. The algorithm controls the formula used to detect the edges and the direction of the edge indicators.
Blurring	Blurs the edges in the image. Check the Use blurring checkbox, and then choose a blur setting to determine how much blur is applied.



You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Contours Effect

You can use the Contours effect to draw contour lines on your image to create a cartoon effect. Select or change the rounding, line frequency, color and strength setting to apply to your image.

 You can [save your settings as a preset](#) for future use.

To Apply a Contours Effect:

1. In Edit mode, in the Add group, select **Special Effect**.

 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Contours**.
3. On the Contours panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.


Contours Options

Rounding	Specifies the amount of curve in the contour lines. The higher the value, the rounder the lines.
Line frequency	Specifies the amount of space between the contour lines. The higher the value, the closer the lines move together.
Strength	Specifies the strength of the line. The higher the value, the darker the line.
Line color	Specifies the color of the contour lines.

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Crayon Drawing Effect

You can use the Crayon Drawing effect to give your photos the appearance of a crayon drawing.

To Use the Crayon Drawing Effect:

1. In Edit mode, in the Add group, select **Special Effect**.

 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Crayon Drawing**.

3. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Crosshatch Effect

You can use the Crosshatch effect to add crosshatching to an image.

To Use the Crosshatch Effect:

1. In Edit mode, in the Add group, select **Special Effect**.

 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Crosshatch**.
3. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Dauber Effect

You can use the Dauber effect to make your images look like they were painted with a paint dauber. Select or change the settings of the effect you want applied to your image, such as intensity, frequency and more.



You can [save your settings as a preset](#) for future use.

To Use the Dauber Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Dauber**.
3. On the Dauber panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Dauber Options

Intensity	Specifies the amount of color applied with each daub.
Frequency	Specifies the number of daubs added to the image.
Background color	Specifies the background color of the filtered image. Check the Image checkbox to use the original image colors or click the color picker to select a different color.
Randomize	Indicates the random placement of the paint daubs. When you apply the Dauber effect to an image, ACDSee Home places the daubs randomly. This makes the paint daubs different every time you apply the filter. You can define a specific random seed to generate identical daubs. To generate a new random seed, click Randomize .



You can right-click a slider to reset to the default value.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Dramatic Effect

You can use the Dramatic effect to make your images look dramatic and moody by drastically changing the contrast in specific areas.



You can [save your settings as a preset](#) for future use.

To Apply a Dramatic Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Dramatic**.
3. On the Dramatic panel, set the options as described below.

4. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

Dramatic Options

Strength	Specifies the strength of the contrast being applied.
Spread	Specifies how far the effect spreads over the details in the photo.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying an Edge Detect Effect

You can use the Edge Detect effect to create a highlighted outline of your image. After creating a black image, the effect uses colored lines to outline the detail of an image where significant color differences exist. Greater differences between colors in the original image produce brighter outline colors. (The Sobel effect is similar to the Edge Detect effect, but produces sharper and brighter outlines.)

To Use the Edge Detect Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Edge Detect**.

3. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying an Emboss Effect

You can use the Emboss effect to add a grayscale relief to an image.



You can [save your settings as a preset](#) for future use.

To Emboss an Image:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Emboss**.
3. On the Emboss panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Emboss Options

Elevation	Specifies the light source's elevation on the image. Lower values produce more shadows and a darker image. Higher values produce fewer shadows and a lighter image.
Weight	Specifies the amount of relief added to the image. Higher values increase the relief depth.
Azimuth	Specifies the angle of shadows that extend from the edges of image details. A value of 0 adds shadows to the left side, while a value of 180 adds shadows to the right side.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Furry Edges Effect

You can use the Furry Edges effect to add fur and bristles to the lines and details of people or objects in your image.



You can [save your settings as a preset](#) for future use.

To Use the Furry Edges Effect:

1. In Edit mode, in the Add group, select **Special Effect**.






You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Furry Edges**.
3. On the Furry Edges panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.


Furry Edges Options

Frequency	Specifies how much fur is added to the image. The higher the setting, the more dense the fur that is applied to the image.
Threshold	Specifies how sharp an edge must be before fur is applied to it. As the value decreases, the area of the image that fur is added to increases.
Fur length	Specifies the length of each strand of fur. As the value increases, the length of each fur strand also increases.
Variance	Specifies how much of the fur grows in the direction indicated by the Hair direction setting. The higher the value, the more random the fur direction will be.
Hair direction	Specifies the general direction in which fur appears to grow.
Edge detection	Specifies the edge detection algorithm. The algorithm controls the formula used to detect the edges and the direction of the edge indicators.
Background color	Specifies the background color of the filtered image. Check the Image checkbox to use the original image colors, or click the color picker to select a different color.
Fur color	Specifies the color of the fur. Check the Image checkbox to use the original image colors, or click the color picker to select a different color.
Randomize	<p>Indicates the random placement of the fur strands.</p> <p>When you apply the Furry Edges effect to an image, ACDSee Home places the fur randomly. This makes the fur strands different every time you apply the filter. You can define a specific random seed to generate identical fur patterns.</p> <p>To generate a new random seed, click Randomize.</p>

 You can right-click a slider to reset to the default value.


 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Glowing Edges Effect

You can use the Glowing Edges effect to add color to the lines and details of people or objects in your images. The colored lines and details appear to glow.

 You can [save your settings as a preset](#) for future use.

To Apply a Glowing Edges Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Glowing Edges**.
3. On the Glowing Edges panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.


Glowing Edges Options

Intensity	Specifies the amount of color added to the edges within the image. The higher the setting, the more intense the color that is applied to the image.
Color	Specifies the color of the edges.

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Granite Effect

You can use the Granite effect to give your images the appearance of being painted on a rock wall.

 You can [save your settings as a preset](#) for future use.

To Use the Granite Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Granite**.
3. On the Granite panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Granite Options**Light Angle**

Specifies the direction from which an imaginary light source is shining on the image. Drag the arrow to adjust the angle. Different light angles will change the highlights and shadows in the peaks and valleys on the rock.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.

Applying a Lomo Effect

Simulate the retro-effects of a lomo camera. Photos taken with a lomo camera are high contrast, with a golden hue and a noticeable vignette.



You can save your settings as a preset for future use.

To Use the Lomo Effect:

1. In Edit mode, in the Add group, select **Special Effect**.




You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Lomo**.
3. Drag the Color Distortion slider to the right to increase the color distortion.


4. Drag the Vignette Strength slider to the right to increase the vignette strength.
5. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

6. Click **Exit** to leave Special Effects, and return to the Filter menu.

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Mirror Effect

You can use the Mirror effect to reflect an image along the horizontal or vertical axis. Select or change the Mirror options to apply mirroring to your image, including mirror axis and direction.

 You can [save your settings as a preset](#) for future use.

To Apply a Mirror Effect:


1. In Edit mode, in the Add group, select **Special Effect**.


 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Mirror**.
3. On the Mirror panel, in the Mirror direction area, select one of the following options to indicate which direction you want to mirror the image:
 - **Horizontal**
 - **Vertical**
4. Drag the **Mirror axis** slider to adjust the position of the mirror. A value of 500 places the mirror in the center of the image.

5. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

 You can right-click a slider to reset to the default value.

 You can use the Edit Brush  to paint this effect onto specific areas of your image.

 You can use the Gradient tool  to transition this effect across specific areas of your image.

 You can use the Radial Gradient tool  to apply effects around, or directly to, a center point.

Applying a Negative Effect

You can use the Negative effect to create a negative of your image. You can also apply the Negative filter to a negative scanned from a roll of film to produce a positive image.

To Create an Image Negative:



1. In Edit mode, in the Add group, select **Special Effect**.

 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Negative**.

3. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

 You can use the Edit Brush  to paint this effect onto specific areas of your image.

 You can use the Gradient tool  to transition this effect across specific areas of your image.

 You can use the Radial Gradient tool  to apply effects around, or directly to, a center point.

Applying an Oil Paint Effect

You can use the Oil Paint effect to give your images a painted appearance.


 You can [save your settings as a preset](#) for future use.

To Create an Oil Painting from a Photo:

1. In Edit mode, in the Add group, select **Special Effect**.

 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Oil Paint**.
3. On the Oil Paint panel, drag the **Brush width** slider to specify the width of the brush strokes in the effect. The higher the value, the wider the brush stroke.
4. Drag the **Variance** slider to specify the color variance in each brush stroke. Higher values increase the number of colors used in each stroke.
5. Drag the **Vibrance** slider to adjust the intensity of the colors in the image.
6. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying an Old Effect

You can use the Old effect to give your images an antique look. (The Old effect is similar to the Sepia effect, but produces a more realistic appearance of age.)

 You can [save your settings as a preset](#) for future use.

To Apply the Old Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Old**.
3. On the Old panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Old Options

Age	Specifies the intensity or degree of the effect. (The numbers do not correspond to how old the photo should appear.)
------------	--



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.

Applying an Orton Effect

Create beautiful impressionistic images with the Orton effect. The Orton effect mimics a darkroom technique created by sandwiching two images together, one of which is slightly out of focus, and both of which are slightly overexposed.



You can [save your settings as a preset](#) for future use.

To Use the Orton Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Orton**.

3. Drag the Blur, Contrast, and Brightness sliders to adjust each effect.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.
5. Click **Exit** to leave Special Effects, and return to the Filter menu.



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.

Applying an Outline Effect

The Outline effect is similar to the Edge Detect effect. You can use the Outline effect to create a highlighted outline of your image. However, with the Outline effect you can control the thickness of the outline, whether an edge is outlined or not, and the color that displays behind the outlined image.



You can [save your settings as a preset](#) for future use.

To Use the Outline Effect:

1. In Edit mode, in the Add group, select **Special Effect**.





You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Outline**.
3. On the Outline panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.



Outline Options

Line width	Specifies the width of the outline in the effect. The higher the value, the wider the outline.
Threshold	Specifies how sharp an edge must be in order to be outlined. If you specify a higher value, more edges in the photo will be outlined.
Background color	Specifies the background color of the filtered image. Click the color picker to select a different color.

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.


 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Pencil Drawing Effect

You can use the Pencil Drawing effect to create a pencil drawing from your images.

To Create a Pencil Drawing from an Image:



1. In Edit mode, in the Add group, select **Special Effect**.

 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Pencil Drawing**.

3. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Pixel Explosion Effect

You can use the Pixel Explosion effect to explode pixels from a center point in your images. Select or change the Pixel Explosion settings, such as intensity and direction, to apply this effect to your image.



You can [save your settings as a preset](#) for future use.

To Use the Pixel Explosion Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Pixel Explosion**.
3. On the Pixel Explosion panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Pixel Explosion Options

Horizontal center	Specifies the center point of the explosion on the horizontal axis. A value of 500 places the explosion at the middle of the image.
Vertical center	Specifies the center point of the explosion on the vertical axis. A value of 500 places the explosion at the middle of the image.
Intensity	Specifies the intensity of the explosion. A higher value creates a larger, more brilliant spread of the pixels in the image.
Explosion direction	<p>Specifies the direction of the explosion. Select one or both of the following:</p> <ul style="list-style-type: none"> • Explode horizontally: explodes the pixels towards the right and left sides of the image. • Explode vertically: explodes the pixels towards the top and bottom of the image.
Randomize	<p>Indicates the random placement of the pixels.</p> <p>When you apply the Pixel Explosion effect to an image, ACDSee Home places the pixels randomly. This makes the pixels different every time you apply the filter. You can define a specific random seed to generate identical pixel patterns.</p> <p>To generate a new random seed, click Randomize.</p>



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Pixelate Effect

A pixel is the smallest piece of a digital image, arranged in rows and columns. When you reduce the resolution of your image, the size of the pixel increases and produces blurring. You can use the Pixelate effect to increase the size of the pixels in your image.



You can [save your settings as a preset](#) for future use.

To Apply a Pixelate Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Pixelate**.
3. On the Pixelate panel, drag the **Width** and **Height** sliders to set the size of the pixels in your image. Check the **Square** checkbox to make the width and height equal.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.

Applying a Posterize Effect

You can use the Posterize effect to reduce the number of brightness levels in your image. Select or change the Posterize options to apply this effect to your image.



You can save your settings as a preset for future use.

To Apply a Posterize Effect:

1. In Edit mode, in the Add group, select **Special Effect**.




You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Posterize**.
3. On the Posterize panel, drag the **Brightness levels** slider to adjust the variance of colors in the image. The lower the value, the fewer colors used in the image.



4. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

 You can right-click a slider to reset to the default value.

 You can use the Edit Brush  to paint this effect onto specific areas of your image.

 You can use the Gradient tool  to transition this effect across specific areas of your image.

 You can use the Radial Gradient tool  to apply effects around, or directly to, a center point.

Applying a Purple Haze Effect

You can use the Purple Haze effect to give your image a hyper-retro, purple tint.

To Apply the Purple Haze Effect:


1. In Edit mode, in the Add group, select **Special Effect**.

 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Purple Haze**.

3. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

 You can right-click a slider to reset to the default value.

 You can use the Edit Brush  to paint this effect onto specific areas of your image.

 You can use the Gradient tool  to transition this effect across specific areas of your image.

 You can use the Radial Gradient tool  to apply effects around, or directly to, a center point.

Applying a Radial Waves Effect

You can use the Radial Waves effect to display waves radiating from a center point in the photo. You can change the center point in the photo and you can also control the appearance of the waves.



You can [save your settings as a preset](#) for future use.

To Apply a Radial Waves Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Radial Waves**.
3. On the Radial waves panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Radial Waves Options

Horizontal position	Specifies the center of the waves on the horizontal axis. A value of 500 places the waves in the middle of the image.
Vertical position	Specifies the center of the waves on the vertical axis. A value of 500 places the waves in the middle of the image.
Amplitude	Specifies the depth and height of each wave.
Wavelength	Specifies the amount of space between waves.
Light strength	Specifies the amount of light contrast between the top and bottom of each wave.
Background color	Specifies the background color of the filtered image. Check the Image checkbox to use the original image colors, or click the color picker to select a different color.
Wave direction	Specifies the direction of the waves. Select one, or both, of the following: <ul style="list-style-type: none"> • Wave horizontally: makes the waves move towards the right and left sides of the image. • Wave vertically: makes the waves move towards the top and bottom of the image.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Rain Effect

You can use the Rain effect to make it look like it was raining when you took a photo. Control the amount, the angle, strength and other characteristics of the rain.



You can [save your settings as a preset](#) for future use.

To Apply Rain to a Photo:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Rain**.
3. On the Rain panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Rain Options

Strength	Specifies the length of the rain drops. Drag the slider to the right to increase the length.
Opacity	Specifies the opacity of the rain drops. Type a number from 0 to 100 or drag the slider to adjust the opacity of the rain drops. The higher the opacity, the more the image is obscured.
Amount	Specifies the number of rain drops.
Angle variance	Specifies the angle of the rain drops. Type a number from 0 to 50 or drag the arrow to adjust the angle.
Strength variance	Specifies how much variety there should be in the length of the rain drops. Drag the slider to the left if you want rain drops to have a similar length. Drag the slider to the right if you want to vary the length of rain drops. If you vary the length of rain drops they look natural.
Background blur	Specifies the amount of blur in the photo. Heavy rain will block your vision. Use this option to blur the photo so the rain effect looks natural.
Angle	Specifies the angle at which the rain drops are falling.
Color	Specifies the color of the rain drops.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Ripple Effect

You can use the Ripple effect to divide your images into concentric circles that resembles what you see when you drop a pebble into water. Select or change the Ripple settings to apply to your image, such as position, strength and more.



You can [save your settings as a preset](#) for future use.

To Apply a Ripple Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Ripple**.
3. On the Ripple panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Ripple Options

Horizontal position	Specifies the center of the ripples on the horizontal axis. A value of 500 places the ripples in the middle of the image.
Vertical position	Specifies the center of the ripples on the vertical axis. A value of 500 places the ripples in the middle of the image.
Amplitude	Specifies the depth and height of each ripple.
Wavelength	Specifies the amount of space between ripples.
Light strength	Specifies the amount of light contrast between the top and bottom of each ripple.
Background color	Specifies the background color of the filtered image. Check the Image checkbox to use the original image colors, or click the color picker to select a different color.
Ripple direction	<p>Specifies the direction of the ripples. Select one or both of the following:</p> <ul style="list-style-type: none"> • Ripple vertically: makes the ripples move towards the top and bottom of the image. • Ripple horizontally: makes the ripples move towards the right and left sides of the image.



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Scattered Tiles Effect

You can use the Scattered Tiles effect to divide your images into rectangular tiles, and scatter and stack the tiles. Select or change the Scattered Tiles options to apply this effect to your image.



You can [save your settings as a preset](#) for future use.

To Apply a Scattered Tiles Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Scattered Tiles**.
3. On the Scattered Tiles panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Scattered Tiles Options

Tile size	Specifies the size of the tiles.
Scatter amount	Specifies how much the tiles will move from their original positions.
Background color	Specifies the color of the background. Click the color picker to select a different color.
Randomize	<p>Indicates the random placement of the tiles.</p> <p>When you apply the Scattered Tiles effect to an image, ACDSee Home places the tiles randomly. This makes the effect different every time you apply the filter. You can define a specific random seed to generate identical tile patterns.</p> <p>To generate a new random seed, click Randomize.</p>





You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Sepia Effect

You can use the Sepia effect to give your images an antique look. (The Old effect is similar to the Sepia effect, but produces a more realistic appearance of age.)

 You can [save your settings as a preset](#) for future use.

To Add a Sepia Tone to an Image:


1. In Edit mode, in the Add group, select **Special Effect**.

 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Sepia**.

3. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Seventies Effect

You can use the Seventies effect to give your images a retro look.

To Apply the Seventies Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Seventies**.
3. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.

Applying a Sheet Metal Effect

You can use the Sheet Metal effect to turn your images into sheet metal impressions.



You can [save your settings as a preset](#) for future use.

To Apply a Sheet Metal Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Sheet Metal**.
3. On the Sheet Metal panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Sheet Metal Options

Rounding	Specifies the amount of curve in the edges of the impressions.
Detail	Specifies the amount of detail in the impression.
Angle	Specifies the angle of the grain in the sheet metal.
Metal color	Specifies the color of the sheet metal.
Direction	<p>Specifies the direction in which the sheet metal was manipulated. Select one of the following:</p> <ul style="list-style-type: none"> • Indented: stamps the metal from the top side of the image. • Pushed out: stamps the metal from underneath the image.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Shift Effect

You can use the Shift effect to divide your images into bars and shift them in random directions.



You can [save your settings as a preset](#) for future use.

To Apply a Shift Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Shift**.
3. On the Shift panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Shift Options

Strength	Specifies the amount of shift between the bars.
Width	Specifies the width of each bar.
Angle	Specifies the angle of the bars.
Background color	Specifies the background color of the filtered image. Check the Image checkbox to use the original image colors, or click the color picker to select a different color.



You can right-click a slider to reset to the default value.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Slant Effect

You can use the Slant effect to make a photo appear slanted. For example, you could use the Slant effect to distort a photo by pushing the top of the photo to the left and the bottom of the photo to the right. Similarly, you could use the slant effect to push the left side of the photo upwards and the right side of the photo downwards.



You can [save your settings as a preset](#) for future use.

To Apply a Slant Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Slant**.
3. On the Slant panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Slant Options

Amount	Specifies the degree of the slant.
Fulcrum	Specifies the center of the slant. Drag the slider to the left to place the center of the slant near the bottom of the photo. Drag the slider to the right to place the center of the slant near the top of the photo.
Background color	Specifies the background color of the filtered image. Click the color picker to select a different color.
Slant Direction	Specifies the angle of the slant: <ul style="list-style-type: none"> • Horizontal: select Horizontal to push the top or bottom of the photo to the left or right. • Vertical: select Vertical to push the left or right side of the photo up or down.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Sobel Effect

You can use the Sobel effect to create a highlighted outline of your image. After creating a black image, the effect uses colored lines to outline the detail of an image where significant color differences exist. Greater differences between colors in the original image produce brighter outline colors. (The Sobel effect is similar to the Edge Detect effect, but produces sharper and brighter outlines.)

To Use the Sobel Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Sobel**.

3. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Solarize Effect

You can use the Solarize effect to simulate the effect of overexposing an image, as though the film was exposed to light before developing. Select or change the Solarize options to apply this effect to your image.



You can [save your settings as a preset](#) for future use.

To Apply a Solarize Effect:

1. In Edit mode, in the Add group, select **Special Effect**.




You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Solarize**.
3. On the Solarize panel, drag the **Threshold** slider to specify the brightness threshold of the image.
4. In the Effect area, specify which pixels you want to adjust by selecting one of the following options:
 - **Solarize**: adjusts pixels located above the specified threshold option. The effect takes any pixels above the threshold and replaces them with their negative value. When you solarize an image, a higher threshold value sets a brighter threshold, and colors need to be brighter to be overexposed.
 - **Lunarize**: adjusts pixels located below the specified threshold option. The effect takes any pixels below the threshold and replaces them with their negative value. When you lunarize an image, a higher threshold value sets a darker threshold, and colors do not have to be as bright to be overexposed.

5. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

 You can right-click a slider to reset to the default value.

 You can use the Edit Brush  to paint this effect onto specific areas of your image.

 You can use the Gradient tool  to transition this effect across specific areas of your image.

 You can use the Radial Gradient tool  to apply effects around, or directly to, a center point.

Applying a Somber Effect

You can use the Somber effect to give your images an austere or sleek look.

To Apply the Somber Effect:


1. In Edit mode, in the Add group, select **Special Effect**.


 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Somber**.

3. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

 You can right-click a slider to reset to the default value.


 You can use the Edit Brush  to paint this effect onto specific areas of your image.

 You can use the Gradient tool  to transition this effect across specific areas of your image.

 You can use the Radial Gradient tool  to apply effects around, or directly to, a center point.

Applying a Stained Glass Effect

You can use the Stained Glass effect to divide your image into fragments of a random size and shape, to give the photo the appearance of a stained glass window. Control the size and position of the fragments using the effect settings.

 You can [save your settings as a preset](#) for future use.

To Apply a Stained Glass Effect:


1. In Edit mode, in the Add group, select **Special Effect**.



 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Stained Glass**.
3. On the Stained Glass panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Stained Glass Options

Fragment size	Specifies the size of the fragments.
Randomize	<p>Indicates the random placement of the fragments.</p> <p>When you apply the Stained Glass effect to an image, ACDSee Home places the fragments randomly. This makes the effect different every time you apply the filter. You can define a specific random seed to generate identical fragment patterns.</p> <p>To generate a new random seed, click Randomize.</p>

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Sunspot Effect

You can use the Sunspot effect to add a bright spot in your images.


 You can [save your settings as a preset](#) for future use.

To Apply a Sunspot Effect:

1. In Edit mode, in the Add group, select **Special Effect**.

 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Sunspot**.
3. On the Sunspot panel, drag the **Horizontal Position** and **Vertical Position** sliders or click the image to set the location of the sunspot.
4. Drag the **Brightness** slider to set the intensity of the sunspot.
5. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

 You can right-click a slider to reset to the default value.

Applying a Swirl Effect

You can use the Swirl effect to rotate and stretch people and objects in your image.

 You can [save your settings as a preset](#) for future use.

To Apply a Swirl Effect:

1. In Edit mode, in the Add group, select **Special Effect**.

 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Swirl**.
3. On the Swirl panel, set the options as described below.

4. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

Swirl Options

Horizontal position	Specifies the center of the swirl on the horizontal axis. A value of 500 places the swirl in the middle of the image.
Vertical position	Specifies the center of the swirl on the vertical axis. A value of 500 places the swirl in the middle of the image.
Radius	Specifies the size of the swirl effect.
Strength	Specifies the strength and direction of the swirl. Higher values create a clockwise swirl, while negative values create a counter-clockwise swirl.
Focus	Specifies the concentration of the swirl. Higher values concentrate the effect on the center of the swirl, while lower values spread the swirl across the image.
Background color	Specifies the background color of the filtered image. Check the Image checkbox to use the original image colors, or click the color picker to select a different color.
Swirl direction	Specifies the direction of the swirl. Select one or both of the following: <ul style="list-style-type: none"> • Swirl horizontally: moves the swirl towards the top and bottom of the image. • Swirl vertically: moves the swirl towards the right and left sides of the image.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.


Applying a Threshold Effect

You can use the Threshold effect to create a black and white image.

 You can [save your settings as a preset](#) for future use.

To Apply the Threshold Effect:


1. In Edit mode, in the Add group, select **Special Effect**.



 You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Threshold**.
3. On the Threshold panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.



Threshold Options

Threshold	This slider determines which pixels become black and which ones become white in the black and white image. Any pixels that are brighter than the selected threshold will become white and any pixels that are darker than the threshold will become black.
------------------	--

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Topography Effect

You can use the Topography effect to change the details of your images into contour lines.

 You can [save your settings as a preset](#) for future use.

To Apply a Topography Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Topography**.
3. On the Topographic Map panel, drag the **Rounding** slider to adjust the amount of curve in the contour lines.
4. Drag the **Number of lines** slider to specify how many contour lines you want to add.
5. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.

Applying a Water Effect

You can use the Water effect to insert an expanse of water below the subject of a photo and to display a reflection of the subject in the water. You can control the position of the water below the subject. For example, you can position the water below a person's chin, or below their waist. You can also control the appearance of ripples in the water and how dark or light the water appears.



You can [save your settings as a preset](#) for future use.

To Apply a Water Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Water**.
3. On the Water panel, set the options as described below.

4. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.

Water Options

Position	Specifies the position of the water below the subject of the photo.
Amplitude	Specifies the height of the ripples in the water. Drag the slider to the left to reduce the height of the ripples and the distortion caused by the ripples. Drag the slider to the right to increase the height of the ripples and the distortion caused by the ripples.
Wavelength	Specifies the distance between ripples. Drag the slider to the left to reduce the distance between ripples and increase the distortion caused by the ripples. Drag the slider to the right to increase the distance between ripples and reduce the distortion caused by the ripples.
Perspective	Changes the size of the waves as they get farther from the subject. Drag the slider to the left to increase the size of the waves farthest from the subject and to increase the illusion of distance.
Lighting	Specifies the amount of light in the water.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Water Drops Effect

You can use the Water Drops effect to display water drops on the surface of the photo. You can control the number and size of water drops, and their position on the photo.



You can [save your settings as a preset](#) for future use.

To Apply Water Drops to a Photo:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Water Drops**.
3. On the Water Drops panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Water Drops Options

Density	Specifies the number of water drops on the photo. Drag the slider to the left to remove water drops. Drag the slider to the right to add water drops.
Radius	Specifies the size of the water drops. Drag the slider to the left to make the water drops smaller. Drag the slider to the right to make the water drops larger.
Height	Specifies the height of the water drops above the photo surface. Drag the slider to the left to reduce the height of the water drops and the distortion caused by the water drops. Drag the slider to the right to increase the height of the water drops and the distortion caused by the water drops.
Randomize	<p>Indicates the random placement of the water drops.</p> <p>When you apply the Water Drops effect to an image, ACDSee Home places the water drops randomly. This makes the effect different every time you apply the filter. You can define a specific random seed to generate identical water drop patterns.</p> <p>To generate a new random seed, click Randomize.</p>



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.

Applying a Waves Effect

You can use the Waves effect to display waves across the photo. You can change the distance between waves. This distance is called wavelength. You can also change the height of the waves, and the angle at which the waves cross the photo.



You can [save your settings as a preset](#) for future use.

To Apply a Waves Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Waves**.
3. On the Waves panel, select or change the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Waves Options

Wavelength	Specifies the distance between waves. Drag the slider to the left to reduce the distance between waves and increase the distortion caused by the waves. Drag the slider to the right to increase the distance between waves and reduce the distortion caused by the waves.
Amplitude	Specifies the height of the waves. Drag the slider to the left to reduce the height of the waves and the distortion caused by the waves. Drag the slider to the right to increase the height of the waves and the distortion caused by the waves.
Angle	Specifies the angle of the waves. Type a number from 1 to 360 or drag the arrow to adjust the angle.
Background color	Specifies the background color. Check the Image checkbox to use the original image colors, or click the color picker to select a different color.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Weave Effect

You can use the Weave effect to give a photo the appearance of being woven into a tapestry or basket. You can control the width of the vertical and horizontal strips, the width of the gap between the strips, and the background color that displays through the gap.



You can [save your settings as a preset](#) for future use.

To Apply a Weave Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Weave**.
3. On the Weave panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Weave Options

Strip width	Specifies the width of the vertical and horizontal strips.
Gap width	Specifies the width of the gap between the strips.
Background color	Specifies the color of the background. Click the color picker to select a different color.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Applying a Wind Effect

You can use the Wind effect to add wind lines that make stationary objects in your image look like they are moving. Select or change the settings to control the effect of the wind added to your image.



You can [save your settings as a preset](#) for future use.

To Apply a Wind Effect:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **Wind**.
3. On the Wind panel, select or change the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

Wind Options

Strength	Determines how strong the wind lines are in the image. The higher the value, the stronger the wind lines.
Threshold	Determines how sharp an edge must be before the filter will apply wind. The higher the value, the sharper the edge needs to be.
Chance of wind	Determines the amount of wind lines to place in the image.
Edge detection	Specifies the edge detection algorithm. The algorithm controls the formula used to detect the edges and the direction of the edge indicators.
Background color	Specifies the background color. Check the Image checkbox to use the original image colors, or click the color picker to select a different color.
Wind color	Specifies the color of the wind lines. Check the Image checkbox to use the original image colors, or click the color picker to select a different color.
Wind angle	Specifies the angle of the wind lines.
Randomize	<p>Indicates the random placement of the wind lines.</p> <p>When you apply the Wind effect to an image, ACDSee Home places the wind lines randomly. This makes the wind lines different every time you apply the filter. You can define a specific random seed to generate identical wind lines.</p> <p>To generate a new random seed, click Randomize.</p>



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Creating a Custom Special Effect Filter (Convolution Effect)

You can use the Convolution filter to create your own special effects and apply them to your image.



You can [save your settings as a preset](#) for future use.

To Create a Custom Effect Filter:

1. In Edit mode, in the Add group, select **Special Effect**.



You can also access the Special Effects menu from the Filter drop-down menu or Filter toolbar.

2. Click **User Defined Convolution**.
3. On the User Defined Convolution panel, set the options as described below.
4. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

User Defined Convolution Options

Convolution Matrix	<p>Specifies the formula to use when altering the image.</p> <p>Type numbers in the matrix fields to change the pixels in the image. Using a mathematical formula, the color value of each pixel in an image is multiplied by the numbers in the matrix to produce an effect.</p>
Division	<p>Specifies the fractional coefficient of the matrix.</p> <p>Type a number into the Division field to use fractional coefficients in the matrix. The product of the convolution matrix is divided by the division factor before being applied to a pixel.</p>
Bias	<p>Specifies the brightness of the image.</p> <p>Type a number into the Bias field to change the brightness of the image. The bias number is added to the RGB values of each pixel. A positive number brightens the image, while a negative number darkens the image.</p>
Clear Matrix	Resets the matrix.
Sample Filters Drop-Down Menu	Loads a sample effect to use as a starting point for creating your own effect.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.




You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.


Rotating an Image

You can rotate an image at preset or custom angles in Edit mode.

 You can [save your settings as a preset](#) for future use.

To Rotate an Image at a Custom Angle:

1. In Edit mode, in the Geometry group, select **Rotate**.

 You can also access the Rotate tool from the Filter drop-down menu or Filter toolbar.

2. Select one or more of the following:
 - Select one of the default orientation options.
 - Drag the **Straightening** slider to the left or right until the image appears straightened.
 - Click the **Horizontal** or **Vertical** button, and use the tools as described below.
 - Select **Crop straightened image** if you want to crop the image after it is straightened.
 - Select **Preserve straightened image** if you do not want to crop the straightened image. Select the color that you would like to display behind the straightened image from the **Fill color** drop-down.
 - Select **Show grid overlay** to display a grid over the image. You may find that the grid helps you straighten the image and understand how the image will be cropped.
3. Do one of the following:
 - Click **Done** to apply your changes and close the tool.
 - Click **Cancel** to discard all changes and close the tool.

 Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

Rotate Icons

Horizontal




Click on the horizontal icon, and then use the cursor to draw a line on the image that you want to set as the horizontal line.

Vertical



Click on the vertical icon, and then use the cursor to draw a line on the image that you want to set as the vertical line.

 You can right-click a slider to reset to the default value.

Flipping an Image

You can flip an image both vertically and horizontally in Edit mode.

 You can [save your settings as a preset](#) for future use.

To Flip an Image:

1. In Edit mode, in the Geometry group, select **Flip**.

 You can also access the Flip tool from the Filter drop-down menu or Filter toolbar.

2. Do one or both of the following:
 - Check the **Horizontal Flip** checkbox.
 - Check the **Vertical Flip** checkbox.
3. Do one of the following:
 - Click **Done** to apply your changes and close the tool.
 - Click **Cancel** to discard all changes and close the tool.

 Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

Cropping an Image

You can use the Crop tool to remove unwanted parts of your images, or to reduce the image canvas to a particular size. You can also enable relative positioning which is useful for creating settings to batch crop a selection of images.

 You can [save your settings as a preset](#) for future use.

 When zooming in, hold down the **Spacebar** to pan the image.

To Crop an Image:

1. In Edit mode, in the Geometry group, select **Crop**.



You can also access the **Crop** tool from the Filter drop-down menu or Filter toolbar.

2. [Resize](#) the crop window, and position it over the area of the image you want to keep.
3. To darken the parts of the image outside the crop window, drag the **Darken outside crop area** slider to the left. Drag the slider to the right to lighten the area outside the crop window.
4. Click **Estimate new file size** to view how big your image file is after cropping.
5. Do one of the following:
 - Click **Done** to crop the image and close the tool.
 - Click **Cancel** to exit the tool without cropping the image.



You can right-click a slider to reset to the default value.

Resizing the Crop Window

You can resize the crop window in three ways:

- Drag the edges of the crop window to the desired size.
- Specify an exact size for the crop window in pixels, inches, centimeters, or millimeters.
- Apply a ratio to constrain the crop window proportions.

To Resize the Crop Window by Dragging:

1. Position your cursor over the edge or corner of the crop window until it changes into a double-pointed arrow.
2. Drag the crop window's border to the desired size.

To Specify an Exact Size for the Crop Window:

1. Type the desired crop window proportions into the **Width** and **Height** spin boxes.
2. In the **Units** drop-down list, select a unit of measurement.
3. Use the **Dots per inch** spin box to specify a resolution.

To Constrain the Crop Window to a Ratio:

1. Check the **Constrain cropping proportion** checkbox.
2. Choose a ratio from the drop-down list.
3. Click on the **Rotate** button if you want to change the orientation of the crop window.

4. Do one of the following:

- Position your cursor over the edge of the crop window until it changes into a double-pointed arrow, and then drag the edge of the crop window to the desired size.
- Use the **Width** or **Height** spin box to specify a dimension for one side of the crop window. ACDSee Home automatically resizes the other dimension based on the ratio you selected.

To Resize the Crop Window by Using Relative Positioning:

You can enable relative positioning to specify how you want your image to crop. This can be particularly useful for cropping in batches.

1. Check the **Enable relative positioning** checkbox.
2. Choose in the Horizontal settings whether you would like to position the crop from the left or right edges, and the distance in pixels or as a percentage.
3. Choose in the Vertical settings whether you would like to position the crop from the left or right edges, and the distance in pixels or as a percentage.

Resizing an Image

You can resize an image by adjusting its dimensions in pixels, percentage, or actual/print size. While resizing, you can also choose an aspect ratio and a resampling filter to adjust the resized image's appearance.



You can [save your settings as a preset](#) for future use.

To Resize an Image:

1. In Edit mode, in the Geometry group, select **Resize**.



You can also access the Resize tool from the Filter drop-down menu or Filter toolbar.

2. Select one of the following resize options:
 - **Pixels:** resizes the image to specific dimensions in pixels.
 - **Percent:** resizes the image to a percentage of the original.
 - **Actual/Print size in:** resizes the image to match a specific output size. Click the drop-down list to specify a unit of measurement.
3. If you want to maintain a specific width to height ratio, check the **Preserve aspect ratio** checkbox, and then select one of the following options from the drop-down list:

- **Original:** maintains the original image's width to height ratio.
 - **1 x 1:** forces the width and height to be equal.
 - **2 x 3:** forces a width to height ratio of 2:3.
 - **3 x 2:** forces a width to height ratio of 3:2.
 - **3 x 5:** forces a width to height ratio of 3:5.
 - **5 x 3:** forces a width to height ratio of 5:3.
 - **Custom:** applies a custom ratio. Enter a width to height ratio in the **Custom Aspect Ratio** dialog box.
4. Select a resizing filter from the **Resizing Filter** drop-down list.
 5. Under the resize option you selected in step #3, type the image's new dimensions into the **Width** and **Height** spin boxes. If you selected Actual/Print size in, click the **Resolution** drop-down list, and then select a resolution (in dots per inch) for your output image.
 6. To estimate the size of the output image, click **Estimate new file size**.
 7. Do one of the following:
 - Click **Done** to apply your changes and close the Resize tool.
 - Click **Cancel** to discard all changes and close the tool.



Resizing Tips:

- Maintain image quality by reducing images only by 33%, 50%, or 66%. Other percentages can distort the aspect ratio.
- Avoid resizing an image repeatedly. Each resizing places image pixels using a slightly different orientation. As a result, multiple resizes can change the overall color and appearance of the image. If your first resize attempt does not produce the desired result, click the Undo button.
- Avoid increasing the size of an image. Increasing image size makes the image's pixels more apparent, causing a grainy effect.

Pixel Resize Options and Resulting Action

You can reduce and enlarge the size of one or more images from Manage mode by entering a new dimension in pixels. For more information on how to resize an image using pixel dimensions, please see [Resizing an image](#) or [Resizing multiple images](#).



Enlarging an image tends to pixelate the image, reducing image quality. It is best to avoid enlarging images.

Resize Options	Fit within Options	Action
Enlarge only		
	Width only	Resizes the image if the specified dimensions are larger than the image's original dimensions. The width is increased to the specified value and the height is increased to maintain the aspect ratio.
	Height only	Resizes the image if the specified dimensions are larger than the image's original dimensions. The height is increased to the specified value and the width is increased to maintain the aspect ratio.
	Width and height	Resizes the image if the specified dimensions are larger than the image's original dimensions. The width and height are increased as close to the specified value as possible, while maintaining the aspect ratio.
	Width or height (largest image)	Resizes the image if the specified dimensions are larger than the image's original dimensions. The width or height is increased as close to the specified value as possible to maximize the size of the image, while maintaining the aspect ratio.
Reduce only		
	Width only	Resizes the image if the specified dimensions are smaller than the image's original dimensions. The width is decreased to the specified value and the height is decreased to maintain the aspect ratio.
	Height only	Resizes the image if the specified dimensions are smaller than the image's original dimensions. The height is decreased to the specified

Resize Options	Fit within Options	Action
		value and the width is decreased to maintain the aspect ratio.
	Width and height	Resizes the image if the specified dimensions are smaller than the image's original dimensions. The width and height are decreased as close to the specified value as possible, while maintaining the aspect ratio.
	Width or height (largest image)	Resizes the image if the specified dimensions are smaller than the image's original dimensions. The width or height is decreased as close to the specified value as possible to minimize the size of the image, while maintaining the aspect ratio.
Enlarge or reduce		
	Width only	Resizes the width to the specified value and resizes the height to whatever value is necessary to maintain the aspect ratio.
	Height only	Resizes the height to the specified value and resizes the width to whatever value is necessary to maintain the aspect ratio.
	Width and height	Resizes the image within the specified width and height. The width and height are resized as close to the specified value as possible while maintaining the aspect ratio.
	Width or height (largest image)	Resizes the image within the specified width and height. The width or height is resized as close to the specified value as possible to maximize (or minimize) the size of the image, while maintaining the aspect ratio.


Adjusting Image Exposure

You can use the Exposure tool to adjust an image's exposure, contrast, and fill light.

 You can [save your settings as a preset](#) for future use.

To Adjust the Image Exposure:

1. In Edit mode, in the Exposure/Lighting group, select **Exposure**.

 You can also access the Exposure tool from the Filter drop-down menu or Filter toolbar.
2. Set the options as described below.
3. Do one of the following:
 - Click **Apply** to apply your changes and set options on another tab.
 - Click **Done** to apply your changes and close the tool.
 - Click **Cancel** to discard all changes and close the tool.




 Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

Image Exposure Options

Exposure	Drag the slider to the right to increase the exposure, or drag to the left to decrease exposure.
Auto	Click the Auto button to automatically adjust the exposure level.
Contrast	Drag the slider to the right to increase contrast, or drag to the left to decrease contrast.
Fill Light	Drag slider to the right to increase the amount of light in the darkest areas of the image, or drag to the left to decrease fill light. Fill light brightens dark areas of the image.
Exposure warning 	Highlights overexposed and underexposed areas of the image. Overexposed pixels turn red, underexposed pixels turn green. The icon is gray when disabled, and turns yellow if enabled.

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Adjusting Image Levels

You can use the Levels tool to precisely adjust the contrast and light levels in your images.



You can [save your settings as a preset](#) for future use.

To Adjust Image levels:

1. In Edit mode, in the Exposure/Lighting group, select **Levels**.





You can also access the Levels tool from the Filter drop-down menu or Filter toolbar.

2. Do one of the following:
 - Set the options as described below to adjust the contrast and light levels manually.
 - Click **Auto** and select a menu option to automatically adjust image properties.
3. Do one of the following:
 - Click **Apply** to apply your changes.
 - Click **Done** to apply your changes and close the Levels tool.
 - Click **Cancel** to discard all changes and close the tool.



Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

Levels Options

Channel	Specifies the brightness or color channel you want to adjust.
Shadows	<p>Specifies the black point of an image.</p> <p>Move the slider or type a number from 0 to 255 into the spin box to define the blackest area of an image. As the value increases, the dark colored areas of the image become darker. You can also click on the arrow to automatically set it to where the black point start in the image.</p>
Midtones	<p>Specifies the midtones in an image.</p> <p>Move the slider or type a number into the spin box to set the midtone. Higher values make the image appear brighter, while lower values make the image appear darker. You can also click on the arrow to automatically set it to the midtone of the image.</p>
Highlights	<p>Specifies the white point of an image.</p> <p>Move the slider or type a number from 0 to 255 into the spin box to define the whitest area of an image. As the value increases, the light colored areas of the image become lighter. You can also click on the arrow to automatically set it to where the highlights start in the image.</p>
Auto	<p>Select one of the following options:</p> <ul style="list-style-type: none">• Adjust Contrast: automatically analyzes and adjusts image contrast.• Adjust Color and Contrast: automatically analyzes and adjusts each color channel independently, and then adjusts the contrast.• Adjust Color and Brightness: automatically analyzes and adjusts image color and brightness.• Tolerance: opens the Tolerance settings dialog box. Specify the maximum clipping percentage for black and white levels, and click OK. ACDSee Home adjusts the image levels automatically.
Black Point picker 	Click the Black Point picker, and then click the image area you want to set as the black point.
Mid Point picker 	Click the Mid Point picker, and then click the image area you want to set as the mid point.
White Point picker	Click the White Point picker, and then click the image area you want to set as the white point.



When you click around the image with a selected eye dropper you will see the RGB numbers changing to reflect the RGB values of the pixel under the eye dropper. The RGB values represent the source pixel (unprocessed) and the current pixel as it appears on the screen.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

Adjusting Levels Automatically

You can use the Auto Levels tool to automatically correct the exposure levels of your images. Auto Levels makes the darkest image pixels darker, and the brightest pixels brighter.



You can [save your settings as a preset](#) for future use.

To Automatically Correct an Image's Levels:

1. In Edit mode, in the Exposure/Lighting group, select **Auto Levels**.



You can also access the Auto Levels tool from the Filter drop-down menu or Filter toolbar.

2. Select one of the following options:
 - **Auto Contrast and Color:** adjusts color differences, brightness, and balances RGB channels.
 - **Auto Contrast:** adjusts the color differences and brightness only.
 - **Auto Color:** balances the RGB channels in the image, without changing the brightness or contrast.
3. Use the **Strength** slider to fine tune the amount of exposure you want to apply.
4. Click **Exposure Warning** to make overexposed and underexposed pixels visible. Overexposed pixels turn red, underexposed pixels turn green.

5. Do one of the following:

- Click **Done** to accept your changes and close the panel.
- Click **Cancel** to discard your changes and close the panel.



Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.

Adjusting Tone Curves in Edit Mode

In **Edit** mode, the **Tone Curves** filter changes the tonal range of an image. Channel Filtering embedded in the **Tone Curves** pane adjusts either the entire range of the image (RGB), or specific colors (Red, Green, and Blue).



Save adjusted settings as a preset for future use.

To adjust the Brightness Curves in an image:

1. In **Edit** mode, do one of the following:
 - In the **Filter Menu** pane, under the **Exposure / Lighting** group, select **Tone Curves**,
 - Select **Filter | Exposure / Lighting | Tone Curves** from the main menu, or
 - Press **U**.
2. Set the options as described below.
3. Do one of the following:
 - Click **Apply** to accept any changes and remain in the tool,
 - Click **Done** to accept any changes and close the tool, or
 - Click **Cancel** to discard any changes and close the tool.



Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

Tone Curves Options

Channel	Specifies the color channels to adjust. Options include RGB, Red, Green, and Blue.
Show Histogram	Toggles the histogram display on and off.
Histogram	Displays a graphic of the color information levels in the image, based on the selected channel. Click and drag the line to manipulate the curve. Note that when a point on the curve is clicked, a Node Info Box appears in the top left corner of the Histogram. The Node Info Box contains In and Out pixel values which are set in blocks of color to give a visual representation. The Node Info Box numbers convey that an In value pixel will be changed to the Out value. For example, if the In value is 40 and the Out value is 80, all pixels with a value of 40 will be changed to 80. Clicking the curve adds a new point to the curve. Drag the points up and down the curve. To delete a point, right-click the node and select Delete point .
Color Picker	Drag the cursor onto the image to change the cursor to a color picker that provides the RGB and luminance values of the picker's current location. Click the image at a desired tone to add a corresponding point to the adjustment curve.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

Adjusting Lighting

You can use the Light EQ™ tool to adjust areas in an image that are too dark or too light, without affecting other areas of the photo. You can also simultaneously brighten dark areas that are too dark, and darken areas that are too bright. An example would be a portrait of someone in shadow but with a light background.



You can [save your settings as a preset](#) for future use.

The Light EQ™ tool lets you make quick and easy adjustments. ACDSee Home analyzes the photo and varies the adjustment throughout the image automatically. For example, darker images are brightened more. By opening the Light EQ™ tool, 1-Step applies an automatic exposure adjustment. For a more hands-on approach, the Basic tab allows you to click the Auto button and have ACDSee Home fully analyze the photo and set the slider positions automatically. You can also click directly on

an area of the image to generate automatic settings optimal for that area, (usually the subject of the photo).

- **1-Step** tab: for an instant, effortless exposure adjustment.
- **Basic** tab: for very quick and easy adjustments using three sliders. ACDSee Home analyzes the photo and varies the adjustment throughout the image automatically. For example, darker images are brightened more. By clicking the **Auto** button, you can have ACDSee Home fully analyze the photo and set the slider positions automatically. You can also click directly on an area of the image to generate automatic settings optimal for that area, (usually the subject of the photo).


To Open the Light EQ™ Tool:

In Edit mode, in the Exposure/Lighting group, select **Light EQ™**.



You can also access the Light EQ tool from the Filter drop-down menu or Filter toolbar.

Light EQ™ Controls

Right-click on a slider	Right-click on a slider to reset it.
Exposure Warning 	Click the Exposure Warning to make any overexposed or underexposed areas visible. Overexposed pixels turn red, underexposed pixels turn green. You can also toggle Exposure Warning on and off momentarily by holding down the E key.
Auto	Click to allow the software to analyze the photo and apply optimal settings based on the amount of light and dark pixels in the photo. Darker photos are brightened more than photos that are already bright.
Done	Click to apply your changes and close the tool.
Cancel	Click to discard all changes and close the tool.



Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

Using the 1-Step Tab

When you open an image in the Light EQ™ tool, 1-Step automatically adjusts your image's exposure. You can further adjust it using the Amount slider. To return to the 1-Step automatic adjustment, press the **Reset** button.

Using the Basic Tab

To Add Light to Dark Areas:


1. Drag the **Shadows** slider to the right to add light to the dark parts of the photo.
2. Adjust the settings using any of the controls in the table below.

To Darken Areas That Are Too Bright:

1. Drag the **Highlights** slider to the left to darken and return detail to areas that are too bright.
2. Adjust the settings using any of the controls in the table below.


To Adjust Midtones That Are Too Light or Dark:

1. Drag the **Midtones** slider to the right or left to brighten or darken the midtones.
2. Adjust the settings using any of the controls in the table below.

 You can right-click a slider to reset to the default value.

 You can use the **Edit Brush**  to paint this effect onto specific areas of your image.

 You can use the **Gradient** tool  to transition this effect across specific areas of your image.

 You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.


Adjusting White Balance

You can use the White Balance tool to remove unwanted hue from an image. For example, if you take a photo at sunset and the resulting image has a reddish hue, also known as a red color cast, you can use the White Balance tool to remove it.

 You can [save your settings as a preset](#) for future use.


To Remove a Color Cast from an Image:



1. In Edit mode, in the Color group, select **White Balance**.


 You can also access the White Balance tool from the Filter drop-down menu or Filter toolbar.

2. Click an image area that should be white or gray. The color square shows the color of the original pixel on the left, and the modified pixel on the right.
3. Drag the Temperature slider to the left (more blue) or right (more yellow) to select a specific color temperature.

4. Drag the Tint slider to the left (more magenta) or right (more green) to match the white balance settings that you selected when you took the photo.
5. To specify the strength of the white balance adjustment, move the Strength slider. Higher settings remove more of the unwanted color.
6. Click **Done** to save your changes, or click **Cancel** to discard your changes and leave the tool.

 You can right-click a slider to reset to the default value.

 You can use the Edit Brush  to paint this effect onto specific areas of your image.

 You can select the **Highlight neutral pixels** option to create a white balance mask over your image. Whiter pixels represent areas of low color saturation, while darker pixels represent areas of higher color saturation.

 If you are having difficulties achieving the desired effect, try clicking an image area that is a different shade of white or gray.

 Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

 You can use the Gradient tool  to transition this effect across specific areas of your image.

 You can use the Radial Gradient tool  to apply effects around, or directly to, a center point.


Adjusting Color with Color EQ

You can use the Color EQ tool in Edit mode to adjust overall colors in an image or each color individually. The advanced tools can subtly fine-tune and enhance colors, or completely change individual colors in an image.

Color EQ is useful for changing a single color in an image. If you have an image with a yellow car, you can use the Saturation tab to saturate the yellow or use the Brightness tab to brighten the yellow. In the Hue tab, you can change the color of the car from yellow to pink. In the Contrast tab, you can adjust the contrast of the yellow and use the Balance slider to target the brightness range for that contrast adjustment.

You can then use the Global Adjustments to make changes to balance the colors in your image. Vibrance adjusts the vibrancy of colors, saturation affects the strength of colors, color shift adjusts the hue without affecting brightness, hue will change colors, and lightness will affect how light the whole image is. You can also adjust color using the Red, Green, and Blue sliders to increase or decrease the balance of those colors.

 You can save your settings as a preset for future use.



 If you have an image of a yellow car with a yellow building in the background, you can change just the car by using the Selections tool. Select the car using the Selections tool and then apply your color adjustments.

To Adjust Color:



1. In Edit mode, in the Color group, select **Color EQ**.

 You can also access the Color EQ tool from the Filter drop-down menu or Filter toolbar.

2. Select any of the tabs within the ColorEQ or any of the sliders in the Global Adjustments section, and adjust them according to the options described in the tables below.
3. Do one of the following:
 - Click **Apply** to apply your changes.
 - Click **Done** to apply your changes and close the tool.
 - Click **Cancel** to discard all changes and close the tool.


 You can use the Edit Brush  to paint this effect onto specific areas of your image.

 You can use the Gradient tool  to transition this effect across specific areas of your image.


 You can use the Radial Gradient tool  to apply effects around, or directly to, a center point.

At the top of the Color EQ pane, choose either High Quality or Standard. Adjust image colors individually. High Quality uses the newer, more modern color models, allowing for a visually perceptive and higher quality adjustment. Standard supports previously developed images and allows you to adjust colors individually or make global adjustments.

Color EQ Options - High Quality.



Presets

In the presets drop-down menu, you can choose from existing presets, or save any of your current edits as a preset, using the save icon. 

Color EQ

Saturation, Brightness and Hue sliders

Adjust each color individually by dragging sliders right for more intensity, or left for less intensity. You can also enter a number into the fields for precise adjustments.

You can also select a precise color to adjust by placing your cursor on the image for the double arrow icon to appear. Then click and drag up or down to adjust the colors beneath the double arrow icon. The affected color sliders automatically adjust as you move your cursor.

The sliders have the following effects:

- **Saturation:** slide left to decrease saturation and slide right to increase saturation.
- **Brightness:** adjusts the image brightness.
- **Hue:** adjusts the hue of the image.

Contrast sliders

Adjust each color individually by dragging sliders right for more intensity, or left for less intensity. You can also enter a number into the fields for precise adjustments.

You can also select a precise

color to adjust by placing your cursor on the image for the double arrow icon to appear. Then click and drag up or down to adjust the colors beneath the double arrow icon. The affected color sliders automatically adjust as you move your cursor.

On the Contrast tab, once you have adjusted contrast, you can adjust contrast balance, which changes whether you apply the contrast to the lighter or darker colors in the image.

Global Adjustments

Vibrance, Saturation, Color Shift, Hue, and Lightness Sliders


Drag the sliders to make global adjustments. They will have the following effects:

- **Vibrance:** adjust the vibrance of the image without affecting skin tones.
- **Saturation:** slide left to decrease saturation and slide right to increase saturation.
- **Color Shift:** adjusts the hue without affecting brightness.
- **Hue:** adjusts the hue of the image.
- **Lightness:** adjusts the image brightness.


Red, Green, and Blue sliders

Drag the sliders to make global adjustments to the red, green, and blue channels in your image.

Color EQ Options - Standard.



Presets

In the presets drop-down menu, you can choose from existing presets, or save any of your current edits as a preset, using the save icon. 

Vibrance

Drag the slider to adjust the vibrance of the image without affecting skin tones.

Vertical slider

The vertical slider applies adjustments to the entire image. It has the following effects on the tabs:

- **Saturation:** adjusts saturation from grayscale to highly saturated.
- **Brightness:** adjusts the image brightness.
- **Hue:** adjusts the hue of the image.

You can also enter a number into the field for precise adjustments.

Direct image adjustments

Place your cursor on the image for the double arrow icon to appear. Then click and drag up or down to adjust the colors beneath the double arrow icon. The curve control and the affected color sliders automatically adjust as you move your cursor. The black down arrow on the graph indicates the color you are adjusting in the image.

The curve appears black in the graph, and you cannot directly adjust it. To apply further adjustments, you can alter the white curve. When you adjust the white curve, the black curve automatically changes with it. You can also enter a number into the fields for precise adjustments.

Individual color sliders

Adjust each color with individual sliders. Select the color you want to adjust and click and drag the sliders. You can also enter a number into the fields for precise adjustments.



You can right-click a slider to reset to the default value.

Creating a Grayscale Image

You can create rich grayscale images when you can control the brightness of the red, green, and blue channels, as well as the overall brightness. Use the Convert to Black and White tool to emphasize different areas or aspects of a photo, as well as alter its mood and tone.

If you hover your mouse over each slider and watch the effect on the small preview, it shows you which parts of the image will be affected by each channel. This helps to gauge the effect of each slider on the image.



You can also [save your settings as a preset](#) for future use.

To Create a Grayscale Image:

1. In Edit mode, in the Color group, select **Convert to Black & White**.



You can also access the Convert to Black & White tool from the Filter drop-down menu or Filter toolbar.

2. Adjust the settings as described in the table below.
3. Click **Done** to save your changes, or click **Cancel** to discard your changes and return to the Filter menu.

Grayscale Options

Brightness Tab

On the Brightness tab, do any of the following:

- Drag individual color sliders, or left-click on the image (where a color previously occurred) and drag up or down to alter the brightness of specific tones. For instance, drag your cursor on sky areas to alter the brightness of the blue.
- Drag the **Percent Red** slider to the left or right.

The more red there is in a pixel, the more effect the red slider has on that pixel. The area of red in the picture is brightened or darkened more than other areas.

- Drag the **Percent Green** slider the left or right.

The more green there is in a pixel, the more effect the green slider has on that pixel. The area of green in the picture is brightened or darkened more than other areas.

- Drag the **Percent Blue** slider to the left or right.

The more blue there is in a pixel, the more effect the blue slider has on that pixel. The area of blue in the picture is brightened or darkened more than other areas.

- Drag the **Percent Brightness** slider to the right or left to brighten or darken the whole image.



You can right-click the slider to reset the value to zero.

Contrast Tab

You can increase or decrease the contrast of each individual color. In addition, you can specify the brightness range that the contrast adjustment will target for each color.

On the Contrast tab, do the following:

Strength: to adjust the contrast in specific color tones, drag individual color sliders, or left-click on the image (where a color previously occurred) and drag up or down.

Balance: to set the targeted brightness range for the contrast adjustment, adjust the slider to bring details out of highlights or shadows. To bring details out of the midtones, leave the Balance sliders set to 0.



Hold down **Shift** while clicking and dragging on the image to target the color's corresponding Balance slider.



You can right-click the slider to reset the value to zero.

At the bottom of the Convert to Black & White panel, you can use the Amount and Hue sliders to add color back into the image. Choose the color using the Hue slider. The saturation of the color added back to any given pixel is scaled based on both the amount of color/saturation that existed in the original image and the Amount slider.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Color Grading with LUTs


"Color LUT" stands for Color Lookup Table. Color LUTs are lists that instruct ACDSee or related programs to map specific RGB values to other specific color values. You can import LUTs and use them as filters in ACDSee. You can apply a LUT in the same way you would use any other Edit mode filter. Color LUT supported file types are .3DL and .CUBE.

To Apply a Color LUT to Your Image:

1. In Edit mode, in the Color group, select **Color LUTs**.
2. On the Color LUTs panel, do one of the following:
 - Select a LUT from the list. The LUT is immediately applied.
 - Press the **Import LUTs** button. In the Open dialog, browse to the location of your LUT files, and press **Open**. The LUT is immediately applied.
3. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.

 If an imported LUT file's location has changed, you will have to reload it in the Color LUTs panel.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

To Refresh Your List of Color LUTs:

You can refresh your list of available LUTs to reveal moved or deleted files. Unavailable LUTs will be indicated in a darker font color.

On the Color LUTs panel, press the **Refresh List** button.

To Remove Color LUTs:

1. On the Color LUTs panel, press the **Remove LUTs** button.
2. In the Remove LUTs dialog, toggle the checkboxes next to the LUTs you want to delete.
3. Press **Remove LUTs**.

Using the Histogram


The Histogram is a graph that represents the distribution of color intensity for each color channel in an image.

To Display and Use the Histogram:

1. In View mode, click **Panes | Histogram**, or **View | Histogram** in Edit mode.
2. On the Histogram, check or uncheck the following checkboxes:
 - **R**: shows or hides the red color channel.
 - **G**: shows or hides the green color channel.
 - **B**: shows or hides the blue color channel.
 - **L**: shows or hides the lightness of the image.

Using the Color Dialog Box

The Colors dialog box appears in several places in Edit mode when you select or apply a color. You can use the Color dialog box to select a color in multiple ways and to adjust a color using several different tools.



The Standard Tab

On the first tab, there is a fixed honeycomb of Basic colors to choose from, including gray, black, and white at the bottom. Below it is a grid of Custom or Favorite colors that you can fill in by selecting a color and then right-clicking a box in the grid. To create a custom color, click the Custom tab.

The Custom Tab

On the second tab, there is a color palette. On the far right is a color slider, which you can use to navigate to a color group and gain access to any or all colors of the spectrum. Add colors to your Custom colors by selecting the color in the palette and then right-clicking a box in the grid.

Selecting and Adjusting Colors

To select a color, click on a square in the grid of custom colors, or on the color palette. You can also drag over the color palette. When you click a color, that color appears in the New box and all of its numerical values, (Hue, Saturation, Luminosity, as well as Red, Green, and Blue), appear in the fields on the Custom tab.

You can also adjust a color by changing the Hue, Saturation, and Luminosity values. To select a precise color, type in the values for that color. You can do the same using the Red, Green, and Blue values.


Sharpening an Image

You can use the Sharpen tool to sharpen an image by enhancing medium and high contrast edges.

 You can [save your settings as a preset](#) for future use.

To Sharpen an Image Using Sharpen Tool:

1. In Edit mode, in the Detail group, select **Sharpen**.

 You can also access the Sharpen tool from the Filter drop-down menu or Filter toolbar.


2. Drag the sliders to enhance or fix your image as described below.
3. Do one of the following:
 - Click **Done** to apply your changes and close the tool.
 - Click **Cancel** to discard all changes and close the tool.

 Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

Sharpen Options

Amount	Specifies the amount of sharpening applied by increasing contrast around the edges.
Radius	Controls the number of pixels to adjust around each edge. Higher values increase the number of sharpened pixels and tend to bring out coarser detail, while lower values reduce the number of sharpened pixels and tend to bring out finer detail.
Detail	Suppresses the halo, (the light border that forms around edges with extreme sharpening), by reducing its intensity. The higher the value, the stronger the reduction.
Threshold	Specifies how different the pixel lightness values within an edge must be before the pixels within the edge are sharpened. Higher values sharpen only stronger edges but minimize the appearance of noise. Lower values sharpen both strong and weaker edges, but can increase the appearance of noise. We recommend you set the threshold to enhance edges while keeping background noise to a minimum.

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.



You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

Blurring an Image

You can use the Blur tool to apply different kinds of blur to an image.



You can [save your settings as a preset](#) for future use.

To Blur an Image:

1. In Edit mode, in the Detail group, select **Blur**.



You can also access the Blur tool from the Filter drop-down menu or Filter toolbar.

2. In the **Blur type** section, select the type of blur to apply.
3. Set the options as described below.
4. Do one of the following:
 - Click **Done** to apply your changes and close the Blur tool.
 - Click **Cancel** to discard all changes and close the tool.



Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

Blur Types

Gaussian

Produces an even, smooth blur.

Amount

Specifies the amount of blur. Move the slider to the right to intensify the effect.

Linear

Produces a blurring effect that gives the illusion of movement.

Amount

Specifies the amount of blur. Move the slider to the right to intensify the effect.

Angle

Specifies the direction of the blur effect.

Radial

Produces blur around a center point. Click the image to set the center point.

Amount

Specifies the amount of blur. Move the slider to the right to intensify the effect.

Clockwise

Specifies clockwise blur.

Counter-clockwise

Specifies counter-clockwise blur.

Horizontal position

Specifies the blur's center point on the horizontal axis.

Vertical position

Specifies the blur's center point on the vertical axis.

Spread

Produces a smeared or frosted blur.

Amount

Specifies the amount of blur. Move the slider to the right to intensify the effect.

Zoom



Produces inward or outward blur to or from a center point.

Amount

Specifies the amount of blur. Move the slider to the right to intensify the effect.

Zoom in

Creates a blur that zooms in to the image's center.

Zoom out

Creates a blur that zooms out from the image's center.

Horizontal position

Specifies the blur's center point on the horizontal axis.

Vertical position

Specifies the blur's center point on the vertical axis.

Smart Blur



Produces blur by detecting and avoiding edges, and preserves detail based on the threshold setting. This effect is usually used to smooth out skin.

Amount

Specifies the amount of blur. Move the slider to the right to intensify the effect.

Threshold

Specifies how little detail an area must have before the blur will apply to it.

Lens



Produces a blur that mimics the blurring effect of a camera aperture.

Select a bokeh shape from the options on the Blur panel. These shapes concentrate in highlights.

Amount

Specifies the strength of the blur. Move the slider to the right to intensify the effect.

Bokeh Frequency

Specifies how often the bokeh shapes show up.

Bokeh Brightness

Specifies how much the bokeh shapes stand out.



You can right-click a slider to reset to the default value.



You can use the [Edit Brush](#)



to paint this effect onto specific areas of your image.



You can use the [Gradient](#) tool



to transition this effect across specific areas of your image.




You can use the [Radial Gradient](#) tool  to apply effects around, or directly to, a center point.

About Noise and Noise Reduction


Image noise looks like random black, white, or colored pixels in an area of a photo where there should be solid color, such as a dark night sky. In digital photography, noise is typically more visible in the dark areas of a photo.

There are many causes of image noise. You will increase image noise if you use a high ISO setting (such as ISO 800) to capture a photo, or if you extend the exposure time. (You would typically use a high ISO setting and extend exposure time to take a photo in low light.) However, image noise can be caused by dead or stuck pixels in a digital camera's image sensor. Similarly, dust on a camera lens or scanner bed can cause noise by blocking or reflecting light.

Images generally have two types of noise: luminance and color. Luminance noise is random variations of brightness, and particularly in gray areas, may appear spotted when there should be a solid color in the area of the image.



Color noise is random variations of color in the image.



Noise is visually distracting, so in most cases you will want to reduce noise in your photos. However, if you reduce noise too much you may unintentionally reduce image sharpness. You can use the Noise Removal tool to remove both luminance and color noise in your images.

Removing Noise

You can use the Remove Noise tool to remove noise from your images while preserving details that you want to retain.



You can use the Remove Noise tool to remove hot image pixels caused by digital cameras with malfunctioning CCD array sensors, or the extra pixels caused by a dusty scanner or camera lens.



You can save your settings as a preset for future use.

To Remove Noise from an Image:

1. In Edit mode, in the Detail group, select **Noise**.



You can also access the Noise tool from the Filter drop-down menu or Filter toolbar.

2. Select the **Remove Noise** tab.
3. Select an option from the Noise Type section.
4. Set the options as described below.



Hold down the **Alt** key while adjusting a slider to view a preview of its effect on the image.

5. Do one of the following:
 - Click **Done** to apply your changes and close the Remove Noise tool.
 - Click **Cancel** to discard all changes and close the tool.



Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

Noise Removal Options

Apply to channel

Modifies a targeted color channel by mixing the existing color channels in the image.

Noise Type



Camera Noise Removal

Removes digital camera noise. Adjust the following sliders to further remove noise:

- Luminance** Reduces the random variations of brightness in the noise.
- Strength** Controls the strength of the Luminance tool.
- Color Noise Reduction** Drag the slider to the right to remove color noise from the image. Hold down the **Alt** key while using the slider to see the remaining color noise in the image.
- Tonal Range** Tonal Range refers to a range of average brightness values in an image. For example, the tonal range of a photo taken in a dark cavern it would be low, whereas a sunny sky would be high.

The **Tonal Range** slider increases in value from left to right, increasing from a low tonal range on the left to a high tonal range on the right. The **Tonal Range** slider is used to focus noise reduction to areas of the image that have a corresponding tonal range. For example, the left-most position would reduce the noise in a cavern more than a sky.

Tonal Range only affects luminance noise reduction.
- Frequency Range** The **Frequency Range** slider adjusts the noise pattern. High frequency noise looks like fine static while low frequency noise looks like coarse grain or "splotches". Move the **Frequency Range** slider to the left to limit noise reduction to high frequency noise.

Frequency Range affects both luminance and color noise reduction.



Median Noise Removal

Reduces impulsive, or salt-and-pepper noise while preserving edges. Select from the following options to further remove noise:

- Square** Removes noise using a 3 x 3 pixel square.
- X** Removes noise using a 3 x 3 pixel X shape. Use this option when you want to preserve an image's thin and diagonal lines.
- Plus** Removes noise using a 3 x 3 pixel plus (+) shape. Use this option when you want to preserve an image's thin, vertical, and horizontal lines.

**Despeckle**

Removes noise.



You can right-click a slider to reset to the default value.



You can use the **Edit Brush**  to paint this effect onto specific areas of your image.



You can use the **Gradient** tool  to transition this effect across specific areas of your image.



You can use the **Radial Gradient** tool  to apply effects around, or directly to, a center point.

Adding Noise

You can use the Add Noise tool to add a grainy texture to an image. Adding small amounts of noise can reduce the appearance of minor imperfections in the original image.



You can [save your settings as a preset](#) for future use.

To Add Noise to an Image:

1. In Edit mode, in the Detail group, select **Noise**.



You can also access the Noise tool from the Filter drop-down menu or Filter toolbar.


2. Select the **Add Noise** tab.
3. Set the options as described below.
4. Do one of the following:
 - Click **Done** to apply your changes and close the Add Noise tool.
 - Click **Cancel** to discard all changes and close the tool.



Click **Reset** to clear your changes and reset to default settings. If you saved your changes, you cannot reset your settings.

Add Noise Options

Intensity	Specifies the amount of noise to add to the image. A higher intensity increases the chance that a noise pixel will replace a pixel in the original image.
Color proximity	Specifies the color of noise pixels to add to the image. A lower value gives each noise pixel a color similar to the pixel it replaces. Higher values result in a random selection of the noise pixel color.
Noise color	<p>Select one of the following options to specify noise pixel color:</p> <ul style="list-style-type: none"> • Random: randomly selects the color. • Monochrome: produces black and white noise pixels. • Adjustable: randomly selects the color of each noise pixel, but more pixels match a defined color. To define a color, click the color picker and select a color.
Noise placement	Adds noise to image areas that closely match a defined color. Check the Set color checkbox to enable noise placement, and click the color picker to specify a color.
Randomize	<p>Indicates the random placement of noise in an image.</p> <p>When you use the Add Noise tool, ACDSee Home places the noise pixels based on a random seed. This makes the image noise different each time you use the Add Noise tool. You can define a specific random seed to generate identical image noise.</p> <p>To generate a new random seed, click Randomize.</p>

 You can right-click a slider to reset to the default value.

 You can use the [Edit Brush](#)  to paint this effect onto specific areas of your image.

 You can use the [Gradient](#) tool  to transition this effect across specific areas of your image.

Adjusting Clarity

The Clarity tool adds subtle definition to the details in your image. Use the Clarity tool to enhance the contrast of midtones in your images, without overpowering the shadows and highlights.

 You can [save your settings as a preset](#) for future use.

To Adjust the Clarity of Your Image:

1. In Edit mode, in the Detail group, select **Clarity**.



You can also access the Clarity tool from the Filter drop-down menu or Filter toolbar.

2. Drag the **Strength** slider to the right for greater clarity, or to the left for reverse clarity.
3. Do one of the following:
 - Click **Done** to accept your changes and close the panel.
 - Click **Cancel** to discard your changes and close the panel.



You can also type a number into the number box and incrementally make precise adjustments.



You can right-click a slider to reset to the default value.



You can use the Edit Brush



to paint this effect onto specific areas of your image.



You can use the Gradient tool  to transition this effect across specific areas of your image.



You can use the Radial Gradient tool  to apply effects around, or directly to, a center point.

Using People Mode

People mode is a dedicated space for managing all your images of the people in your life.

People mode can be accessed by selecting the **People** mode icon in the mode bar, or by selecting **Tools | Manage People...** from the **Manage** mode main menu.

There are three views in **People** mode:



- Named
- Unnamed
- Person

The **Named** and **Unnamed** views can be accessed from the **Named** and **Unnamed** buttons directly above the results grid in the button bar. To access the **Person** view, double-click a person's facial image in **Named** view only.



In Unnamed and Person view, select faces by clicking the face, or multi-select with **Ctrl + click**, **Shift + click**. Click the mode switch toolbar to take your selected thumbnails directly to **View** or **Edit** mode. Double-clicking on a single thumbnail will bring the image into View mode.



For both the **Unnamed** and **Person** views, toggle the **Show Face Thumbnails**  icon and the **Source Image Thumbnails**  icon to view the face thumbnail or the entire source image.

Named View

The **Named** view in **People** mode is populated with images of all the people that have been assigned a name in the ACDSee photo database. Images of identified people can be merged (for people with many like-sounding names such as "Jonathan", "Johnny", "John"), renamed, or removed. Double-clicking a person opens that person's **Person** view where all of the person's assigned faces reside and AI-prepared suggestions can be confirmed or denied.



The **Named** view will display the number of faces assigned to each person. More faces can still be assigned beyond 9999.

Unnamed View

The **Unnamed** view in **People** mode is populated with faces that haven't been assigned a name.

The **Unnamed** view can be filtered between **Grouped** and **Ungrouped** faces by toggling the drop-down list located at the far right of the button bar above the facial images.

In **Grouped**, the view is split between two panes. The top pane displays grouped faces with a number in the bottom-right corner of each, indicating how many similar faces have been detected. The bottom pane shows both the total number of faces and the faces associated with the selected group(s).

Grouped faces are similar enough in structure that the AI in People mode suggests grouping them together.

In **Ungrouped**, the view displays a flat grid of all of the unnamed faces in the database. **Ungrouped** images are all of the single facial images without AI-generated groups applied.

The **Unnamed** view is used to manage the unnamed faces by assigning them to a name, or deleting the face.

Person View

In **People** mode, the **Person** view is a display of all faces associated with one person.


The **Person** view is comprised of two separate areas:

- The **Assigned Faces** pane, a collection of facial images previously assigned with the person's name.
- The **Suggested Faces** pane, a collection of faces that AI considers a possible match with the person.



Person view can only be accessed from the **Named** view.

Folders Pane

The **Folders** pane is used for filtering results by folder. Click to select a single folder, or multi-select with **Ctrl + click**, **Shift + click**, or by clicking the Easy-Select arrows  to the left of the folder names.

The **Folders** pane is located to the left of the results grid and has two views:


- Tree view, for an expanded view of folders visited in **Manage** mode that contain faces.
- List view, for a flat list of folders containing faces.

Use the View button to the right of the **Folders** label to toggle between the Tree view and the List view.

Use the Folders Refresh icon  below the **Folders** label to clear the current folder selection.

The Named View

The **Named** view in **People** mode is populated with images of all the people that have been assigned a name in the ACDSee photo database. Images of identified people can be merged (for people with many like-sounding names such as "Jonathon", "Johnny", "John"), renamed, or removed. Double-clicking a person opens that person's **Person** view where all of the person's assigned faces reside and AI-prepared suggestions can be confirmed or denied.

 The **Named** view will display the number of faces assigned to each person. More faces can still be assigned beyond 9999.

To Merge People:

1. In **People** mode, in the **Named** view, select more than one person.
2. Right-click one of the selected people.
3. From the context menu, select **Merge People**.
4. In the **Merge People** dialog, do one of the following two options:
 - Enter a new name in the **Enter or select a name** field, or
 - Select a name from the **Enter or select a name** dropdown.
5. Click the **OK** button.

 Merging can also be driven from the Edit menu.

To Rename a Person:

1. In **People** mode, in the **Named** view, select a person to rename.
2. Right-click the selected person.
3. From the context menu, select **Rename Person**.

4. Enter the person's new name in the highlighted bar beneath the person's image.
5. Press **Enter**.



Renaming can also be driven by clicking an associated name box beneath the image, or from the Edit menu.

To Remove a Person or Persons:

1. In **People** mode, in the **Named** view, select a single person or people to remove.
2. Right-click the selected person(s).
3. From the context menu, select **Remove Person(s)**.
4. In the prompted dialog, click the **OK** button.



Removing can also be driven from the Edit menu.

Grouping People:

Located directly above your named people and to the right-side of the **Named** and **Unnamed** buttons, the **Group** dropdown is used to alter how people are presented. Groups can be sorted forward or backward.

Type	Description	Example
Name	Displays people grouped by names. Groups are ordered alphabetically by first letter.	Use this when you want to organize all detected people under their assigned names for easier browsing and verification.
Face Count	Displays people grouped by the number of detections for each person.	Use this when you want to prioritize people that appear most frequently in your photos, which can speed up tagging for commonly seen individuals.
Suggestions	Displays people grouped by whether or not suggestions are available for each detected person.	Use this when you want to review people that specifically do or do not have suggestions.



Right-click on group headers to show options for collapsing and expanding groups.

Unnamed View

The **Unnamed** view in **People** mode is populated with faces that haven't been assigned a name.

The **Unnamed** view can be filtered between **Grouped** and **Ungrouped** faces by toggling the drop-down list located at the far right of the button bar above the facial images.

In **Grouped**, the view is split between two panes. The top pane displays grouped faces with a number in the bottom-right corner of each, indicating how many similar faces have been detected. The bottom pane shows both the total number of faces and the faces associated with the selected group(s).

Grouped faces are similar enough in structure that the AI in People mode suggests grouping them together.

In **Ungrouped**, the view displays a flat grid of all of the unnamed faces in the database. **Ungrouped** images are all of the single facial images without AI-generated groups applied.

The **Unnamed** view is used to manage the unnamed faces by assigning them to a name, or deleting the face.

To Delete the Face From the Unnamed View:

1. Select the face to be deleted.
2. Do one of the following:
 - Right-click the face and select Delete Face(s) from the context menu,
 - Select Edit | Delete Face(s) from the main menu, or
 - Press Delete.

To Assign a Name to an Unnamed Face Using the Name Bar:

1. Click the bar beneath an unnamed face.
2. Enter a name.
3. Press **Enter**.



When pressing enter, the cursor will be automatically taken to the next unnamed face.

To Assign a Name to an Unnamed Face Using the Context Menu:

1. Right-click an unnamed face.
2. Select **Name Face(s)...** from the context menu, or press **F2**,
3. Enter a name in the **Name** field.
4. Click **OK**.



Faces supplied with names automatically disappear from the **Unnamed** view and are populated into the **Named** view.



In **Grouped**, deleting or naming a group in the top pane will affect all of the faces in the group. Deleting or naming faces in the bottom pane will affect only those faces.

Deleting Images and Faces in the Unnamed View:

To Delete Faces:

1. Select one or more unnamed faces.
2. Perform one of the following:
 - Select **Edit | Delete Face(s)**.
 - Right-click on one of the selected faces and select **Delete Face(s)** from the context menu
 - Press **Delete**.

To Delete Images:

1. Right-click one or more selected unnamed faces.
2. Perform one of the following:
 - Select **Edit | Delete Image(s)**.
 - Right-click on one of the selected faces and select **Delete Image(s)** from the context menu.
 - Press **Ctrl + Delete**.



Deleting images in **People** mode will delete them from the hard drive entirely.

Person View

In **People** mode, the **Person** view is a display of all faces associated with one person.

The **Person** view is comprised of two separate areas:

- The **Assigned Faces** pane, a collection of facial images previously assigned with the person's name.
- The **Suggested Faces** pane, a collection of faces that AI considers a possible match with the person.



Person view can only be accessed from the **Named** view.

Assigned Faces Pane

The **Assigned Faces** pane is populated with facial images previously assigned with the person's name. Each image in the **Assigned Faces** pane has a right-click context menu detailed in the following table.


Assigned Faces Pane Context Menu Options



Menu Item	Shortcut	Description
Rename Face(s)...	F2	Opens the Rename Face(s) dialog where a new name can be entered. The facial image is automatically removed from the current Person view and placed in the Named view after a new name is applied.
Remove Face(s)...	Delete	Removes the name from the facial image and returns the image to the Unnamed view.
Set as Profile		Sets the selected image as the profile image for the person.
Delete Face(s)	Shift + Delete	Removes the association with a person and deletes the facial image from People mode.
Delete Image(s)	Ctrl + Delete	Deletes the source image from the hard drive.

Renaming Faces

To rename faces, you can left-click on a face in **Assigned Faces** and press **F2**, or right-click and choose **Rename Face(s)...** in the Context menu. This will bring up a **Rename Faces** dialog where a new name can be entered. When confirming the new name, the face will be automatically moved to the new person.

The Suggested Faces Pane



The **Suggested Faces** pane is populated with faces that AI considers a possible match with the person. When the AI in **People** mode considers unnamed faces to be a possible match for a person, a face icon  will appear in the lower left corner of a named face in **Named** view.

You can manage **Suggested Faces** by clicking on the green check mark icon  to confirm, the red crossed out circle icon  to deny, or by clicking directly into the text field for the name and changing the name manually. If you've clicked into the text field for the name, pressing **Enter** will confirm your change and automatically move to the next face in **Suggested Faces**. Each image in the **Suggested Faces** pane has a right-click context menu detailed in the following table.





The total number of suggested faces will display above the face suggestions.

Suggested Faces Pane Context Menu Options

Menu Item	Shortcut	Description
Confirm Face(s)...	Enter	Confirms the AI-generated suggestion as belonging to the person. The green check mark icon  located in the name bar beneath the facial image can also be used to confirm.
Deny Face(s)...	Delete	Removes the AI-generated suggestion from the facial image and returns the image to the Unnamed view. The red crossed out circle icon  located in the name bar beneath the facial image can also be used to deny.
Rename Face(s)	F2	Opens the Rename Face(s) dialog where a new name can be entered. The facial image is automatically removed from the current Person view and placed in the Named view after a new name is applied.
Delete Face(s)	Shift + Delete	Removes the AI-generated suggestion from the facial image and deletes the facial image from People mode.
Delete Image(s)	Ctrl + Delete	Deletes the source image from the hard drive.



To confirm or deny all faces in the pane, click the Confirm All Suggestions icon  or the Deny All Suggestions icon  located at the far right of the **Suggested Faces** pane header bar.




Confirming a face by pressing **Enter** will move the **Suggested Face** into **Assigned Faces** and highlight the next **Suggested Face**.

Chapter 7: 365 Mode



For help with seedrive.acdsee.com, click the **Web** tab, then click **Support**.

You can use 365 mode to upload your images to seedrive.acdsee.com, an image sharing and storage service available to ACDSee Home users. With 365 mode and seedrive.acdsee.com, you can upload and browse through your online images without having to launch an Internet browser. You need to create a seedrive.acdsee.com account first, before uploading your photos.



With seedrive.acdsee.com, you can:

- [Create Your seedrive.acdsee.com Account](#)
- [Upload Images](#)
- [Set Privacy Settings for Your Image Folders](#)

Working in 365 Mode



For help with seedrive.acdsee.com, click the **Web** tab, then click **Support**.

You can use 365 mode to upload your images to seedrive.acdsee.com, an image sharing and storage service available to ACDSee Home users. With 365 mode and seedrive.acdsee.com, you can upload and browse through your online images without having to launch an Internet browser. Or you can access seedrive.acdsee.com at any time directly from an Internet browser.

365 Mode Has Two Parts: seedrive.acdsee.com and Transfer



To enable the seedrive.acdsee.com and Transfer tabs, you need to [create a \[seedrive.acdsee.com\]\(https://seedrive.acdsee.com\) account](#).

seedrive.acdsee.com

Clicking the seedrive.acdsee.com tab takes you to seedrive.acdsee.com, where you can browse through images you have uploaded to your online account, see other users' images, or upgrade your membership level. seedrive.acdsee.com has the following menus:

- **Manage:** organize your images into folders.
- **Upload:** click Upload to switch to Transfer for uploading images.
- **Profile:** modify your profile and set specific information to public or private.
- **Support:** see the Help or FAQs for assistance with seedrive.acdsee.com.

Transfer

Transfer allows you to upload images to your seedrive.acdsee.com account. In Transfer, the screen splits into two. The bottom of the screen displays the available images in your computer, and the top of the screen displays your seedrive.acdsee.com account.



You cannot take an image from 365 mode and open it in Edit mode for editing. To edit an image, select an image in Manage or View mode and open it in Edit mode for editing.

Creating an ACDSee 365 Account

Before you can upload your images to seedrive.acdsee.com, you need to create an account.

To Create an ACDSee 365 Account:

1. Click the **365** tab to enter **ACDSee 365** mode.
2. Press the **Sign Up** button.
3. Enter your information into the fields and click **Create your account**.



If you already have an account, click the **Sign In** button.

Uploading Images to ACDSee 365



For help with seedrive.acdsee.com, click the **Web** tab, then click **Support**.

ACDSee 365, or seedrive.acdsee.com, is an image sharing and storage service for ACDSee users. Before you upload photos, you need to create a seedrive.acdsee.com account. There is no size limit for uploading images to your seedrive.acdsee.com account.



Depending on your ACDSee 365 account level, you can also upload videos.

To Upload Your Images:

1. In 365 mode, click **Sign In**.
2. Log in to your account.
3. Click **Upload** to switch to Transfer.

Your screen splits in two, with the bottom part of the screen displaying images on your computer, and the top part of the screen representing your images online.

4. Use the drop-down list in the top right corner to select one of the following:
 - **Upload Original with associated data:** upload image in current file format, including any associated files such as those containing metadata. This option is the best for images you want to archive.
 - **Upload Original (as JPG):** uploads image as a JPG in its original size.
 - **Upload 1920 x 1440 JPG:** converts the image to JPG and sets the size to 1920 x 1440. This option is the best for high quality JPGs.
 - **Upload 1024 x 768 JPG:** converts the image to JPG and sets the size to 1024 x 768. This option results in the fastest upload.
5. Do one of the following to select an image to upload:
 - Click and drag an image into the top part of the screen to upload it to your seedrive.acdsee.com account. To select multiple images, press the **Shift** or the **Ctrl** key and click on the images to select them. You can also click and drag your cursor to select multiple images.
 - Drag a folder of your images to the top part of the screen.
 - Select images and click the up arrow icon beside Transfer Manager, or click Sync to Web to upload all the images in the Sync to Web folders.

When upload is complete, images are displayed in the order they were uploaded. Overlay icons indicate the file type and if the image has been edited.



You can upload a folder with sub-folders. 365 mode respects folder hierarchy when uploading a folder to your seedrive.acdsee.com account.

Setting Folders to Sync to Web



For help with seedrive.acdsee.com, click the **Web** tab, then click **Support**.

You can set specific folders on your computer to upload all of their images to specific folders on seedrive.acdsee.com. As you add new images to the folder on your computer, you can quickly sync the corresponding folder on seedrive.acdsee.com by pressing the Sync to Web button. The sync works in one direction; images from your computer are uploaded to your seedrive.acdsee.com account.

To Set a Folder to Sync to Web:

1. In 365 mode, click **Sign in**.
2. Click the **Transfer** tab.
3. In the Folders pane in the bottom half of the screen, right-click a folder and select **Set as "Sync to Web" Folder** or click **Alt + A**.
4. In the Setup "Sync to Web" Folder dialog box, set the options as described below.
5. Click **OK**.



You can also set Sync to Web folders by clicking **File | Manage Sync to Web Folders**.

To Run Sync to Web:

1. In Transfer, on the right side along the screen split, click **Sync to Web**.
2. Click **OK**.

To Edit a Folder's Sync to Web Settings:

1. In Transfer, in the Folders pane in the bottom half of the screen, right-click a Sync to Web folder, and select **Edit "Sync to Web" Folder**.
2. In the Edit "Sync to Web" Folder dialog box, set the options as described below.
3. Click **OK**.

Sync to Web Folder Options

Upload Type	<p>Use the drop-down list to select one of the following:</p> <ul style="list-style-type: none"> • Upload Original with associated data: uploads images in their current file format, including any associated files such as those containing metadata. This option is the best for images you want to archive. • Upload Original (as JPG): converts the image to JPEG in it's original size. • Upload 1920 x 1440 JPG: converts the image to JPEG and sets the resolution to 1920 x 1440. This option is the best for high quality JPEGs. • Upload 1024 x 768 JPG: converts the image to JPEG and sets the resolution to 1024 x 768. This option is the best for images you want to view on a Netbook, and results in the fastest upload.
Local Folder	Displays the path to the folder you selected. Click the browse button to select a different folder.
Online Folder	Enter a name for the online folder. By default this is set to the same name as the folder on your computer that you want to sync to Web.
Sync to Web right away	Check this box to upload the images in the selected folder immediately. If you do not check this checkbox, you can click Sync to Web to upload all the images in all the folders you have chosen to sync.

Creating Folders and Setting Privacy



For help with seedrive.acdsee.com, click the **Web** tab, then click **Support**.


In seedrive.acdsee.com and Transfer, you can create folders and make them private or public. When you make a folder public, anyone can find and see the images in that folder. You can also copy the URL for your public folders and share it with family and friends.



When you create a new folder, it is set to private by default.

To Create a Folder and Make it Private or Public in Transfer:

1. In 365 mode, click **Transfer**.
2. In the Folders pane on the top left, right-click your user name, and select **New Online Folder...**
3. In the New Online Folder dialog box, enter a name for the new folder.
4. Click **OK**.

By default the new folder is Private. 

To change the folder to Public , right-click on the folder, and then click **Make Public**.

To Share the URL for a Public Folder:

1. In 365 mode, click **Transfer**.
2. In the Folders pane on the top left, right-click on a public folder.
3. Click **Copy URL**.
4. Paste the URL into an email, instant message, or other application to share it.



Right-click a public folder and select **Share folder** to share in an email, post on a social networking site, or to create a widget.

Changing the Rating System



For help with seedrive.acdsee.com, click the **Web** tab, then click **Support**.

Photos that you have rated in Manage mode are rated with a star rating system in 365 mode. You can select how to use stars to rate your photos.

To Change Your Rating System:

1. Click **Tools** and then select **Options**.
2. In the Options dialog box, select **ACDSee 365**.
3. In Ratings, select **Convert 'Rating 1' to 5 stars** or **Convert 'Rating 1' to 1 star**.
4. Click **OK**.

Downloading Images



For help with seedrive.acdsee.com, click the **Web** tab, then click **Support**.

seedrive.acdsee.com is also a storage service for ACDSee Home users. You can download your images from your seedrive.acdsee.com account to your computer at any time.

To Download Your Images:

1. In 365 mode, click **Sign In**.
2. Log in to your account.
3. Click the **Transfer** tab.

Your screen splits in two, with the bottom part of the screen displaying images on your computer, and the top part of the screen representing your images online.

4. In the top part of the screen, in the Folders pane in the top left, navigate through your seedrive.acdsee.com folders to the images you want to download.

5. In the bottom part of the screen, in the Local Computer pane, select a folder that you want to download your image to.
6. Do one of the following to select an image to download:
 - Click and drag an image into the bottom part of the screen to download it to your computer. To select multiple images, press the **Shift** or the **Ctrl** key and click on the images to select them. You can also click and drag your cursor to select multiple images.
 - Drag a folder of your images to the bottom part of the screen.
 - Select images and click the down arrow icon beside Transfer Manager.

Using the Transfer Manager









For help with seedrive.acdsee.com, click the **Web** tab, then click **Support**.

The Transfer Manager lets you monitor the progress of your uploads and downloads on your seedrive.acdsee.com account, and also lets you cancel or pause image transfers. The Transfer Manager has two tabs: Uploads and Downloads. These two tabs list images that are being uploaded, downloaded, paused, or canceled.

To Open the Transfer Manager:

Click **Tools** | **Transfer Manager**.

You can do the following in Transfer Manager:

	Cancel an upload or download.
	Retry the image upload or download.
	Pause an upload or a download.
	Continue the image upload or download.
	Selects all images in the list.
	Clear uploaded, downloaded or canceled images from the list.

Chapter 8: Dashboard Mode

Using Dashboard Mode

Dashboard mode provides an easy way to monitor your file, camera, and database statistics in one place. Camera data is gathered from your image metadata, and file information is analyzed from your ACDSee database. To see the most accurate information, make sure your files are [cataloged](#).

Cataloging Files

To catalog your files, do one of the following:

- Go to **Tools | Database | Catalog**.
- Browse your folders in Manage mode.

Dashboard Mode Tabs

Dashboard mode is organized into four tabs, each giving you a different view of your data:

- **Overview tab:** Provides a high-level summary of your photo activity and database status.
 - At the top, a graph shows your photo counts by month or year. Use the drop-down menu to switch between Yearly and Monthly views, and the Prev and Next buttons to move through time.
 - Below the graph, you will find:
 - **Database Summary:** Total Database Size, Total # of Files and Folders, and Last Backup Date.
 - **Cameras Summary:** Camera Most Used, Total # of Cameras, and Favorite ISO Setting.
 - **File Summary:** # of Image and Video Files, Favorite File Format, and Favorite Image Resolution.



This tab is useful for a quick health check of your photo collection and database.

- **Database tab:** Displays detailed information about your database so you can track its size, structure, and backup status.

- **Total Database Size:** Includes the database file path.
- **File Information:** A breakdown of Image Files, Video Files, and Other Files.
- **Folder Information:** Counts for Folders Browsed, Remote Folders Browsed, and Removable Folders Browsed.
- **Orphan Assets:** Shows the number of orphaned Files and Folders.
- **ACDSee Database Backup:** Displays your last backup date, so you can confirm your data is safe.
- **Thumbnail Information:** Includes the size of the Thumbnail Cache and how many images have thumbnails.



Use this tab to monitor database performance and ensure your backups and thumbnails are up to date.

- **Cameras tab:** Shows how you use your cameras and lenses.
 - The **Cameras Summary** panel (on the left) highlights your Most Used Camera, Lens, Focal Length, Aperture, Shutter Speed, and ISO.
 - The main display includes:
 - Circle graphs showing the number of photos by Camera, Lens, and Focal Length, with percentage breakdowns.
 - Bar graphs showing the number of photos by Aperture, Shutter Speed, and ISO.
 - You can toggle these graphs on or off from **View | Graphs**.



This tab helps you understand your shooting habits, such as which lenses or settings you use most often.

- **Files tab:** Displays information about your image and video files.
 - The **File Summary** section (upper left) shows the total number of files, your favorite file format, and your most common image resolution.
 - Two circle graphs provide a breakdown of File Formats and Bit Depths, with percentages displayed in a legend.
 - A bar graph displays the Top 20 Image Resolutions in your collection.



This tab gives you insight into the types of files you work with most frequently.

Chapter 9: PicaView

About ACDSee PicaView

ACDSee PicaView is a quick and easy file viewer "add-on" for Windows/File Explorer™ that saves you time by letting you preview files without having to open them in an application. If you right-click, you can view your image EXIF information or view your image files in various sizes — including RAW files. You can also view a preview of any other image file format supported by ACDSee. You can access the ACDSee PicaView preview by right-clicking a file in Windows/File Explorer™.

You can configure a variety of ACDSee PicaView's settings, including the size of the preview, what information displays, and more. Access these settings by clicking **ACDSee PicaView | Options...**, or through ACDSee, by going to **Tools | Options...** and navigating to ACDSee PicaView in the Options dialog's menu.

To Adjust the ACDSee PicaView Options:

1. Right-click a file in Windows/File Explorer™ to access the ACDSee PicaView preview.
2. At the top of the preview, click **ACDSee PicaView | Options...**
3. On the ACDSee PicaView Options dialog, set or change the options as described below.
4. Click **OK** to apply your changes.

ACDSee PicaView Options

Display Image

Check the **Display Image** checkbox to display a preview of the right-clicked file on the context menu.

Location

- **Add image to main menu:** when you right-click, displays preview in the main menu.
- **Add image to sub-menu:** when you right-click, displays preview in a sub-menu, available by clicking the arrow next to **ACDSee PicaView**.

Size

Select the size of the preview that displays when you right-click.

Show Original

Select **Show Original** to display the pre-edited version of the image when you right-click.

Show EXIF Information

Check or uncheck the **Show EXIF Information** checkbox to display the right-clicked photo's EXIF information.

Using ACDSee Quick View

ACDSee Quick View is an image viewer that you can use to quickly view images without opening ACDSee. For example, imagine that you want to view an image that someone sent to you in an email. If you double-click the image it will open in Quick View, which is like a pared-down version of View mode in ACDSee.

With Quick View you can quickly scroll through your images, temporarily rotate images, and zoom in and out. If you are viewing a particularly appealing image in Quick View, you can also set the image as your desktop wallpaper or print the image.








You can easily switch from Quick View to ACDSee. You also have the option to open an image in Manage, Media, View, or Edit mode.

If you are accustomed to using keyboard and mouse shortcuts in View mode you can use most of those shortcuts in Quick View as well.

To Open an Image in Quick View:

1. With ACDSee Home closed, double-click an image. For example, double-click the image in Windows Explorer or in an email message.
2. Use the viewing options described below to view the image.

ACDSee Quick View Viewing Options

	Previous	View the previous image.
	Next	View the next image.
	Rotate Left	Rotate the image to the left.
	Rotate Right	Rotate the image to the right.
	Zoom In	View the image at a higher magnification.
	Zoom Out	View the image at a lower magnification.
	Delete	Move the image to the computer's Recycle Bin.



You can close ACDSee by pressing **Esc**.

To Open the Image in ACDSee:

Click **Manage**, **Media**, **View**, or **Edit** mode.

To Set an Image as Your Desktop Wallpaper:

1. Click **Previous** or **Next** until the image that you want to make your desktop wallpaper displays in Quick View.
2. Click **Tools | Set Wallpaper** and select one of the following:
 - **Centered**: displays the image in the center of the desktop.
 - **Tiled**: displays the image in one or more tiles until the desktop is covered. If the image is small it may appear in several tiles on the desktop. If the image is large it may appear in only one or two tiles.
 - **Stretched**: stretches the image proportionally to fill as much of the desktop as possible.

To Restore Your System to the Default Desktop Wallpaper:

Click **Tools | Set Wallpaper | Restore**.

To Print the Image:

1. Click **File | Print**.
2. Under **Format**, choose a print size.
3. On the **Printer Options** tab, [specify the printer](#) you want to use, the paper size, the number of copies you want, the range of pages that you want to print, and image resolution.
4. On the **Page Settings** tab, [specify the image position](#) on the paper and the margin widths, and specify the number of prints of each photo.
5. Add [captions, headers, or footers](#).
6. Click **Print**.

Using Windows Touch Gestures™ with Quick View

If you have a Windows Touch Gestures™-enabled device, you can use it with ACDSee Quick View for quick, easy viewing of photos.

To Use Windows Touch Gestures™ with Quick View:

Open an image in ACDSee Quick View.

- Swipe on the image to scroll through images one at a time.
- Hold and swipe slowly in one direction to go through all of the images in the folder.
- Hold down on an image, and then let go to achieve the same results as right-clicking with a mouse.
- Double-tap the image to launch it in ACDSee.
- Move two fingers apart to zoom in, and toward each other to zoom out.
- After zooming in, you can pan the image with your finger. To return, choose **View | Zoom | Fit Image**.

Chapter 10: Options and Configuration

Setting the General Options

You can adjust settings in the Options dialog box to display helpful tips, set the format for date displays, set automatic rotate options, and control the display of certain image types.

To Access the General Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **General**.
3. On the General page, set or change any of the options described below.
4. Click **OK** to apply your changes and return to ACDSee.

General Options

Enable gamma correction	Applies the specified amount of gamma correction when viewing or previewing images.
Automatically stretch wallpaper to fit screen	Stretches small images to fit the entire desktop when you set them as your wallpaper.
Disable image animation	Displays only the first frame of an animated image in Manage mode's Preview pane and in View mode.
Automatically rotate JPEG and TIFF images based on EXIF orientation	Automatically corrects the orientation of TIFF and JPEG images (based on their EXIF data) when displayed in ACDSee.
Status bar date	Specifies the date to display in the status bar for a selected file.
Date/Time output format	Select one of the following: <ul style="list-style-type: none"> • Default system format: uses the default system format when displaying the date and time in information overlays. • Custom format: uses the specified format to display the date and time in all information overlays. Select a format for both Date and Time from the drop-down lists.
Show icon in Taskbar Notification area	Displays the ACDSee Home icon in the Taskbar Notification area.
Show the Mode Switching icons	Displays the icons next to the names of each mode.


Setting the Auto Advance Options

You can control which applied metadata will trigger [Auto Advance](#).

To Adjust the Auto Advance Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **General | Auto Advance**.
3. On the Auto Advance page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

Auto Advance Options


Enable Auto Advance in	<ul style="list-style-type: none">• Manage Mode• View Mode	Deselect to turn off Auto Advance in either Manage or View mode.
Auto Advance when applying/clearing	<ul style="list-style-type: none">• Tags• Ratings• Labels• Categories• Keywords	Specifies which applied or removed metadata will trigger Auto Advance.  Keywords and Categories are disabled by default.

Setting the Mode Configuration Options

You can control the appearance of the mode buttons to maximize viewing space.

To Set the Mode Button Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **Mode Configuration**.
3. On the Mode Configuration page, hide modes by unchecking their corresponding checkboxes.

 **You cannot hide Manage mode.**
4. Use the modes' corresponding drop-down menus to set them to display icons and labels, labels only, or icons only.
5. Click **Condense the appearance of the mode buttons** to conserve space with smaller mode buttons.
6. Click **OK**.

Setting the Batch Operation Options

You can control which error logs appear for batch operations including batch rename, batch resize, and batch convert.

To Adjust the Batch Operation Options:

1. In any mode, click **Tools | Options...** or press **Alt + O**.
2. In the Options dialog box, click **General | Batch Operations**.
3. On the Batch Operations page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

Batch Operations Options

Don't show results for AI Super-Resolution Check the box to prevent results from being output when AI Super-Resolution completes.

Don't show results for Batch Rename Check the box to prevent results from being output when Batch Rename completes.

Setting the Batch AI Super-Resolution Options

You can enhance multiple images at once using the batch AI Super-Resolution tool.

To Enhance Multiple Images:

1. In Manage mode, select one or more images, and then click **Tools | Batch | AI Super-Resolution | AI Super-Resolution...**, or press **Shift + S**.
2. In the Batch AI Super-Resolution dialog box, you can choose from multiple ways to enhance your images. Choose either Percentage, Size in Pixels, Print Size, Long Edge, or Short Edge. Follow the directions in the table below.
3. Click **Options** to specify how you want to save and store the images.
4. Click **Enhance**.



You can save your enhance settings as a preset by clicking the save icon beside the preset drop-down. From there, enter a name and press **OK**. To delete a preset, press the trash icon.



You can assign shortcuts to speed up your process of enhancing multiple images by following the directions in the [Customizing Keyboard Shortcuts](#) topic.

Resizing Options

Resize Method	Setting	Explanation
Percentage		
	Width	Enter a new width for the images as a percentage of the original image.
	Height	Enter a new height for the images as a percentage of the original image.
	Preserve original aspect ratio	Check this box to keep the width-to-height ratio of the original images.
Size in Pixels		
	Width	Enter a new width for the images in pixels.
	Height	Enter a new height for the images in pixels.
	Preserve original aspect ratio	Check this box to keep the width-to-height ratio of the original images.
	Fit within	Specifies whether the aspect ratio is maintained based on the specified width. For more information about how the different combinations affect the images, see Pixel resize options and resulting action .
Print Size		
	Width	Enter a new width for the images in pixels.
	Units	Choose from inches, cm (centimeters), mm (millimeters), or pixels.
	Height	Enter a new height for the images in pixels.
	Resolution	Enter a resolution for the images in pixels per inch.
	Preserve original aspect ratio	Check this box to keep the width-to-height ratio of the original images.
	Fit within	Specifies whether the aspect ratio is maintained based on the specified width. For more information about how the different combinations affect the images, see Pixel resize options and resulting action .
Long Edge		
	Size	Enter a size in units, and choose the units from the

Resize Method	Setting	Explanation
Short Edge		drop-down menu. There, you can choose from inches, cm (centimeters), mm (millimeters), or pixels.
	Resolution	Enter a resolution for the images in pixels per inch.
	Size	Enter a size in units, and choose the units from the drop-down menu. There, you can choose from inches, cm (centimeters), mm (millimeters), or pixels.
	Resolution	Enter a resolution for the images in pixels per inch.
Options		
	Output Location	<p>Choose an output location from the options:</p> <ul style="list-style-type: none"> • Same as source folder: pastes the enhanced files in the folder they originated. • Specific folder: use the folder icon to navigate to a specific folder for the output files. • Create subfolder: with an output location selected, check this checkbox to create a subfolder for your enhanced images. Enter a name in the box. This is useful if you are making multiple batch resizes to specific dimensions. You can save your enhanced files in separate folders.
	File options	<p>Overwrite Existing Files: Sets the default action when overwriting files.</p> <ul style="list-style-type: none"> • Ask: Asks for confirmation before overwriting any files. • Skip: Skips any files that would be overwritten. • Rename: Prompts a renaming dialogue for the new file when output is complete. • Replace: Replaces the original file with the

Resize Method	Setting	Explanation
		new enhanced one.
		Preserve last-modified dates: Toggles whether the last-modified dates are saved into the enhanced file output.
		Preserve metadata: Toggles whether metadata is saved into the enhanced file output.
		Preserve database information: Toggles whether database information is saved into the enhanced file output.

Setting the Manage Mode Options

You can use the Options dialog box to set various options for Manage mode, including the default start folder.

To Set Manage Mode Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **Manage Mode**.
3. On the Manage mode page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

Manage Mode Options

Startup Behavior

On Startup

Opens Manage mode on launch with one of four startup behaviors: **Open ACDSee Home Page**, **Open Start Folder**, **Reopen Last Active Tab**, or **Reopen All Previous Tabs**.

Start Folder

Designates where new tabs will open. Click the **Browse** button to locate a starting folder on your hard drive. If **Open Start Folder** is selected for **On Startup**, always opens Manage mode to the specified start folder on startup.

Display theme

Specifies the color scheme to use in ACDSee.

Clear path history on exit

Clears the list of recently-accessed folders whenever you exit ACDSee.

Show full path in title bar

Displays the full path of an image in the ACDSee title bar.

Show database filename in title bar

Displays the name of the database that ACDSee is currently running in the title bar.

Folder Tree

Display Density

Sets how condensed the Folder tree appears.

Use plus signs to expand folder tree

Displays plus signs next to items on the Folder tree that can be expanded.

Error Reporting

Select this option if you do not want to see a system error report if there is an error in ACDSee.

Scanning Destination

Click the **Browse For Folder** button to specify the destination for your scanned images.

Setting the ACDSee Home Page Options

You can adjust settings in the ACDSee Home Page Options dialog to control how **Recently Modified** and **Recently Added** searches work in your database.

To Access the ACDSee Home Page Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **ACDSee Home Page**.
3. On the ACDSee Home Page Options page, set or change any of the options described below.
4. Click **OK** to apply your changes and return to ACDSee.

ACDSee Home Page Options

Recently Modified in the Last:

Select a time frame to display **Recently Modified** files.

Options include:

- 1 day
- 3 days
- 1 week
- 2 weeks
- 1 month
- 3 months
- 6 months
- 1 year

Recently Added in the Last:

Select a time frame to display **Recently Added** files.

Options include:

- 1 day
- 3 days
- 1 week
- 2 weeks
- 1 month
- 3 months
- 6 months
- 1 year

Search by:

Specify how **Recently Added** searches are calculated.

Options include:

- Date Taken: Uses the EXIF *Date/Time Original*, or the *Windows Date Created* for files that don't have EXIF *Date/Time Original*.
- Date Added to Database: Uses the *ACDSee Imported Date*.

Setting the Quick Search Options

You can use the Quick Search options to refine your search.

To Set Quick Search Options:

1. In **Manage** mode, click **Tools | Options...**
2. In the Options dialog box, click **Manage Mode | Quick Search**.
3. On the Quick Search page, set or change any of the Quick Search options described below.
4. Click **OK** to apply your changes and return to ACDSee.

Search Fields	Description
Include file names	Searches for file and folder names that begin with the search term.
Include ACDSee Metadata and IPTC fields	Searches for ACDSee Metadata fields such as Caption, Author, Notes, and Color Labels, in addition to IPTC fields such as Title, Headline, Description, People, Keywords, Creator, City, Location, State/Province, Country, and Instructions.
Include ACDSee Categories	Searches for ACDSee Categories that match the search term, and returns any files assigned to those categories. Subcategories are not included.
Include ACDSee Keywords	Searches for ACDSee Keywords that match the search term, including subkeywords.
Include people	Searches for people detected in images and named using Face Detection in View mode.
Search for People	Description
Assigned names	When you search using the Quick Search bar, ACDSee will return photos with names assigned using Face Detection.
Suggested names:	When you search using the Quick Search bar, ACDSee will return photos with names suggested by ACDSee, (but not confirmed by you).
Both assigned and suggested names:	When you search using the Quick Search bar, ACDSee will return photos with both assigned and suggested names.
Search Results	Description
Return contents of folders	Checks the search results for folders and adds folders' contents to the results when selected.



You must select at least one search field to save changes to these options.

Setting the Face Detection and Recognition Options

You can toggle Face Detection on and off, trigger Face Detection to rerun, or allow the ACDSee Indexer to undertake Face Detection while your computer is idle.

To Set the Face Detection Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **Face Detection**.
3. On the Face Detection page, set or change the options as described below.
4. Click **OK**.

Face Detection Options

Face Detection

Enable Face Detection

Toggle this option to turn on Face Detection. With this option enabled, Face Detection will run on files encountered during browsing in Manage mode. In View mode, Face Detection will run on the open image only.

Once Face Detection has been run on an image, that information is stored in the database. Therefore, with this option disabled, previously detected faces will still display face outlines and names (if named) in View mode. You will also be able to search using the names you have assigned to faces.

Allow Face Detection to detect faces while your computer is idle using the ACDSee Indexer.

You can enable Face Detection to be undertaken by the [ACDSee Indexer](#). The ACDSee Indexer will allow the Face Detection process to be done when your computer is idle and ACDSee is not running. This allows you to avoid having to browse all of your folders.

While browsing, automatically rerun Face Detection on images that have changed since Face Detection last ran.

Toggle this option to allow Face Detection to be rerun automatically on images that have changed since the last time Face Detection was run while you browse or edit your images.

Facial Recognition

Enable Facial Recognition

Toggle this option to turn on Facial Recognition. With this option enabled, ACDSee will attempt to recognize individuals based on the faces you have named in previous images.

Use the slider to set how similar two faces need to be in order for ACDSee to identify them as the same individual.

Moderate: the default setting is optimized to name most faces without adding too many incorrect names.

Aggressive: faces need to be less similar in order to be recognized. This option is useful if your photo collection consists of just a few people in a wide variety of poses, lighting, and film quality. You may experience more incorrect names.

Conservative: faces need to be more similar in order to be recognized. This option is useful if your photo collection consists of a large number of different people, especially if those people are physically similar, such as close family members. You will experience fewer incorrect names, but may have to manually name people more frequently.



If the Enable Auto Naming option is enabled, all three settings can result in incorrect names, especially when Facial Recognition encounters a person for the first time. If you experience more incorrect names than you can reasonably correct by hand, disable Facial Recognition and manually name several faces for each person in your photo collection. Then, re-enable Facial Recognition, and, if necessary, rerun Facial Recognition [on a selection of files](#), or your entire library.

Enable Auto Naming

Toggle this option to turn on or off **Auto Naming**.

Disabled: When disabled, Photo Studio will not automatically assign names to faces, giving you full control over naming. Face Detection will provide suggestions based on faces that you've already named.

Enabled: When enabled, Photo Studio will automatically assign names to faces based on faces that you've already named.

Remove All Face Data

Removes all data related to Face Detection and Recognition from the database, including face outlines, names, and information relating to whether Face Detection has been run on files. This action will require ACDSee to restart.

Rerun Recognition

In order to correct names mistakenly assigned to faces by ACDSee, you can rerun facial recognition on faces you have not manually named. This clears all names assigned by ACDSee's facial recognition, but leaves manually entered names. ACDSee will then attempt to recognize unnamed faces based on names you have entered manually.



Faces can only be auto named if the [Enable Auto Naming](#) option is enabled.

Setting the File List Pane Options

You can use the Options dialog box to set options for the File List pane to suit your preferences, such as grouping archive files with subfolders, or highlighting image types with different background colors. You can also customize your thumbnails, the file types ACDSee Home displays, and adjust how ACDSee Home handles files and thumbnails in the File List pane.

To Adjust the File List Pane Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **File List**.
3. On the File List page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

File List Options

File List

Automatically select new files	Automatically selects new files when they are added to the folder displayed in the File List pane.
Group archives with folders	Treats archive files as folders when sorting items in the File List pane.
Use embedded thumbnails	Displays the RAW files embedded thumbnail if the RAW file has them.
Generate high quality thumbnails	Creates a high-quality thumbnail of the RAW file in the background while the embedded thumbnail is displayed, then replaces the poorer quality thumbnail once it is ready.
Show thumbnails on folders	Displays thumbnails of a folder's contents on the folder icon in the File List pane.
Remember each folder's sort settings	Select this option if you want ACDSee Home to remember the sort settings that you used in specific folders.
<Ctrl> key activates hot-tracking	Activates hot-tracking when holding the Ctrl key. Hot-tracking means that when you hold down Ctrl and hover over an image in Manage mode, the contents of the Preview and Properties panes will update, without you having to click on each individual image.
Use animations	Activates or deactivates animation for some features as they close or open. For example, group headers.

Configure Filters

Show all files	Shows image files, folders, media files and archive files in the File List.
Apply filtering criteria	Shows any of the following that you select, and hides any that are not selected. <ul style="list-style-type: none"> • Show image files • Show folders • Show media files

	<ul style="list-style-type: none">• Show archive files
Show hidden files and folders	Shows system and other files and that are normally hidden for safety.
Show THM files	Shows Canon THM files in the File List.
Show XMP files	Shows XMP sidecar files in the File List.
Highlight image files	
Don't highlight image files	Does not highlight image files in Details and Thumbs+Details views.
Use a single color to highlight image files	Uses a single color to highlight all image file types in Details and Thumbs+Details views.
Use multiple colors to highlight image files	Uses a different color to highlight each image type in Details and Thumbs+Details views.
Pop-ups	
Mouse cursor hover activates pop-ups	<p>Activates or deactivates the animated pop-up preview that displays when you hover over thumbnails in the File List.</p> <p>Settings below allow you to include text and/or an image in the pop-up, or if you turn this option off, to activate the pop-up only when you hold down the Shift key.</p>
<Shift> key activates pop-ups	Activates the pop-up only if you hold down the Shift key while hovering over a thumbnail in the File List. You can turn this option off if it interferes with Shift selection.
Auto hide pop-ups	Hides pop-ups after 5 seconds, even if you are still hovering over the image.
Show thumbnail in pop-ups	Shows a pop-up preview of images in the File List when you hover over them with a mouse.
Show information in pop-ups	Includes text file information in the mouse-over pop-up. You can select the information to display by clicking the Configure file information... button and selecting your desired pop-up information.

Configure file information

Opens the Choose Pop-up Information dialog where you can select what information to display in the pop-up when you hover over a thumbnail in the File List. The default is file name, location, size, modified date, and image dimension, but you can select other ACDSee Metadata, EXIF, file, image, IPTC, or multimedia attributes.

Show the Windows Explorer shell context menu as the default right-click menu

Displays the default Windows Explorer context menu instead of the ACDSee Home context menu.

Setting the Thumbnail Info Options

You can use the Options dialog box to change the information that displays with thumbnails of images in the File List pane. These options are set under **File List | Thumbnail Info**.

To Adjust the Thumbnail Info Options:

1. In Manage mode, click **Tools | Options...**
2. In the Options dialog box, click **File List | Thumbnail Info**.
3. On the Thumbnail Info page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

Thumbnail Info Options

Information

File name	Displays the name of each file on the thumbnail in the File List pane.
Choose Thumbnail Info	Opens a dialog box where you can select the information to display on each thumbnail in the File List pane.
Choose Tiles Info	Opens a dialog box where you can select the information to display on each tile in Tiles view mode.
Show unrated, untagged, and unlabeled overlay icons on hover	Shows unrated, untagged, and unlabeled overlay icons when you hover over them.

Overlay icons

To view the overlay icons, go to [Browsing Files in the File List Pane](#).

Rating	Displays a rating overlay icon on thumbnails if the file has been rated in the ACDSee Home database.
Embed Pending	Displays a database overlay icon on the thumbnails of files that have had metadata information added and stored in the ACDSee Home database, but have not yet been written to the files. This icon indicates that a file and the database are out of sync.
Icon	Displays a file format overlay icon on thumbnails in the File List pane.
Category	Displays a category overlay icon on thumbnails if the file has been categorized.
Collection	Displays a collection overlay icon on thumbnails if the file has been added to a collection.
Shortcut	Displays a shortcut overlay icon on thumbnails if the item is a shortcut to another file.
Offline	Displays an offline overlay icon on thumbnails if the file is stored on an offline device.
Excluded items	Displays an excluded file icon on thumbnails if the file is excluded from the ACDSee Home database.
Tagged items	Displays a tagging overlay icon on thumbnails. If the file is tagged, a checkmark displays in the icon.
Auto-rotate	Displays an auto-rotate overlay icon on thumbnails if the

	file was automatically rotated.
Edited	Displays an Edit overlay icon on thumbnails if the file has been edited.
Geotagged	Displays a marker overlay icon on thumbnails if the file has been pinned on the map.
Label	Displays a color label overlay icon on thumbnails if the file has been labeled.

Setting the Thumbnail Style Options

You can use the Options dialog box to change how the thumbnails of images display in the File List pane. These options are set under **File List | Thumbnail Style**.

To Adjust the Thumbnail Style Options:

1. In Manage mode, click **Tools | Options...**
2. In the Options dialog box, click **File List | Thumbnail Style**.
3. On the Thumbnail Style page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

Thumbnail Style Options

Thumbnail frame

Show drop shadow	Shows thumbnails with a 3D drop shadow.
Show slide background	Displays a shaded background behind the thumbnail and its information.

Folder style

XP style folder	Displays folders as an XP-style image.
3D style folder	Displays folders as a 3D folder with transparency.

Thumbnail ratio

Custom	Specifies a custom height-to-width ratio for the shape of the thumbnails in the File List pane. Drag the slider under the preview to set the ratio. The preview shows you the shape as you move the slider.
Portrait	Specifies a standard 3:4 portrait ratio for the shape of the thumbnails in the File List pane.
Landscape	Specifies a standard 4:3 landscape ratio for the shape of the thumbnails in the File List pane.

Thumbnail spacing

Slider	Increases or decreases the space between each thumbnail.
---------------	--

High-quality scaling

Uses high-quality thumbnail scaling in the File List pane.

Setting the Details View Options

You can use the Options dialog box to change how thumbnails display in the File List pane.

To Adjust the Details View Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **File List | Details View**.
3. On the Details View page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

Details View Options

Show grid lines	Separates each row and column in Details view mode with a grid line.
Full row select	Selects the entire row when you click a column entry in that row.
Column auto-width	Automatically resizes each column to fit its contents.
Highlight sort column	Highlights the column used to sort files when you click on the column's title.
Choose Details	Specifies the columns you want to use to sort files in Details view mode.

Setting the Preview Pane Options

You can specify how ACDSee Home displays previews of your images, and configure settings to play audio and video files automatically, as soon as you view them in the Preview pane.

To Set the Preview Options:

1. Do one of the following:
 - In Manage mode, click **Tools | Options | Preview...**
 - In Manage mode, right-click in the Preview pane and select **Preview Options**.
2. On the Preview options page, set or change the options as described below.
3. Click **OK** to apply your changes and return to ACDSee.

Preview Options

Delay	Specifies how quickly the Preview pane displays an image after you select it in the File List pane.
Size	Specifies the size of the previewed image in relation to the selected image.
Preview audio and video clips	Previews media files as you select them in the File List pane.
Autoplay audio and video clips	Automatically starts playing audio and video files in the Preview pane.
Instant image preview	Displays an instant preview that improves in quality as the image is decoded.
Image and Information	<p>Select one of the following:</p> <ul style="list-style-type: none"> • Show image: displays a preview of the selected image in the Preview pane. • Show information: displays information about the selected image in the Preview pane.
Choose Preview Info	Specifies the type of information you want to display in the Preview pane. For more information, see Previewing Images .

Setting the Folders Pane Options

You can customize the Folders pane by showing or hiding the Easy-Select bar, displaying archives, and identifying excluded folders.

To Customize the Folders Pane:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **Folders**.
3. On the Folders page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

Folders Pane Options

Easy-Select

Show Easy-Select	Displays the Easy-Select bar in the Folders pane, which you can use to select multiple folders.
Enable Easy-Select tooltip	Displays a tool-tip when you place your cursor over the Easy-Select bar.

Folder display

Show archives in Folder Pane	Lists archive files in the Folders pane.
Confirm drag & drop move within folder views	Prompts you for confirmation of folder movements within the Folders pane.
Show overlay for excluded folders	Displays an overlay icon on folders that are excluded from the ACDSee Home database.

Setting the Catalog Pane Options

You can customize the Catalog pane to specify which confirmations you want to be prompted for while working with categories, and choose whether to show the Easy-Select bar.

To Set the Catalog Pane Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **Catalog**.
3. On the Catalog page, set or change the options as described below.
4. Click **OK**.

Catalog Options

Category deletion

Confirm if category has assigned files	Prompts you for confirmation when deleting a category with assigned files.
Confirm if category has sub-categories	Prompts you for confirmation when deleting a category containing sub-categories.

File removal

Confirm file removal from category	Prompts you for confirmation when un-assigning files from a category.
---	---

Easy select

Show Easy-Select	Displays an Easy-Select bar in the Catalog pane, which you can use to select multiple categories, special items, and ratings.
Enable Easy-Select tooltip	Displays a tool-tip when you place your cursor over the Easy-Select bar.

Icons

Show icons for categories, ratings, color labels, and special items	Displays icons so you can easily identify categories, ratings, color labels, and special items.
Enable setting categories, keywords, ratings, and color labels	Allows you to set categories, ratings, and color labels in the Catalog pane.

Setting the Calendar Pane Options

You can customize the ACDSee Home Calendar to start each week on a specific day, to use a 12 or 24-hour clock format, and to use one of four date types when sorting files.

To Set the Calendar Pane Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **Calendar**.
3. On the Calendar page, set or change any of the options described below.
4. Click **OK** to accept your changes and return to ACDSee.

Calendar Pane Options

Date types

Database date	Sorts files in the Calendar pane based on the date stored in the ACDSee Home database .
Date taken	Sorts files in the Calendar pane based on the EXIF date of each item.
File modified date	Sorts files in the Calendar pane based on the last-modified date of each item.
File created date	Sorts files in the Calendar pane based on the date each file was created on your computer.

Filters

Apply Advanced File List Filters (excluding folders)	Filters the items displayed in the Calendar pane based on the current File List pane filter settings .
Show image and media files only	Displays only image, audio, and video files in the Calendar pane.

Start of week

Specifies the first day of each week in the Calendar pane.

Clock formats

12 hour	Uses a 12-hour clock in the Calendar pane.
24 hour	Uses a 24-hour clock in the Calendar pane.

Setting the CD/DVD Management Options

You can use the Options dialog box to set the preferred method for identifying Photo Discs.

To Change the Photo Disc Identification Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **CD/DVD Management**.
3. On the CD/DVD Management page, set or change any of the options described below.
4. Click **OK** to apply your changes and return to ACDSee.

CD/DVD Management Options

Photo Disc Identification

Use disc volume label	Attempts to identify a Photo Disc by its volume label. This setting is recommended if you are working with multi-session Photo Discs.
Use disc serial number	Attempts to identify a Photo Disc by its serial number. This setting is preferred when working with single-session Photo Discs, or importing or converting Photo Discs from a previous version of ACDSee.

Setting the Properties Pane Options

You can use the Options dialog box to customize the information available on the Metadata tab in the Properties pane.

To Customize the Metadata Tab in the Properties Pane:

1. In Manage mode, click **Tools | Options...**
2. In the Options dialog box, click **Properties Pane**.
3. On the Properties Pane page, hide the Tagged, Rating, and Color Labels, by unchecking the corresponding checkbox.
4. Hide the Categories by unchecking the checkbox.
5. Click **Manage Metadata Views** to open the Choose Metadata to Display dialog box.
6. Click the plus signs to expand the tree and select your preferences.
7. Click **OK**.
8. Click **OK** to apply your changes and return to ACDSee.



You can also click the Metadata View drop-down list in the Properties pane Metadata tab and select **Manage Metadata Views**.

Setting the File Management Options

You can specify how ACDSee Home handles renaming and deleting files and folders, and whether ACDSee Home sends deleted files to the desktop Recycle Bin by default.

To Set the File Management Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **File Management**.

3. On the File Management page, set or change any of the options as described below.
4. Click **OK** to accept your changes and return to ACDSee.

File Management Options

Confirmations

You can use the following options to display confirmation dialogs upon folder or file deletion.

In order for the settings in this dialog to take effect, you must enable them in your Recycle Bin Properties settings.

- **Enabled:** A confirmation prompt will be displayed if the Recycle Bin setting "Display delete confirmation dialog" is enabled.
- **Disabled:** No confirmation prompt will be displayed regardless of the Recycle Bin setting.

Overwriting duplicate files

Ask	Prompts you for confirmation when overwriting duplicate files.
Rename	Automatically resolves any naming conflicts when moving or copying files by renaming the source files. In the Separator character field, type a character to use to separate file names in the automatic renaming system.
Replace	Automatically overwrites files in the target folder without prompting for confirmation.
Skip	Does not move, copy, or overwrite any files that result in naming conflicts.

Save Originals

Saves a copy of the original file when it is edited using one of the batch editing tools. This makes it possible to restore the original file later. Turning this option off means that originals are not saved during batch editing, and so cannot be restored.

In Edit mode, a copy of the original file is always saved, whether or not this option is selected.

Other

Click to edit file name	Specifies that file names can be edited by clicking the file name in the File List pane.
Use Recycle Bin	Sends files to the Desktop Recycle Bin. If not selected, deleted files are permanently removed from your hard drive.
Preserve database information when files are copied	Copies database information with files when you copy them to another location.



Control confirmations for folder delete, file delete, and read-only rename and delete actions in your operating system settings.

Setting the Database Options

You can adjust settings in the Options dialog box to display reminders, control database information, and specify a location on your hard drive where you want to store your database files and cached thumbnails.

To Set the Database Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog, click **Database**.
3. On the Database page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

Database Options

Database file

Displays the location on your hard drive where the ACDSee Home [database](#) is stored.

Display backup reminder

Automatically reminds you to back up your ACDSee Home database. Click the **Every** drop-down list and select how often you would like to be reminded.

Manage excluded folders

Opens the Excluded Folders List dialog box, where you can specify which folders you want to exclude from the ACDSee Home database.

Set database date to EXIF date

Automatically adds the EXIF date to the ACDSee Home database when you catalog the contents of a folder.



Note: if the database date is changed, the [Embed Pending](#) icon does not show up.

Metadata**Import EXIF and IPTC metadata from cataloged files**

Automatically imports EXIF and IPTC information into the ACDSee Home database whenever you catalog the contents of a folder.

If this option is not selected, ACDSee Home does not import the EXIF and IPTC information, but does set aside space within the database records. To remove the empty records, be sure to [optimize your database](#) frequently.

Set "Embed Pending" when tagging files

Displays a database overlay icon on thumbnails if the file has been tagged, but this metadata has not yet been written to the file. This icon indicates that the file and the database are out of sync. When this option is disabled, tagged images will not show up under Embed Pending in the Special Items section of the Catalog pane.

IPTC conflicts**Show separator conflict dialog for IPTC keywords**

Displays the IPTC Keywords dialog box when a separator conflict occurs. You can specify a method of handling conflicts within the dialog and select not to display it again. Select this option to change or adjust those settings the next time a separator conflict occurs.

Show separator conflict dialog for IPTC

Displays the IPTC Supplemental Categories dialog box when a separator conflict occurs. You can specify a method of handling conflicts within the dialog and elect not to display it again. Select this option to change or adjust those settings the next time a separator conflict occurs.

Setting the Media Options

You can change what application handles your audio and video files when launched from ACDSee.

To Customize the Default Media Player for Files Launched from ACDSee:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **Media**.
3. To launch audio and video files in your system's default media player, check the **Use default media player to open audio and video files** checkbox.
4. Click **OK** to apply your changes.

Setting the Embed ACDSee Metadata Options

You can adjust settings in the Options dialog box to set options for auto-embedding ACDSee Metadata, choosing what metadata is embedded, how files and drives interact with it, and prompt settings.

To Set the Embed ACDSee Metadata Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog, click **Embed ACDSee Metadata**.
3. On the Embed ACDSee Metadata page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

Embed ACDSee Metadata Options

Auto-Embed ACDSee Metadata

- Do not auto embed metadata: [Set by Default] Selecting this will disable auto-embedding of ACDSee Metadata.
- Embed metadata on shutdown: Selecting this will embed pending ACDSee Metadata on program shutdown.
- Display embed reminder every: Selecting this will embed pending ACDSee Metadata on the day selected in the dropdown.

Choose Metadata to Embed

- Embed ACDSee Metadata: Selecting this allows ACDSee Metadata to be embedded to images.
 - Embed Categories into IPTC: Selecting this will allow ACDSee to automatically embed categories into IPTC when embedding metadata.
 - Embed Keywords into IPTC: Selecting this will allow ACDSee to automatically embed keywords into IPTC when embedding metadata.
- IPTC Write Behavior: When selecting to embed **Keywords** or **Categories** into **IPTC metadata**, you can choose how the data is saved alongside previously saved metadata.
 - Merge: **Keywords** or **Categories** will be added to any existing **IPTC Keywords** and/or **IPTC Supplemental Categories**.
 - Overwrite: **Keywords** or **Categories** will replace any existing **IPTC Keywords** and/or **IPTC Supplemental Categories**.
- Embed ACDSee Face Data: Selecting this will allow ACDSee to automatically embed pending Face Data to images when embedding metadata.

Files and Drives

- Write sidecar files for formats that do not support embedded XMP: Selecting this will create sidecar files for formats that do not support directly embedded XMP.
- Download and include online OneDrive files: Selecting this will include files from connected OneDrives.
- Include files on network drives: Selecting this will include files on connected network drives.

Prompts

- Do not prompt when embedding ACDSee Metadata: While selected, the initial prompt before embedding ACDSee Metadata will not be displayed.
 - Do not show the summary page after embedding metadata: While selected, the summary page will not
-

appear after embedding ACDSee Metadata.

Setting the View Mode Options

You can use the Options dialog box to adjust the behavior of View mode to suit your preferences, and increase the speed with which images are displayed.

To Set the View Mode Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **View Mode**.
3. On the View mode options page, set or change any of the View mode options described below.
4. Click **OK** to accept your changes and return to ACDSee.

View Mode Options

Decoding and caching**Decode next image in advance**

Automatically decodes the next image in sequence in View mode, resulting in shorter load times.

Keep previous image in memory

Keeps the previously decoded image in memory for quick display in View mode.

Startup files**Replace images in list**

Does not open a new View mode window if an image is opened from another application.

Images in new window

Opens a new View mode window to display images opened from another application.

Dropped files**Replace images in list**

Replaces the list of images open in View mode with images dropped into View mode from another application.

Add images to list

Adds any images dropped into View mode by another application to the list of images already open.

Always on top

Keeps the ACDSee Home window as the top window in a stack of windows.

Full-screen

Opens images in View mode in full-screen mode. (Press **F** to exit full-screen mode.)

Hide mouse cursor in full-screen

Hides the cursor in full-screen mode.

Instant image preview

Displays an instant preview in View mode that improves in quality as the image is decoded.

Use ACDSee Home Quick View

If selected, ACDSee Home Quick View is set as the default viewer for images when ACDSee Home is closed.

Show pixels when zoomed past 100%

Resampling is not applied to images zoomed past 100%. When the box is unchecked, images zoomed past 100% are resampled to produce smooth transitions, but this may result in excessive blurring.

Always open in selected Auto Lens

On startup, opens images in the Auto Lens last selected prior to closing ACDSee.

Exit after delete/move

Automatically returns to Manage mode after moving or deleting an image in View mode.

View all images in folder

Adds all images in a folder to the current image list when viewing any file from that folder.

Show full image file path

Displays the image's full file path in View mode title and status bars.

Sharpen subsampled images

Automatically sharpens the view for images zoomed in at less than 100%.

Setting the People Mode Options

Select **Tools | Options...** from the main menu to open the **Options** dialog and select "People Mode" from the left-hand list.

The options in the **People Mode** pane include four field sets:

- Confirmation Prompts
- Thumbnail Style
- Folder Pane Style
- Unnamed View Style

Confirmation Prompts Options

Do not prompt when confirming all suggestions	Enable to turn off prompts when confirming all suggestions.
Do not prompt when denying all suggestions	Enable to turn off prompts when denying all suggestions.
Do not prompt when deleting faces	Enable to turn off prompts when deleting faces.

Thumbnail Style Options

Face Thumbnail	Enable to use thumbnails featuring the person's face.
Asset Thumbnail	Enable to use thumbnails featuring the entirety of the asset's original dimensions.

Folder Pane Style Options

List	Enable to use the List view as the default for the Folders pane.
Tree	Enable to use the Tree view as the default for the Folders pane.

Unnamed Style Options

Ungrouped	Enable to use the Ungrouped category as a default for sorting the Unnamed view results.
Grouped	Enable to use the Grouped category as a default for sorting the Unnamed view results.

Pop-ups Options

Mouse cursor hover activates pop-ups	Enable to allow a mouse cursor hover to activate pop-ups.
<Shift> key activates pop-ups	Enable to allow the pressing of the Shift key to activate pop-ups.
Auto hide pop-ups	Enable to auto-hide pop-ups.
Show thumbnail in pop-ups	Enable to show thumbnail images of the original image in the pop-up.
Show information in pop-ups	Enable to show image-related information in the pop-up.
Configure Information...	If the Show information in pop-ups check box is enabled, click the Configure information... button to open the Choose Pop-up Information dialog. Available details can be added or removed from the list of currently displayed details which can also be moved up or down in the list.

Setting the Display Options

You can use the Options dialog box to change the window background and specify how images are zoomed.

To Set the Display Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **Display**.
3. On the Display options page, set or change the options described below.
4. Click **OK** to accept your changes and return to ACDSee.

Display Options

Zoom options

Default zoom mode	Specifies the default zoom level for images in View mode.
Reset zoom mode to default on every image change	Resets the zoom mode to the selected default when the displayed image changes.
Resize	Resizes the image based on the selected option. For more information about how these choices affect the Viewer, see Automatically shrinking or enlarging images .

Pan tool

Enable click-zooming	Deselect to turn off the one click image toggle between Default view and Actual Size view.
----------------------	--

Pan speed

Slow - Fast	Specifies the speed when panning an image.
-------------	--

Background

Default color	Uses the default ACDSee Home color for the background in View and Edit mode.
Custom color	Specifies a color to use as the background in View and Edit mode.
Tiled image	Uses a tiled image as the background for View and Edit mode. Click Browse to locate an image on your hard drive.



The background color and tiled image options do not affect full screen mode.



To change the background color in ACDSee Quick View, [open an image in Quick View](#), and then click **Tools | Options**.

Setting the Edit Mode Options

You can use the Options dialog box to show icons in Edit mode.

To Show Icons in the Edit Pane:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **Edit Mode**.
3. Set the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

Edit	Show icons on filter menu pane	Displays icons next to the tools in Edit.
	AutoSave all changes	Toggles AutoSave on and off. AutoSave saves your changes in Edit mode automatically, without prompting the Save Changes dialog.
	GPU selection	<p>In order to ensure optimum performance, parts of Edit mode run off of your GPU. ACDSee Home automatically chooses the best GPU in your system. This option —Let ACDSee decide— is enabled by default. When Let ACDSee decide is enabled, GPU model text displays next to the option, specifying whether Edit mode is running off of your primary GPU or another, more superior GPU that ACDSee Home has detected. In most cases, the GPU detected and identified as the best by ACDSee Home will be one and the same: your primary GPU.</p> <ul style="list-style-type: none"> • Use primary: you can enable this option if you prefer to use your primary GPU over the GPU ACDSee Home has chosen. • Let ACDSee decide: select this option to enable using the superior GPU found by ACDSee.

Setting the ACDSee 365 Options

You can use the Options dialog box to set options for ACDSee 365, such as the temporary folder location and what to do with uploads and downloads when you close ACDSee.

To Set the ACDSee 365 Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **ACDSee 365**.
3. On the ACDSee 365 page, set or change any of the options described below.
4. Click **OK** to accept your changes and return to ACDSee.

ACDSee 365 Options

Folder locations

Temporary folder

Click the **Browse** button to change the folder where ACDSee Home temporarily keeps files during uploads and downloads.

Uploads/Downloads

On shutdown, always pause all transfers

Pauses all transfers when you close ACDSee.

On startup, always automatically resume all paused transfers

Resumes all transfers when you reopen ACDSee.

Number of concurrent uploads (1-10)

Select the number of files to be uploaded at the same time.

Number of concurrent downloads (1-10)

Select the number of files to be downloaded at the same time.

Ratings

Convert 'Rating 1' to 5 stars

Converts a numeric rating of 1 to five stars.

Convert 'Rating 1' to 1 star

Converts a numeric rating of 1 to one star.

Setting the ACDSee Showroom Options

You can customize the ACDSee Showroom desktop slideshow in a number of ways, including changing the slide duration, order, and transition or changing the frame opacity, size, and frame style.

To Customize the ACDSee Showroom Desktop Slideshow:

1. Start ACDSee Showroom by doing one of the following:
 - In any mode, click **Tools | Create | ACDSee Showroom**.
 - Click **Start | Programs | ACD Systems | ACDSee Showroom**.
2. Right-click anywhere in the ACDSee Showroom window and select **Options**.
3. Set or change the options as described below.
4. Click **Set As Default** to use the currently selected options as the default for new Showroom windows.
5. Click **OK** to apply your changes.

ACDSee Showroom Options

Picture Folder

Include subfolders	Select this option if you want to include photos from subfolders in the slideshow.
Skip hidden folders	Select this option to skip hidden folders such as the [Originals] folders that are created when you process images.

Slide

Duration	Drag the slider to the left to decrease the display time for each photo and to the right to increase the display time for each photo.
Order	From the Order drop-down list select Sequential to display photos in order or Random to display photos randomly.
Transition	From the Transition drop-down list select None if you do not want any special transition effects, Slide if you want photos to enter the window from the right and exit to the left, and Fade if you want to reduce photo opacity during the transition from one photo to another.
Apply to all	Select Apply to all if you want to apply these changes to all slideshows.

Showroom Window

Opacity	Drag the Opacity slider to the left to reduce the opacity of the Showroom window and to the right to increase opacity.
Size	From the Size drop-down list select either a Small , Medium , or Large Showroom window frame.
Frame	From the Frame drop-down list select a frame style.
Always on top	Select Always on top if you want the Showroom window to display on top of all other application windows.
Apply to all	Select Apply to all if you want to apply these changes to all Showroom windows.

Run at startup

Select **Run at startup** if you want to start ACDSee Showroom automatically when you start your computer.

Setting the ACDSee Quick View Options

You can customize ACDSee Quick View in a number of ways, including displaying Quick View on top of any open windows, displaying Quick view at full screen, or even changing the background color in the Quick View window.

To Customize ACDSee Quick View:

1. Double-click on an image. For example, double-click on the image in Windows Explorer or in an email message.
2. Click **Tools | Options...**
3. Set or change the options as described below.
4. Click **OK** to apply your changes.

ACDSee Quick View Options

Use ACDSee Quick View

If selected, ACDSee Quick View is set as the default viewer for images when ACDSee Home is closed.

Enable gamma correction

Applies the specified amount of gamma correction when viewing images.

Disable animation

Displays only the first frame of an animated image.

Always on top

Keeps the Quick View window as the top window in a stack of windows.

Full screen

Opens images in the Quick View window in full screen mode.

Hide mouse cursor in full screen

Hides the cursor in full screen mode.

Default zoom mode

Fit image	Displays the image at the largest magnification that fits in the Quick View window. Images that are smaller than the Quick View window display at their original size.
Actual size	Displays the image at its actual size in the Quick View window.

Background

Default color	Uses the ACDSee Home background color in Quick View.
Custom color	Specifies a color to use as the background in the Quick View window. Click the color swatch to select a different color.

Setting the Media Options

You can change what application handles your audio and video files when launched from ACDSee.

To Customize the Default Media Player for Files Launched from ACDSee:

- 1. In any mode, click **Tools | Options...**
- 2. In the Options dialog box, click **Media**.

3. To launch audio and video files in your system's default media player, check the **Use default media player to open audio and video files** checkbox.
4. Click **OK** to apply your changes.

Setting the ACDSee Indexer Options

You can use the Options dialog to customize the functionality of the ACDSee Indexer.

To Customize the ACDSee Indexer:

1. In any mode, click **Tools | Options...**
2. In the Options dialog box, click **ACDSee Indexer**.
3. On the ACDSee Indexer page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

ACDSee Indexer Options

Auto index folders or images when computer is idle for	Enables the indexing of folders or images while the computer is idle. Set the slider to indicate how long your computer should be idle before indexing begins.
Index image files only	Deselect to index all file types supported by ACDSee.
Current database	Displays which database will be indexed.
Folders to monitor	Displays which folders will be indexed.
Add Folder...	Click the Add Folder... button to add additional folders to be indexed.
Remove Folder	Select a folder from the list and click the Remove Folder button to remove it from the folders to be indexed.
Include Microsoft OneDrive	Enables the indexing of your OneDrive folder.

Setting the ACDSee PicaView Options

You can use the Options dialog box to change your ACDSee PicaView settings, as well as toggling it on and off.

To Adjust the ACDSee PicaView Options:

1. In Manage mode, click **Tools | Options...**
2. In the Options dialog box, click **ACDSee PicaView**.

3. On the ACDSee PicaView page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.

ACDSee Picaview Options

Enable ACDSee Picaview

This checkbox enables or disables ACDSee PicaView. When enabled, ACDSee PicaView appears when an ACDSee-supported file is right-clicked anywhere on your hard drive. You have the option of displaying a preview of the file or image, and its EXIF information, or one or the other.

Display Image

Check the **Display Image** checkbox to display a preview of the right-clicked file.

Location:

- **Add image to main menu:** when you right-click, displays image in the main menu.
- **Add image to sub-menu:** when you right-click, displays image in a sub-menu, available by clicking the arrow next to **ACDSee PicaView**.

Size:

Select the size of the preview that displays when you right-click.

Show Original

Select **Show Original** to display the pre-edited version of the image when you right-click.

Show EXIF Information

Check or uncheck the **Show EXIF Information** checkbox to show or hide the right-clicked photo's EXIF information.

Setting the ACDSee Mobile Sync Options

You can use the Options dialog box to change your ACDSee Mobile Sync settings.

To Set the ACDSee Mobile Sync Options:

1. In any mode, click **Tools | Options...**
2. In the Options dialog, click **ACDSee Mobile Sync**.
3. On the ACDSee Mobile Sync page, set or change the options as described below.
4. Click **OK** to apply your changes and return to ACDSee.


ACDSee Mobile Sync Options

Root Folder	Click the Browse For Folder button to specify the destination for your sent images and videos.
Server Name	To customize the name of the target server (ACDSee on your PC), enter text in the field. This name will appear in your list of targets in the ACDSee Mobile Sync app.
Show ACDSee Mobile Sync Root Folder on Folder Tree	Displays the ACDSee Mobile Sync folder in the Folders pane.

Import Options

Use the Import Options tool to seamlessly migrate settings from the previous version of ACDSee starting with 2022.


The Import Options tool will import all settings in every Options page, with the exception of Mode Configuration.


 If a previous version of ACDSee Photo Studio is installed (beginning with 2022), ACDSee Photo Studio Home 2026 will automatically import your options upon the first time the program is run.

To Use the Import Tool:

While options are imported automatically, there may be times where you need to import your options again. For example, if you were to install a newer version of ACDSee Photo Studio Home 2026 and then went back to a previous version and made a few changes to the settings. Manually importing the options will allow you to bring over your most recent settings, no matter when your software was installed.

1. Click on **Tools | Options...**
2. In the dialog box, click on Import Options under General
3. Click **Import...**
4. Click OK on the confirmation dialog
5. Click OK when prompted to restart ACDSee

 If the previous version of ACDSee has not been launched on this machine the option will not appear.

 The import tool is only available when importing from a previous year and within the same product model. (e.g. ACDSee Photo Studio Home 2026 can only import options from ACDSee Photo Studio Home 2022 or newer.)



The import tool will always import from the most recent previous version that can be found. (e.g. ACDSee Photo Studio Home 2022 and ACDSee Photo Studio Home 2023 are both installed, only the settings from ACDSee Photo Studio Home 2023 will be imported.)



When importing Search options, only the Quick Search options will be affected.

Auto-hiding Panes and Panels

You can use the **Auto Hide** button to automatically hide some panes and panels in ACDSee. When a pane is set to auto-hide, it rolls away when you click outside of it, leaving a tab displayed. You can access the pane by moving the cursor over the tab. When a pane or panel is floating, the auto-hide feature is not available. You cannot move the pane to a new location if it is set to auto-hide.

The Auto Hide button's appearance on the pane's title bar reflects its current setting:

A horizontal pushpin indicates that the pane is set to automatically hide when you click outside of it.

A vertical pushpin indicates that the pane is fixed and will remain visible even if you click outside of it.

To Set or Remove Auto-Hide:

Click the **Auto Hide** button on the title bar so that it displays a slanted or horizontal pushpin.

Using the Task Pane

The Task Pane displays groups of often-used tasks from the menus and toolbars based on your current location and selections in ACDSee. By default, the Task Pane opens on the right side of the Manage mode window.

To Open or Close the Task Pane:

In Manage mode, click **Panes | Task Pane**.

The menus in the Task Pane change depending on what area of the Manage mode window you are working in and what items you select. For example, if you select more than a folder in the File List pane, the Task Pane displays different menus than it does if you select a photo or media file.

The options on the Task Pane menus also change dynamically. For example, if you select multiple images in the File List, the options in the Fix and Enhance Photos menu change to list options that you can use with multiple images.

Customizing Toolbars

You can customize the appearance and organization of toolbars in Manage mode and View mode by selecting which toolbars to display, and specifying each toolbar's buttons or commands. You can also discard your changes and reset the toolbars to their default layout at any time.

Displaying and Hiding Toolbars

You can choose to display or hide the specific toolbars in Manage mode and View mode.

To Display or Hide a Toolbar:

- In Manage or View mode, click **View | Toolbars**, and then select the toolbar you want to display or hide.

Customizing Toolbar Contents

You can customize the following toolbars:

- In Manage mode: the Main toolbar and the File List toolbar.
- In View mode: the Bottom toolbar.

You can add, remove, and rearrange buttons on these toolbars. You can also display or hide text labels and tool tips for the buttons on these toolbars. All toolbar customization options are in the Customize dialog box.

To Display the Customize Dialog Box:

Do one of the following:

- In Manage mode, click **View | Toolbars** and then select **Customize**.
- In Manage mode, click the drop-down arrow, located to the right of the Main toolbar or File List toolbar, select **Add or Remove Buttons**, and then select **Customize**.
- In View mode, click the drop-down arrow, located to the right of the Bottom toolbar, select **Add or Remove Buttons**, and then select **Customize**.

To Add or Remove Toolbar Buttons in Manage Mode:

Main toolbar:

1. Click the drop-down arrow located on the right side of the Main toolbar.
2. Select **Add or Remove Buttons | Main Toolbar**, then select the name of the button you want to add or remove.

File List toolbar:

- With the Customize dialog box open, on the Commands tab, drag items from the Commands field to the toolbar to add buttons.
- To remove buttons, drag them from the toolbar to the Customize dialog box.

To Add or Remove Toolbar Buttons in View Mode:

Bottom toolbar:

1. Click the drop-down arrow, located to the right of the Bottom toolbar.
2. Select **Add or Remove Buttons | Bottom Toolbar**, then select the name of the button you want to add or remove.

To Rearrange Toolbar Buttons:

With the Customize dialog box open, drag buttons to your desired toolbar location.

To Display or Hide Text Labels Below Toolbar Buttons:

1. Display the Customize dialog box.
2. Click the **Toolbars** tab.
3. In Manage mode: select **File List Toolbar** or **Main Toolbar**.
In View mode: select **Bottom Toolbar**.
4. Check the **Show text labels** checkbox to display text labels, or clear the **Show text labels** checkbox to hide text labels.
5. Click **Close**.

To Display or Hide Tool Tips for Toolbar Buttons:

1. Display the Customize dialog box.
2. Click the **Options** tab.
3. Select **Show ScreenTips on toolbars** to display tool-tips, or clear **Show ScreenTips on toolbars** to hide tool-tips. If you select this option, you can also select **Show shortcut keys in ScreenTips** to show keyboard shortcuts in the tool-tips.
4. Click **Close**.

Resetting Toolbars

You can discard all of your changes, and return the toolbars and buttons to their default states.

To Reset the Toolbars:

1. Display the Customize dialog box.
2. Click the **Toolbars** tab, and then click **Reset All**.

3. Click **Yes** to reset the toolbars.
4. Click **Close**.

Customizing Toolbar and Pane Locations

You can hide, resize, float, move, and dock most toolbars and panes to suit your preferences. To learn about all the ways you can customize your experience in Manage mode, see [Using Manage Mode](#).

Hiding Panes

At the top right corner of Manage, View, and Edit mode, you can use the Hide/Unhide buttons to hide and reveal panes on the left, right, or bottom of the screen.

Hide/Unhide Left Panels



Hide/Unhide Bottom Panels



Hide/Unhide Right Panels



Moving Panes and Toolbars in View and Edit Mode

You can move a pane or toolbar from a docked or floating position to a new location.

 **Some toolbars do not activate the Docking Compass.**

To Move a Pane or Toolbar:

1. Drag the pane or toolbar's title bar and hold your cursor over any of the arrows of the Docking Compass.
2. When the shaded marquee displays the position of the pane or toolbar you want, release the mouse button.
3. To return a pane to its previous location, double-click its title bar.

To Move a Docked or Floating Pane or Toolbar:

Do one of the following:

- Drag the pane or toolbar's tab to a new location.
- Drag the pane or toolbar's title bar to a new location.
- If you use dual monitors, you can move the panes and toolbars to your second monitor to free up space on your main monitor.

Docking Panes and Toolbars in View and Edit Mode

When you select a pane or toolbar, the Docking Compass activates to help you place the pane precisely. The Docking Compass consists of an outer and inner ring of arrows. When you hold your cursor over any of the arrows, a shaded marquee displays the potential position of the pane.

 Some toolbars do not activate the Docking Compass.

To Dock a Pane or Toolbar:

Drag the pane or toolbar's title bar or tab to activate the Docking Compass. To dock a pane around the outer edge of the window, hold your cursor over any of the outer arrows of the Docking Compass, and then release the mouse button.

Resizing Panes


You can resize all the panes and toolbars, whether they are docked or floating.

To Resize a Docked Pane:

1. Hold your cursor over the edge of the pane or toolbar until the cursor changes to arrows and lines.
2. Drag the edge of the pane or toolbar to the size you want.

To Resize a Floating Pane:

Hold your cursor over the edge or corner of the pane or toolbar and then drag the pane to the size you want.

 You can enlarge the Filmstrip in View and Edit mode to expedite browsing your folder. To resize the Filmstrip, drag one of its edges.

 You can move the Drawing and Selections Toolbar, as well as the ACDSee Actions bar.

Creating a Custom Menu

You can create a new menu in Manage mode with custom commands for easy access. You can also customize the name and location of your new menu.

To Create a New Menu:

1. Do one of the following:
 - In Manage mode, click **View | Toolbars** and then select **Customize**.
 - In Manage mode, click the drop-down arrow located to the right of the Main toolbar or File List toolbar, select **Add or Remove Buttons**, and then select **Customize**.
2. In the Customize dialog, on the Commands tab, select **New Menu** from the Categories field.
3. In the Commands field, select **New Menu** and drag it to your desired toolbar location.

To Add Commands to a New Menu:

1. In the Customize dialog, on the Commands tab, select any option from the Categories field.
2. In the Commands field, select your command and drag it over to your new menu on the toolbar. The new menu will expand down. Drop the command on the menu.

To Delete a New Menu or Command:

 The Customize dialog must be open to delete a new menu or command.

Right-click the new menu or command and choose **Delete** from the context menu.


To Name a New Menu:

 The Customize dialog must be open to name a new menu.

1. Right-click the new menu and choose **Button Appearance...** from the context menu.
2. In the Button Appearance dialog, with **Text only** selected, enter a name in the Button text field.
3. Press **OK**.

Configuring External Editors

To open images in external editing applications from within ACDSee, configure ACDSee Home to work with a variety of image editors, such as LUXEA Pro Video Editor 7, and specify which image editor ACDSee Home uses by default.

 An external editor must be configured before it can be assigned a shortcut key or used as a button on the toolbar.

To configure an External Editor in ACDSee:

1. In **Manage** mode, select **Tools | External Editors | Configure Editors** from the main menu.
2. In the **Configure Photo Editors** dialog box, click the **Add...** button.
3. Browse to the hard drive folder containing an image editing application.

4. Select the executable file of the editing application. For example, LUXEA Pro Video Editor 7.exe.
5. Click **Open**.
6. Enter an editor name in the **Name** field, then click **OK**.

To create a shortcut to the default External Editor:

1. Select **Tools | Customize Shortcuts...** from the main menu.
2. In the **Customize Shortcuts** dialog box, select "Tools" from the **Category** drop-down menu.
3. From the **Commands** menu, select **Default External Editor**.
4. Enter a shortcut key into the **Enter new shortcut key** field.
5. Click **Assign** and close the dialog box.

A new keyboard shortcut has been set for the default external editor.

To create a shortcut to an individual External Editor:

1. Select **Tools | Customize Shortcuts...** from the main menu.
2. In the **Customize Shortcuts** dialog box, select "External Editors" from the **Category** drop-down menu.
3. From the **Commands** menu, select the desired external editor.
4. Enter a shortcut key into the **Enter new shortcut key** field.
5. Click **Assign** and close the dialog box.

A new keyboard shortcut has been set for an individual external editor.

To add an External Editor to the FileList toolbar in Manage mode:

1. Click the **Toolbar Options** drop-down arrow, to the right of the **Editors** and **Actions** menu options, and select **Add or Remove Buttons | Customize**.
2. In the **Customize** dialog box, in the **Commands** tab, select "Tools" from the **Category** list.
3. Click and drag an External Editor from the list onto the FileList toolbar.
4. Close the dialog box.

An External Editor is added to the FileList toolbar.

To add an External Editor button to the toolbar in View mode:

1. Click the **Toolbar Options** drop-down arrow, to the right of the tools, and select **Add or Remove Buttons | Customize**.
2. In the **Customize** dialog box, in the **Commands** tab, select "Tools" from the **Category** list.
3. In the **Commands** list, select **Default External Editor**, and click and drag it onto the toolbar.
4. Close the dialog box.

The default External Editor is added to the toolbar.

To manage image editors:


1. In **Manage** mode, select **Tools | External Editors | Configure Editors** from the main menu.
2. In the **Configure Photo Editors** dialog box, in the **Editors** list, select an application to change.
3. Do any of the following:
 - To change the location of the executable file or the name of the application displayed in the Editors list, click **Edit**. Set the location and name of the application, and then click **OK**.
 - To set the application as the default external editor for ACDSee, click **Set As Default**.
 - To specify whether the application can handle multiple images at the same time, check or uncheck the checkbox in the **Supports Multiple Images** column.
 - To remove the application from the list, click **Remove**.
4. Click **OK** to accept your changes and return to ACDSee.


To open an image in an external image editor:

1. In **Manage** or **View** mode, select an image to open in an external editor.
2. Do one of the following:
 - Select **Tools | External Editors | Default External Editor** or the name of an editor.
 - Press **Ctrl + Alt + X** to open the image in the default external editor.

Customizing Keyboard Shortcuts

There are pre-defined keyboard shortcuts for commands that you use frequently. You can change pre-defined shortcuts, or create keyboard shortcuts for commands that do not currently have shortcuts. The options available in the Customize Shortcut dialog will be mode-specific, depending on which mode you opened the dialog from.

 Keyboard shortcuts customized in one mode will not take effect in the other modes, even if the defined command name is the same.

 If a shortcut is already assigned to a command, then assigning it to another command will unassign it from the original command.

To Customize Keyboard Shortcuts:

In Manage, View, Edit, and People mode:

1. Click **Tools | Customize Shortcuts...** or press **Ctrl + Shift + Alt + S**.
2. From the Category drop-down menu, select a category, such as File, Edit, or View. The commands available from that menu display in the Commands list box.
3. Select a command in the **Commands** list box.
 - If a keyboard shortcut has been defined for that command, it displays in the **Current Keys** box.
 - If a keyboard shortcut has not been defined for that command, the Current Keys box will be empty.

To remove an existing keyboard shortcut, select the keyboard shortcut in the Current Keys box, and then click **Remove**.

To Define a New Keyboard Shortcut:

1. Click in the **Enter a new shortcut key** text box.
2. Press the keys on your keyboard that you want to use for the keyboard shortcut.

The keys display in the Enter a new shortcut key text box. The Currently assigned to field will display the function your entered shortcut is assigned to, if applicable.

3. Click **Assign**.

The new keyboard shortcut displays in the Current keys box.

4. Click **Close**.

To remove all custom keyboard shortcuts and restore the default keyboard shortcuts, click **Reset All**.

Changing the Display Theme

In ACDSee Home you can change the display theme to change the background color of the panes and toolbars.

To Change the Display Theme:

1. In Manage mode, click **Tools | Options**.
2. In the Options dialog box, click **Manage Mode**.
3. In the **Display theme** drop-down list, select a theme.
4. Click **OK** to apply your changes and return to ACDSee.

Setting JPEG Options

You can change the settings in the Options dialog box to control the quality of the JPEG image, encoding method, color subsampling method, and whether to update or create embedded thumbnails in the JPEG image.

JPEG Options

Image quality	Drag the slider to determine the quality of the JPEG image.
Encoding	<ul style="list-style-type: none"> • Progressive: select to enable progressive encoding. • Optimize Huffman codes: select to optimize Huffman codes to increase compression.
Color component sampling	<ul style="list-style-type: none"> • 2:1 Horizontal: select to subsample color channels on the horizontal axis by a factor of 2:1. • 2:1 Vertical: select to subsample color channels on the vertical axis by a factor of 2:1.
Embedded thumbnails	<ul style="list-style-type: none"> • Only update existing thumbnails: select to update any existing embedded thumbnails. • Always add/update thumbnails: select to update any existing embedded thumbnails, or create embedded thumbnails. • Never add/update thumbnails: select if you do not want to update any existing embedded thumbnails, or if you do not want to create embedded thumbnails. • Generate DCF compatible thumbnails: select to generate thumbnails that meet the Digital Camera Format (DCF) specification and are compatible with the thumbnail view on the LCD of a digital camera. This option forces a fixed resolution of 160 x 120 and pads any extra space with black.
Save these settings as the defaults	Select this option to use these JPEG settings by default for all JPEGs.

Chapter 11: Shortcuts

Manage Mode Keyboard Shortcuts

You can use the following keyboard shortcuts while working in Manage mode. There are also shortcuts that can be used specifically in the [Calendar pane](#).



To print this page for easy reference, right-click and select **Print...**

This Shortcut	Has This Result
Alt + F4	Closes ACDSee.
Ctrl + Shift + Alt + S	Opens the Customize Shortcuts dialog box, in which you can customize keyboard shortcuts.
Alt + O	Opens the Options dialog box.
F1	Opens the Help file.
Enter	Opens the selected item in View mode.
Delete	Deletes the selected items.

Using ACDSee Tabs

Ctrl + T	Opens a new tab.
Alt + D	Duplicates the currently selected tab.
Ctrl + W	Closes the currently selected tab.
Ctrl + Page Down Ctrl + Tab	Activates the next tab to the right of your currently selected one.
Ctrl + Page Up Ctrl + Shift + Tab	Activates the previous tab to the left of your currently selected one.

Using Manage Mode

This Shortcut	Has This Result
\ (backslash)	Tags or untags the image.

	This Shortcut	Has This Result
	` (grave accent)	Toggles image audio on or off.

This Shortcut	Has This Result
Alt + C	Copies one or more selected files to a folder you specify.
Alt + Comma	Opens the previous tab in the Properties pane.
Alt + Period	Opens the next tab in the Properties pane.
Alt + Enter	Opens or closes the Properties pane.
Alt + G	Opens the Import dialog box.
Alt + I	Opens the Filters dialog box where you can specify the types of files displayed in the File List pane.
Alt + K	Places the cursor in the Keyword section of the IPTC group in the Metadata tab of the Properties pane.
Alt + M	Moves one or more selected files to a folder you specify.
Ctrl + 0	Clears the rating.
Ctrl + 1	Assigns a rating of 1.
Ctrl + 2	Assigns a rating of 2.
Ctrl + 3	Assigns a rating of 3.
Ctrl + 4	Assigns a rating of 4.
Ctrl + 5	Assigns a rating of 5.
Alt + 0	Clears the color label.
Alt + 1	Assigns a red color label.
Alt + 2	Assigns a yellow color label.
Alt + 3	Assigns a green color label.
Alt + 4	Assigns a blue color label.
Alt + 5	Assigns a purple color label.

This Shortcut	Has This Result
Alt + Shift + F	Maximizes the File List pane.

This Shortcut		Has This Result
	F2	Renames one or more selected files.

This Shortcut	Has This Result
Alt + W	Restores your desktop wallpaper to the settings you were using before you applied an ACDSee Home wallpaper.
Alt + X	Removes currently displayed item from the active Image Basket.
Backspace	Moves up one level in the current drive's folder structure.
Ctrl + \ (backslash)	Selects the tagged images.
Ctrl + A	Selects the entire contents of the current folder.
Ctrl + B	Adds the selected items to the active Image Basket.
Ctrl + E	Opens the currently selected image in Edit mode.
Ctrl + G	Generates a file listing as a text document.
Ctrl + I	Selects all images in the current folder.
Ctrl + Alt + D	Opens the Edit Caption dialog box.
Ctrl + K	Places the cursor in the Keywords field of the Organize tab in the Properties pane.
Ctrl + N	Creates a new folder in the File List pane.
Ctrl + O	Opens the Open Files dialog box, in which you can select one or more images to open in View mode.
Ctrl + P	Opens the currently selected image or images in the ACDSee Home Print utility.
Ctrl + X	Cuts the currently selected items to the Clipboard.
Ctrl + C Ctrl + Insert	Copies the selected items to the Clipboard.
Ctrl + V	Pastes the contents of the Clipboard.

This Shortcut	Has This Result
Shift + Insert	

This Shortcut	Has This Result
Ctrl + F	Puts the focus in the Quick Search bar so that you can begin typing your search query.
F5	Refreshes Manage mode.
F3	Opens the Advanced Search pane.
Ctrl + Alt + E	Opens the Export dialog box.
F4	Displays the Contents bar drop-down list.
F6	Changes the File List to Thumbs+Details view.
F7	Changes the File List to Filmstrip view.
F8	Changes the File List to Thumbnails view.
F9	Changes the File List to Tiles view.
F10	Changes the File List to Icons view.
F11	Changes the File List to List view.
F12	Changes the File List to Details view.
Shift + Alt + S	Opens the AI Super-Resolution dialog box.
Shift + Delete	Removes the selected item from your hard drive.
Shift + F5	Refreshes the File List pane.
Shift + Tab	Moves the focus of the Manage mode window to the previous pane or tool in sequence.
Tab	Moves the focus of the Manage mode window to the next pane or tool in sequence.
Ctrl + Alt + R	Opens the selected images in the Compare Images viewer.
Ctrl + Alt + W	Sets the selected image as a stretched desktop wallpaper.

This Shortcut	Has This Result
Ctrl + Alt + X	Opens the current image in the default external editor.
Ctrl + Right-Click	Opens Windows Explorer context menu.
Ctrl + Shift + 1	Opens or closes the Folders pane.
Ctrl + Shift + 2	Opens or closes the Catalog pane.
Ctrl + Shift + 3	Opens or closes the Advanced Search pane.
Ctrl + Shift + 4	Opens or closes the Calendar pane.
Ctrl + Shift + 5	Shows or hides all Image Baskets.
Ctrl + Shift + 6	Opens or closes the Activity Manager.
Ctrl + Shift + 7	Opens or closes the Task Pane.
Ctrl + Shift + 9	Creates a new Image Basket.
Ctrl + Shift + -	Deletes the active Image Basket.
Ctrl + Shift + A	Selects all files in the current folder.
Ctrl + Shift + B	Shows or hides the status bar.
Ctrl + Shift + C	Copies the currently selected image to the Clipboard.
Ctrl + Shift + D	Clears your current selection.
Ctrl + Shift + E	Opens the current file in the default system application or opens a dialog box where you can select an application.
Ctrl + Shift + F	Toggles the full-screen view for the File List pane.
Ctrl + Shift + I	Inverts your current selection.
Ctrl + Shift + L	Opens or closes the Selective Browsing panel.
Ctrl + Shift + M	Opens or closes the Map pane.
Ctrl + Shift + N	Opens a second instance of the ACDSee

This Shortcut	Has This Result
	program.
Ctrl + Shift + O	Opens the file using the system application associated with its file extension.
Ctrl + Shift + T	Displays or hides the Manage mode Main toolbar.
Ctrl + Shift + W	Sets the selected image as a tiled desktop wallpaper.
Ctrl + Shift + Alt + W	Sets the selected image as a centered desktop wallpaper.
Viewing	
Alt + Left Arrow	Returns to the previous folder you browsed in the File List pane.
Alt + Right Arrow	Returns to the folder you last moved back from in the File List pane.
Ctrl + S	Creates a slideshow from the currently selected images.
Ctrl + Shift + P	Opens or closes the Preview pane.
Batch Editing	
Shift + S	Opens the Batch AI Super-Resolution dialog box.
Ctrl + R	Opens the Batch Resize Images dialog box.
Ctrl + Alt + F	Opens the Batch Convert File Format dialog box.
Ctrl + J	Opens the Batch Rotate/Flip Images dialog box.
Ctrl + Alt + T	Opens the Batch Adjust Time Stamp dialog box.
Ctrl + L	Opens the Batch Adjust Exposure dialog box.
Mode Switching	

This Shortcut	Has This Result
Ctrl + F2	Switches to Media mode.
Ctrl + F3	Opens the image in View mode.
Ctrl + F5	Opens the image in Edit mode.
Ctrl + F6	Switches to People mode.
Ctrl + F7	Switches to 365 mode.
Ctrl + F8	Switches to Dashboard mode.

Manage Mode Mouse Shortcuts

You can use the following mouse shortcuts in Manage mode.



To print this page for easy reference, right-click and select **Print...**

Shortcut	Resulting Action
Double-click	Opens the selected image in View mode.
Right-click	Opens the Manage mode context menu.
Shift + click	Selects a group of images.
Click + drag	Selects a group of images. Be sure to click on a blank area of the screen, not on an image or folder, before you drag, so you can draw a selection box around the group of images.
Ctrl + click	Selects images you click on.
Ctrl + right-click	Opens the Windows Explorer context menu.
Ctrl + Wheel up	Increases the magnification of the thumbnail (zooms in).
Ctrl + Wheel down	Decreases the magnification of the thumbnail (zooms out).

Calendar Pane Shortcuts

Once you are familiar with the basic calendar pane options, consider using the following shortcuts:

- Click the title bar on a year, month, or day table to display all available images for that year, month, or day.
- Right-click the title bar on a year, month, or day table to scroll through and select from adjacent years, months, or days.
- In Year view double-click any month to switch to Month view. Or, in Month view, double-click any date to switch to Day view.
- In Month view click the letter indicating a day of the week to display all available images for that day of the week. For example, click **F** to select all Fridays in that month.
- In Day view click **AM** or **PM** to select the first or second half of a day.
- In Event view press and hold the **Ctrl** key and click any month or day to display all available images for those months or days.
- Click on the title of any month calendar, to select all the photos in that month.
- Click the name of the week, to select all the photos in those weeks of the month.
- Drag and select any days in the calendar to select all the photos in those days.

Media Mode Keyboard Shortcuts

You can use the following keyboard shortcuts while working in Media mode.



To print this page for easy reference, right-click and select **Print...**

Shortcut	Resulting Action
Alt + F4 Ctrl + W	Closes ACDSee.
Alt + O	Opens the Options dialog.
Ctrl + P	Prints the selected image.
Ctrl + L	Rotates the selected image left.
Ctrl + R	Rotates the selected image right.
F5	Refreshes.
Ctrl + F	Show/Hide Folder pane.
Ctrl + G ALT + ENTER	Show/Hide Group/Properties pane.
SPACE, RIGHT, DOWN	Next image in Full Screen
BACKSPACE, LEFT, UP	Previous image in Full Screen
DELETE	Delete selected file

Mode Switching

Ctrl + F1	Switches to Manage mode.
Ctrl + F3	Opens the currently selected image in View mode.
Ctrl + F5	Opens the currently selected image in Edit mode.
Ctrl + F6	Switches to People mode.
Ctrl + F7	Switches to 365 mode.
Ctrl + F8	Switches to Dashboard mode.

View Mode Keyboard Shortcuts

You can use the following keyboard shortcuts while working in View mode.



To print this page for easy reference, right-click and select **Print...**



If you would like to define your own keyboard shortcuts, see [Customizing Keyboard Shortcuts](#).

Shortcut	Resulting Action
Alt + F4	Closes ACDSee.
` (grave accent)	Toggles the display of the full file path in the Status bar.
Enter Esc	Switches to the previous mode.
Shift + Esc	Minimizes ACDSee in View and Edit mode.
Ctrl + Shift + Alt + S	Opens the Customize Shortcuts dialog box, in which you can customize keyboard shortcuts.
Alt + O	Opens the Options dialog box.
F1	Opens the Help file.

File Menu

Ctrl + O Insert	Opens the Open files dialog box.
Shift + F4	Closes the current item.
Ctrl + Shift + F4	Closes all images.
Ctrl + S	Opens the Save Image As dialog box, in which you can save your image with a different name or file format.
Shift + L	Opens the file using the system application associated with its file extension.
Shift + E	Opens the current file in the default system application or opens a dialog box where you can select an application.
Ctrl + P	Opens the current image in the ACDSee Home Print utility.
Ctrl + Shift + P	Prints all currently selected images, or all images in the current folder.
Alt + L	Opens the Flickr Uploader dialog box.
Alt + U	Opens the SmugMug Uploader dialog box.
Alt + Z	Opens the Zenfolio Uploader dialog box.

Customizing the Interface

Shortcut	Resulting Action
Ctrl + Shift + H	Toggles the Histogram open and closed.
Ctrl + Shift + M	Toggles the Magnifying Glass pane open and closed.
Ctrl + + (plus)	Zooms in on the Magnifying Glass pane.
Ctrl + - (minus)	Zooms out on the Magnifying Glass pane.
Ctrl + Shift + S	Toggles the Navigator open and closed.
Alt + Enter	Toggles the Properties pane open and closed.
Alt + ,	Switches to the tab to the left on the Properties pane.
Alt + .	Switches to the tab to the right on the Properties pane.
Ctrl + Shift + F	Toggles the Filmstrip open and closed.
Ctrl + Shift + I	Toggles the Info palette open and closed.
T Ctrl + Shift + T	Toggles the Toolbar open and closed.
B Ctrl + Shift + B	Toggles the Status bar open and closed.
Ctrl + Shift + V	Toggles the Page View panel open and closed for multi-page images.

Managing

Shortcut		Resulting Action
	Ctrl + X	Cuts the current item to the Clipboard.

Shortcut	Resulting Action
Ctrl + C	Copies the currently displayed file to the Clipboard.

	Shortcut	Resulting Action
	Ctrl + V	Pastes the contents of the Clipboard.

Shortcut	Resulting Action
Alt + C	Opens the Copy To Folder dialog box.

	Shortcut	Resulting Action
	Alt + M	Opens the Move To Folder dialog box.

Shortcut	Resulting Action
Delete	Deletes the selected image.

Shortcut	Resulting Action
F2	Opens the Rename File dialog box.
Alt + R	
Ctrl + B	Adds the selected image to the active Image Basket.
Alt + X	Removes the selected image from the active Image Basket.
Alt + A	Opens the Add Shortcut dialog box.
Ctrl + Alt + D	Opens the Edit Caption dialog box.
\ (back slash)	Tags or untags the image.
Ctrl + M	Opens the Manage Metadata Presets dialog box.
Ctrl + 0	Clears the rating.
Ctrl + 1	Assigns a rating of 1.
Ctrl + 2	Assigns a rating of 2.
Ctrl + 3	Assigns a rating of 3.
Ctrl + 4	Assigns a rating of 4.
Ctrl + 5	Assigns a rating of 5.
Alt + 0	Clears the color label.
Alt + 1	Assigns a red color label.
Alt + 2	Assigns a yellow color label.
Alt + 3	Assigns a green color label.
Alt + 4	Assigns a blue color label.
Alt + 5	Assigns a purple color label.
Ctrl + K	Opens the Keywords section of the Properties pane.
Alt + K	Opens the Metadata tab of the Properties pane.
Ctrl + Shift + Alt + W	Sets the selected image as the desktop wallpaper, centered.
Ctrl + Shift + W	Sets the selected image as the desktop wallpaper, tiled.

Shortcut	Resulting Action
Ctrl + Alt + W	Sets the selected image as the desktop wallpaper, stretched.
Alt + W	Restores your desktop wallpaper to the settings you were using before you applied an ACDSee Home wallpaper.
Viewing	
Page Arrow Right	Displays the next image.
Page Down	
3 (numeric keypad)	
Spacebar	
Page Arrow Left	Displays the previous image.
Page Up	
9 (numeric keypad)	
Backspace	
End	Switches to the last image in the Filmstrip.
Home	Switches to the first image in the Filmstrip.
Ctrl + Right-click	Opens the Windows Explorer context menu.
+ (plus)	Zooms in.
- (minus)	Zooms out.
Shift + Z	Zooms in to the area you select.
/ (forward slash)	Zooms the image to its actual size.
* (numeric keypad asterisk)	Fits the image to the viewing area.
Shift + 8	
Alt + Page Arrow Right	Fits image width to the display area.

Shortcut	Resulting Action
Alt + Page Down	Fits image height to the display area.
Alt + \	Toggles the zoom lock on and off.
L	Toggles the pan lock.
Z	Opens the Set Zoom Level dialog box.
Page Arrow Right	Pans right when zoomed into the image.
Page Arrow Left	Pans left when zoomed into the image.
Page Down	Pans down when zoomed into the image.
Page Up	Pans up when zoomed into the image.
F	Toggles full screen mode.
Ctrl + Page Arrow Right	Toggles the right pane open and closed.
Ctrl + Page Arrow Down	Toggles the bottom pane open and closed.
O	Displays saved version of the image.
E	Toggles the exposure warning on and off.
Shift + F1	Activates the Hand tool after zooming in with the Zoom tool.
Shift + F2	Activates the Select tool.
Ctrl + Q	Clears the current selection.
Shift + F3	Activates the Zoom tool.
Shift + F	Activates the Face tool.
Shift + B	Toggles face outlines.
Ctrl + N	Opens the Face Detection pane and puts the cursor in the first name field.
TAB	Moves the cursor between name fields on the image, as well as on the Face Detection pane.

Shortcut	Resulting Action
Ctrl + Shift + D	Toggles the Face Detection pane.
Ctrl + F	Redetects faces.
F5	Refreshes the View mode window and reloads the current image.
Ctrl + 6	Toggles the Light EQ button on and off.
Alt + S	Automatically advances to the next image every 1 to 2 seconds.
Ctrl + Alt + S	Launches the slideshow.
Ctrl + A	Displays or hides headers and footers.
Ctrl + Shift + Q	Opens the View Header/Footer dialog box, in which you can specify the text to display on your images in View mode.
Alt + Ctrl + S	Starts or stops the slideshow.
Shift + Page Arrow Down	Advances to the next page of a multi-page image.
Shift + Page Arrow Up	Switches to the previous page of a multi-page image.
Shift + Home	Switches to the first page of a multi-page image.
Shift + End	Switches to the last page of a multi-page image.

Editing

Ctrl + Shift + Page Arrow Left	Rotates the current image 90° counterclockwise.
Ctrl + Shift + Page Arrow Right	Rotates the current image 90° clockwise.
Alt + E	Opens the image in the default editor.
Shift + O	Restores an edited image to the original version.
Shift + S	Commits the changes.
Shift + Alt + S	Opens the AI Super-Resolution dialog box.

Shortcut	Resulting Action
Ctrl + Alt + F	Opens the Batch Convert File Format dialog box.
Ctrl + J	Opens the Batch Rotate/Flip Images dialog box.
Ctrl + R	Opens the Batch Resize Images dialog box.
Ctrl + L	Opens the Batch Adjust Exposure dialog box.
Ctrl + Alt + T	Opens the Batch Adjust Time Stamp dialog box.
Ctrl + Alt + R	Opens the Batch Rename dialog box.
Ctrl + Shift + 1	Changes the image color depth to Black and White.
Ctrl + Shift + 2	Changes the image color depth to 16 grays.
Ctrl + Shift + 3	Changes the image color depth to 256 grays.
Ctrl + Shift + 4	Changes the image color depth to 16 colors.
Ctrl + Shift + 5	Changes the image color depth to 256 colors.
Ctrl + Shift + 6	Changes the image color depth to Hicolor.
Ctrl + Shift + 7	Changes the image color depth to Truecolor.
Ctrl + Shift + 8	Converts the image to a 16-bit grayscale palette.
Ctrl + Shift + 9	Converts the image to a 48-bit color palette.

Mode Switching

Ctrl + F1	Switches to Manage mode.
Ctrl + F2	Switches to Media mode.
Ctrl + F5	Opens the currently selected image in Edit mode.
Ctrl + F6	Switches to People mode.
Ctrl + F7	Switches to 365 mode.
Ctrl + F8	Switches to Dashboard mode.

View Mode Mouse Shortcuts

You can use the following mouse shortcuts while working in View mode.



To print this page for easy reference, right-click and select **Print...**

Shortcut	Resulting Action
Double-click	Closes View mode and returns to the previous mode.
Right-click	Opens the View mode context menu.
Middle click	Toggles full screen mode (on 3-button mouse).
Wheel click	Toggles full screen mode.
Wheel up	Displays the previous item.
Wheel down	Displays the next item.
Ctrl + Right-click	Opens the Windows Explorer context menu.
Ctrl + Wheel up	Increases the magnification of the image (zooms in).
Ctrl + Wheel down	Decreases the magnification of the image (zooms out).
Shift + Wheel up	Displays the previous page of a multiple-page image.
Shift + Wheel down	Displays the next page of a multiple-page image.

Edit Mode Keyboard Shortcuts

Use the following keyboard shortcuts in Edit mode.



To print this page for easy reference, right-click and select **Print...**



If you would like to define your own keyboard shortcuts, see [Customizing Keyboard Shortcuts](#).

Edit Mode Keyboard Shortcuts

Shortcut	Resulting Action
Alt + F4	Closes ACDSee in all modes.
Shift + Esc	Minimizes ACDSee in View and Edit mode.
Ctrl + Shift + Alt + S	Opens the Customize Shortcuts dialog box, in which you can customize keyboard shortcuts.
Alt + O	Opens the Options dialog box.
F1	Opens the Help file.
` (grave accent)	Toggles the display of the full file path in the Status bar.

File Menu

Page Arrow Right	Opens the next image.
Page Down	
3 (numeric keypad)	
Page Arrow Left	Opens the previous image.
Page Up	
9 (numeric keypad)	
Ctrl + S	Saves the image.
Ctrl + Alt + S	Saves a copy.
Ctrl + Alt + E	Opens the Export dialog.
End	Switches to the last image in the Filmstrip.
Home	Switches to the first image in the Filmstrip.
Esc	Switches to the previous mode.
Enter	

Edit Menu

Shortcut		Resulting Action
	Ctrl + Y	Redo.
	Ctrl + Z	Undo.
	Ctrl + Shift + Z	Undo all.
	Ctrl + C	Copy.
	Ctrl + V	Paste.
	Delete	Delete.
Managing		

Shortcut	Resulting Action
Alt + 0	Clears the color label.
Alt + 1	Assigns a red color label.
Alt + 2	Assigns a yellow color label.
Alt + 3	Assigns a green color label.
Alt + 4	Assigns a blue color label.
Alt + 5	Assigns a purple color label.
Ctrl + 0	Clears the rating.
Ctrl + 1	Assigns a rating of 1.
Ctrl + 2	Assigns a rating of 2.
Ctrl + 3	Assigns a rating of 3.
Ctrl + 4	Assigns a rating of 4.
Ctrl + 5	Assigns a rating of 5.
Ctrl + K	Opens the Keywords section of the Properties pane.
Alt + K	Opens the Metadata tab of the Properties pane.
\ (back slash)	Tags the photo.
Ctrl + M	Opens the Manage Metadata Presets dialog box.
Ctrl + Alt + D	Opens the Edit Caption dialog box.
Viewing	

Shortcut	Resulting Action
Ctrl + Page Arrow Right	Toggles the right pane open and closed.
Ctrl + Page Arrow Left	Toggles the left pane open and closed.
Ctrl + Page Arrow Down	Toggles the bottom pane open and closed.
/ (forward slash)	Zooms the image to its actual size.
Shift + 8 * (numeric keypad asterisk)	Fits the image to the viewing area.
+ (plus)	Zooms in.
- (minus)	Zoomed out.
F	Displays the image full screen.
'	Toggles Navigator open and closed when zoomed into the image.
Z	Displays saved version of the image.
Page Arrow Right	Pans right when zoomed into the image.
Page Arrow Left	Pans left when zoomed into the image.
Down Arrow	Pans down when zoomed into the image.
Up Arrow	Pans up when zoomed into the image.

Customizing the Interface

Shortcut	Resulting Action
F2	Toggles the Filter Menu open and closed.
F4 Alt + Enter	Toggles the Properties pane open and closed.
F5	Toggles the Filmstrip open and closed.
F6	Toggles the Info palette open and closed.
F7 Ctrl + Shift + H	Toggles the Histogram open and closed.
F10	Toggles the Colors pane open and closed.
Alt + F1	Toggles the Toolbar open and closed.
Alt + F2	Toggles the Filters toolbar open and closed.
Selecting	
Alt + A	Selects all.
Alt + D	Deselects.
Alt + I	Inverts selection.
Shift + Alt + S	Saves the selection.
Shift + Alt + L	Opens the Load Selection dialog box.
Shift + Alt + M	Opens the Manage Selections dialog box
Filters	
Y	Opens the Red Eye Reduction tool.
Alt + P	Opens the Repair tool.
K	Opens the Skin Tune tool.
X	Opens the Text tool.
Alt + W	Opens the Watermark tool.
Alt + B	Opens the Border tool.
V	Opens the Vignette tool.

Shortcut	Resulting Action
Alt + S	Opens the Special Effects panel.
T	Opens the Tilt-Shift tool.
Alt + G	Opens the Grain tool.
Alt + R	Opens the Rotate tool.
Alt + F	Opens the Flip tool.
C	Opens the Crop tool.
J	Opens the Resize tool.
Alt + X	Opens the Exposure tool.
L	Opens the Levels tool.
Alt + J	Opens the Auto Levels tool.
U	Opens the Tones Curves tool.
Q	Opens the Light EQ™ tool.
H	Opens the Dehaze tool.
A	Opens the White Balance tool.
W	Opens the Convert to Black & White tool.
Alt + M	Opens the Color LUTs tool.
Alt + N	Opens the Sharpen tool.
Alt + U	Opens the Blur tool.
N	Opens the Noise Reduction tool.
Alt + C	Opens the Clarity tool.

Working Inside Filters

Shortcut	Resulting Action
B	Toggles Brush controls open and closed.
S	Toggles the brush stroke display when working inside a filter.
G	Toggles Gradient controls open and closed.
R	Toggles Radial Gradient controls open and closed.
Spacebar	Switches to the Hand tool when working with the Brush or Gradients inside a filter.
E	Toggles the exposure warning on and off in the Exposure tool.

Tools

Ctrl + Q	Activates the Hand tool.
Ctrl + Shift + R	Activates the Rectangle tool.
Ctrl + Shift + E	Activates the Elliptical tool.
Ctrl + Shift + L	Activates the Line tool.
Ctrl + A	Activates the Arrow tool.
Ctrl + Shift + P	Activates the Polygon tool.
Ctrl + Shift + B	Activates the Curve tool.
B	Activates the Brush tool.
Ctrl + F	Activates the Fill tool.
Ctrl + G	Activates the Gradient tool.
Ctrl + Shift + I	Activates the Eyedropper tool.

Color Tools

Shortcut	Resulting Action
Ctrl + [Opens the Foreground Color dialog box.
Ctrl +]	Opens the Background Color dialog box.
Ctrl + X	Switches the foreground and background color.
Selection Tools	
Ctrl + R	Activates the Rectangle Selection tool.
Ctrl + I	Activates the Ellipse Selection tool.
Ctrl + L	Activates the Lasso Selection tool.
Ctrl + W	Activates the Magic Wand Selection tool.
Mode Switching	
Ctrl + F1	Switches to Manage mode.
Ctrl + F2	Switches to Media mode.
Ctrl + F3	Opens the image in View mode.
Ctrl + F7	Switches to 365 mode.
Ctrl + F8	Switches to Dashboard mode.

Edit Mode Mouse Shortcuts

Use the following mouse shortcuts in Edit mode to make quick image adjustments.



To print this page for easy reference, right-click and select **Print...**

Shortcut	Resulting Action
Shift + click	Turns off the auto-collapse feature in the pane as you open groups.
Shift + mouse wheel	Makes large adjustments to the sliders.
Ctrl + mouse wheel	Makes small adjustments to the sliders.
Right-click	Resets any slider to its default value.
Mouse wheel over slider	Makes fine adjustments to a slider. Place your cursor over the slider and scroll up or down.
Mouse wheel over image	Adjusts brush size. Place your cursor over the image and scroll up or down to adjust nib width.
Shift + mouse wheel	Adjusts feathering. Place your cursor over the image and scroll up or down to adjust feathering.

365 Mode Keyboard Shortcuts

Use the following keyboard shortcuts in the Transfer mode.



To print this page for easy reference, right-click and select **Print...**



If you would like to define your own keyboard shortcuts, see [Customizing Keyboard Shortcuts](#).

Shortcut	Resulting Action
Alt + A	Sets selected folder as an Upsync folder.
Alt + D	Downloads selected files and folders.
Alt + Enter	Displays Properties pane in the lower screen of Transfer mode.
Alt + Num +	Group forward files and folders in the lower screen of Transfer mode.
Alt + Num -	Group backward files and folders in the lower screen of Transfer mode.
Alt + O	Displays Options dialog.
Alt + U	Uploads selected files and folders.
Alt + Shift + U	Upsyncs all files.
Ctrl + \	Selects tagged files.
Ctrl + A	Selects all files and folders.
Ctrl + F8	Changes the view in the upper screen in Transfer mode to thumbnail view of images in your account.
Ctrl + F12	Changes the view in the upper screen in Transfer mode to a detailed view of images in your account.
Ctrl + Shift + D	Clears image selection.
Ctrl + Shift + I	Inverts image selection.
Ctrl + Shift + 1	Displays Folders pane in the lower screen of Transfer mode.
Ctrl + Shift + 2	Displays Catalog pane in the lower screen of Transfer mode.
Ctrl + Shift + 3	Displays Advanced Search pane in the lower screen of Transfer mode.
Ctrl + Shift + 4	Displays Calendar pane in the lower screen of Transfer mode.
Ctrl + Shift + 5	Shows or hides all Image Baskets.
Ctrl + W	Closes ACDSee.
Delete	Deletes files or folders.
Enter	Opens the selected item in View mode.
F2	Renames files and folders.

Shortcut	Resulting Action
F5	Refreshes the view.
F6	Displays thumbnails and details of folders and files in the lower screen of Transfer mode.
F7	Displays filmstrip view of folders and files in the lower screen of Transfer mode.
F8	Displays thumbnails of folders and files in the lower screen of Transfer mode.
F9	Displays tile view of folders and files in the lower screen of Transfer mode.
F10	Displays icon view of folders and file types in the lower screen of Transfer mode.
F11	Displays a list of folder and file types in the lower screen of Transfer mode.
F12	Displays a detailed view of folders and files in the lower screen of Transfer mode.
Num +	Sort forward files and folders in the lower screen of Transfer mode.
Num -	Sort backward files and folders in the lower screen of Transfer mode.
Shift + Alt + A	Displays seedrive.acdsee.com mode.
Shift + Alt + C	Copies URL.
Shift + Alt + T	Displays Transfer mode.

365 Mode Mouse Shortcuts

Use the following mouse shortcuts in Transfer mode.



To print this page for easy reference, right-click and select **Print...**

Shortcut	Resulting Action
Click + drag	Selects a group of images.
Ctrl + click	Selects images you click on.
Shift + click	Selects a group of images.

ACDSee PicaView Keyboard Shortcuts

You can use the following shortcut with ACDSee PicaView.

This Shortcut	Has This Result
Shift + right-click an image	<ul style="list-style-type: none">• If you have Display Image enabled: the image will not display in the main context menu.• If you have Display Image disabled: the image will display in the main context menu.

Chapter 12: File Formats

Supported File Formats in ACDSee Home

Files that can be read by ACDSee:

ABR	Adobe™ brush format	
ACDC	ACDSee Home ACDC Image	
AFPHOTO	Affinity	Thumbnails only.
ANI	Windows animated cursor	Shows cursor animation.
ARW	Sony RAW	
AVIF	AV1 Image File Format	Animated AVIF files are not supported. IPTC metadata is supported for AVIF files with XMP.
BMP	Windows Bitmap	Windows and OS/2; 2/8/16/24/32 bpp; RLE and uncompressed.
CNV	Canvas	Thumbnails only.
CR2	Canon RAW CR2	
CR3	Canon RAW CR3	To see applicable cameras, please refer to the supported RAW format page on the ACDSee website.
cRAW	Sony cRAW	
CRW	Canon RAW CRW	
CS1	Sinar RAW	In the Image Type metadata field, this file format is referred to as "RAW".
CUR	Windows cursor	
CVX	Canvas	Thumbnails only.
DCR	Kodak RAW DCR	
DCX	Multi-page PCX	All sub-types and multiple pages supported.
DNG	Digital Negative	An open-source archival format for RAW files.
EMF	Enhanced Metafile Format	Win32 enhanced placeable metafiles.
ERF	Epson RAW	
FFF	Hasselblad RAW FFF	In the Image Type metadata field, this file format is referred to as "RAW".
GIF	Graphics Interchange Format	Single page animated; 87a and 89a.

GPR	GoPro RAW	
GSD	Gemstone Document	Layers only supported in Gemstone Photo Editor.
HDR	Creo RAW	
HEIC/HEIF	High Efficiency Image File Format	Includes support for HIF files. Supports EXIF only. IPTC metadata is not supported for HEIC files.
ICN	AT&T ICN	
ICO	Windows icon	Shows multiple resolutions as separate pages.
JBR	Corel brush format	
JP2	JPEG 2000	48-bit support.
JPC	JPEG 2000	48-bit support.
JPG	JPEG JFIF	JFIF and Adobe CMYK.
JXL	JPEG-XL	IPTC metadata is supported for JPEG-XL files with XMP.
MOS	Creo RAW	In the Image Type metadata field, this file format is referred to as "RAW".
MRW	Konica Minolta RAW	
NEF	Nikon RAW	
ORF	Olympus RAW	
PBR	Corel PaintShop Pro brush format	Up to 3072×2048 resolution (16BASE).
PCX	ZSoft Publishers Paintbrush	All sub-types supported.
PEF	Pentax RAW PEF, Samsung RAW	
PCT	Macintosh PICT	
PNG	Portable Network Graphics	All sub-types supported.
PSD	Adobe PhotoShop Document	RGB, grayscale, duotone, paletted and bi-level Lab color interpreted as grayscale only.
RAF	FujiFilm RAW	
RAW	Pentax RAW, Leica RAW, Contax RAW, Casio RAW, Panasonic	

	RAW	
RWL	Leica RAW	
sRAW	Canon sRAW	
SRW	Samsung SRW	
SVG	Scalable Vector Graphics	
TGA	Targa TGA	All sub-types supported.
TIFF	Tag Image File Format	Bilevel / RGB / Paletted / CMYK / YCrCb / LOGL / LOGLUV; Uncompressed / PackBits / LZW / ThunderScan / SGILog / CCITT / ZIP / NEXT / New-JPEG (no v6.0 JPEG support) Support for multiple-page documents Kodak RAW TIFF, Canon RAW TIFF
WBMP	Wireless Bitmap	
WEBP	Google WebP Format	Includes support for animated and transparent WebP files.
WMF	Windows Metafile Format	Win 3.x placeable metafiles.

Files that can be written by ACDSee:

ACDC	ACDSee Home ACDC Image	Not supported on ACDSee Pro or ACDSee Home.
AVIF	AV1 Image File Format	Supports EXIF only. IPTC metadata is not supported for AVIF files.
BMP	Windows Bitmap	Windows 1/8/24 bpp.
GIF	Graphics Interchange Format	Non-interlaced GIF 89a only.
GPR	GoPro RAW	
JP2	JPEG2000	
JPEG	JPEG JFIF	
PCX	ZSoft Publishers Paintbrush	8 and 24 bpp; RLE compressed.
PNG	Portable Network Graphics	1/4/8 bpp colormapped; 24 bpp RGB.
PSD	Adobe PhotoShop Document	RGB, grayscale, duotone, paletted and bi-level Lab color interpreted as grayscale only.
WBMP	Wireless Bitmap	
WEBP	Google WebP Format	
TGA	Targa TGA	8 and 24 bpp. RLE and uncompressed top-down and bottom-up.
TIFF	Tag Image File Format	1/8/24 bits per pixel, single-page; uncompressed, CCITT3, CCITT4, LZW, Deflate (ZIP), and JPEG compression; Adjustable DPI tags.

Archive read support formats:

ARJ	ARJ archive	ARJ format.
CAB	CAB archive	Microsoft CAB file format.
GZ	GZ archive	Unix GZIP (GnuZIP).
RAR	RAR archive	RAR format (RAR5 is not supported).
TAR	TAR archive	Unix TAR format.
TGZ	TGZ archive	TAR format compressed with GZIP.
ZIP	ZIP archive	Store and deflate.

Archive write support formats:

ZIP	ZIP archive	Store and deflate.
------------	-------------	--------------------

Video and audio read support formats:

AAC	Audio Data Transport Format
ADST	Audio Data Transport Stream
ASF	Active Streaming File – HotMetaL Pro
AVI	AVI movie format
M4A	MPEG-4
M4V	MPEG-4
MOV	MPEG-4
MP3	MPEG Layer III compressed audio
MP4	MPEG-4
WAV	Sound file
VMA	Sound file
WMV	Windows Metafile

About RAW Files

A RAW file is like a negative. RAW files contain all of the data that was collected by your digital camera's sensor when you took a photo. If you tried to view a RAW file without processing, it would appear almost completely black. It is therefore necessary to process your RAW files to produce a photo.

In ACDSee, you can view RAW files using the embedded thumbnail image created by your camera. If you want to process RAW images, you must use a photo editing program such as ACDSee Professional or ACDSee Ultimate, which includes tools for developing RAW images.



ACDSee will automatically apply geometry corrections to DNG files that include geometric distortion correction tags. DNG files created from the Adobe DNG Converter© will often generate geometric distortion tags for micro 4/3rds cameras.

Associating Files

ACDSee Home can work with a large number of file formats. ACDSee Home can be set as the default application for opening certain file types. This process is called associating files. When you associate file types, you set ACDSee Home as the default program to open these kinds of files when you double-click them.

To Set File Association Options in ACDSee:

1. Click **Tools | File Association Settings**.
2. In the four format sections, check the checkboxes of the file formats you would like to associate with ACDSee Home for image formats, RAW formats, media formats, and archive formats.
3. Click **Save**.

To Disassociate a File Type with ACDSee:

1. Click **Tools | File Association Settings**.
2. In the four format sections, uncheck the checkboxes of the file formats you would like to disassociate with ACDSee Home for image formats, RAW formats, media formats, and archive formats.
3. Click **Save**.

Glossary

A

Absolute Colorimetric

Colors that fall outside the range of what the output device can render are adjusted to the closest color that can be rendered.

Actions, ACDSee Actions

You can record the steps you take when editing images in Edit mode. You can then save them as "ACDSee Actions". Once saved, you can apply the actions to other images. This is particularly useful for batch editing.

Album

Collection of images, often organized by theme or event. In ACDSee, albums contain shortcuts to where the images are stored on your hard drive.

Aliasing

Jagged edges caused by pixels. Occurs most often in low resolution images or images that have been enlarged. See [jaggies](#).

Antialiasing, Anti-Aliasing

Software technique for reducing jagged lines, or 'jaggies'. Uses shades of gray and color to smooth out the contrast between adjacent pixels.

Aspect Ratio

An image's width-to-height ratio. For example, an image with an aspect ratio of 3:1 has a width 3 times larger than its height.

Azimuth

Angle of shadows that extend from the edges of image details. In ACDSee Home you can control azimuth when applying the Emboss effect to an image.

B

Background Processing

Tasks or programs that function without user interaction.

Barrel Distortion

In barrel distortion the photo appears to bulge outwards from the center.

Batch Editing

Any operation or tool, such as resizing, converting, or renaming, that can be used to adjust multiple images or files simultaneously.

Bit

Bits are small units of computer memory. The color depth of your image is constrained by the number of bits available to store color information. For example, it is possible to store 256 different color values per color channel in 8-bit RGB images. Similarly, it is possible to store 65,536 different color values per color channel in 18-bit images.

Blackpoint

An image's darkest area. You can control the intensity of the black in an image by adjusting its blackpoint.

Blend Modes

Filters that change the effect of a tool or the appearance of a selected object.

Brightness

Light intensity of an image. You can make an image appear brighter or darker by adjusting its brightness.

Brush

A tool that you can use in Edit mode to isolate or indicate pixels you want to apply effects or adjustments to. The Brush in Drawing Tools can be used to draw in color on your image.

C**Cache**

High-speed storage mechanism. The ACDSee Database is a cache.

Caption

Text associated with a file, or a comment or description added to a printed image.

Cataloging

Adding file information to the ACDSee Home database.

Category

Assign categories to photos to help sort and manage them more easily.

Chromatic Aberration

A lens artifact that can result in fringes in high contrast areas of some photos.

CMYK

Color model that uses cyan, magenta, yellow, and black (key) as its primary colors.

Color Cast

A color cast is a visible color tint that affects your image. For example, many digital cameras produce pictures with a slightly blue color cast. ACDSee Home includes a tool that removes an unwanted color cast.

Color Channel Value

Contains all pixel information for a single color. A grayscale image has one channel, while an RGB image has three channels. You can adjust RGB values when editing a color.

Color Gamut

Range of colors that a device such as a printer or monitor can produce or display.

Color Management

Process of adjusting your computer settings so that the color output from your printer matches the colors you see on your monitor.

Color Space

There are two types of color spaces: device-independent or device-dependent. A device-independent color space, such as RGB, describes all possible colors. A device-dependent color space describes the subset of colors (from the device-independent color space) that a particular device can reproduce. Device-dependent color spaces are used to map colors between devices (for example, from a monitor to a printer) to ensure that colors are reproduced accurately.

Compression

Process that converts data to a storage format requiring less space than the original data.

Contact Sheet

Physical or digital page that contains a series of small images, usually in a grid format.

Context Menu

Menu that appears when you right-click within a program.

Contrast

Measure of an image's color and brightness differences.

Convert

Change a file from one format to another. For example, you might convert a file from a bitmap (.bmp) to a JPEG (.jpg) to reduce the file size.

Cropping

Removing unwanted image areas.

D**Database**

Electronic filing system that provides fast access to stored data. The ACDSee Database contains two parts: a cached thumbnail file and an information file. The cached thumbnail file contains small copies (thumbnails) of the images on your system. The information file contains details about the files on your system, such as descriptions, dates, authors, notes, keywords, and categories.

Database Date

Date that you apply to the properties of a file and save in the ACDSee Database.

Descriptions

ACDSee Home stores descriptions in a hidden file named `descript.ion`. Descriptions such as file name and captions for an image will be included in the `descript.ion` files.

Dock

Attaching a toolbar, window, or pane to different screen areas.

DPI (dots per inch)

Measurement of an image's resolution. For example, 92 DPI means 92 dots horizontally and 92 dots vertically, which equals 8,464 dots per square inch. More dots per inch result in higher resolution and image quality.

Dynamic Range

The dynamic range of an image is directly related to the dynamic range of your digital camera's sensor. If your digital camera's sensor has a large dynamic range it can capture the darkest shadows and brightest highlights at the same time, without clipping the shadows or highlights. (RAW images preserve the dynamic range of your digital camera's sensor.) Adjusting the tonal range of the image changes how the dynamic range of the image is represented on a monitor or in a photo.

E

Elevation

Height of an imaginary light source over an image. The elevation of the light source works in conjunction with azimuth to generate a three-dimensional emboss effect.

Encode

Writing (or saving) a file format.

Encryption

Method of converting data into a secure format. You need a digital password or key to read an encrypted file.

EXIF (Exchangeable Image File)

Standard for storing information, primarily with images that use JPEG compression. Most digital cameras create EXIF information and embed it in the image file. For example, EXIF information can include details about shutter speed and whether a flash was used.

Export

Moving data from one application to another. The exporting application places the data in a format that the other application understands.

Exposure

Exposure is the amount of time that your digital camera's sensor is exposed to light.

F

Face Detection, Facial Recognition

Face Detection will detect the faces of individuals in your images. You can assign names to the faces, and ACDSee will recognize the individuals going forward. You can search for images using the names of the people in them.

Feather

Softening image edges to blend them into the background.

File Listing

In ACDSee, a report of the files currently displayed in Manage mode.

File Format

Medium for encoding information in a file. Each type of file has a different file format that specifies how it organizes the information it contains.

Filter

Program that can apply an effect to an image, such as an embossed appearance or a sepia tone.

Fisheye Distortion

In fisheye distortion, the photo appears to bulge outwards from the center, as if the photo were wrapped around a sphere.

G

Gamma

Range of color values a monitor, scanner, or printer can display. Adjusting this value increases or decreases the intensity of the light spectrum.

Grayscale Image

Image composed of different shades of gray.

H

Highlights

Highlights are the brightest or whitest parts of an image.

Histogram

A histogram is a graph that displays the dynamic range of shadows and highlights in an image.

Hue

Predominant color in an image.

I

Image Editor

Program that you can use to create and edit images. ACDSee Home is an image editor.

Image Resolution

Quality of image details and colors. Also used to describe the quality of monitors and printer output.

Image Viewer

Program that displays images. ACDSee Home is an image viewer.

Import

Bringing data into an application from another using a format that the receiving application understands.

Interpolation

Process that uses nearby pixels to estimate the color of new pixels added to the larger image. For example, interpolation might be used when enlarging a digital image.

IPTC

Standard method of encoding information within image files so that items such as descriptive comments and copyright information can be transmitted with the image.

J-K

Jaggies

Individual pixels displayed in an image with low resolution. The appearance of pixels in an image causes lines and curves to appear jagged.

L

Lens Vignetting

Unusual darkness in the corners of images as a result of an inability of the lens to distribute light into the corners of the image.

Lossless Compression

Form of compression that retains all image data and quality.

Lossless Rotation and Flipping

Rotation of a JPEG image without loss of image quality. This works best on images with dimensions that are a multiple of 8 or 16.

Lossy Compression

Form of compression that attempts to remove unnecessary data. This data loss can affect image quality.

M

Marquee

Dashed-line frame that identifies a selected portion of an image. Depending on the tool, you can resize or move a marquee with or without changing the underlying image.

Metadata

Information about an image and how it was taken. This can be stored within the image itself or in a sidecar file. For example, the metadata of digital camera images can contain the date and time the picture was taken, the shutter speed, the exposure settings of the camera, and whether a flash was used.

Monochrome Image

Image containing a single color.

N

Noise

Effect produced when a variety of pixel colors are used in the same color region. Noise often occurs in images with high ISO setting or slow shutter speed.

O

Opacity

Determines how visible an effect is when applied to an image or a selection. High opacity produces a more solid effect, while low opacity results in a nearly invisible effect.

Overexposed

Images that are overexposed have too many highlights, and tend to look faded. You typically overexpose images by exposing your digital camera's sensor to light for too long.

P-Q

Panning

Moving zoomed images vertically, horizontally, and diagonally across the display area to view specific areas of the image.

PDF

An acronym for Portable Document Format. You can view PDFs on any computer using the free Adobe Reader® software.

Perceptual

Rendering intent that scales all of the colors within one gamut to fit within another gamut. Best used for photographic images, as it maintains the relationship between the colors more accurately than the colors themselves.

Photo Album

See [album](#).

Photo Editor

See [image editor](#).

Pincushion Distortion

In pincushion distortion the photo appears to shrink inwards toward the center.

Pixel (or Picture Element)

Smallest visible portion of a digital image, arranged in rows and columns.

Plug-in

Software module that adds functionality to a larger program.

PPI (pixels per inch)

Measurement of how an image is displayed. More pixels per inch result in higher image quality.

Presets

A preset contains image correction settings. You can create and use presets to ensure that settings you apply are the same and consistent across all images.

Primary Colors

Colors that can produce other colors when blended. For example, in the RGB color model, red, green, and blue are primary colors.

R**Raster Image**

Image composed of a rectangular grid of pixels. Each pixel contains a defined value about its color, size, and location in the image. As a result, resizing the image can affect its quality.

Rasterize

To convert a vector layer to pixels, defining the resolution. To rasterize a layer can be seen as finalizing a layer, as it is no longer editable.

Rating

Assign ratings (1, 2, 3, 4, 5) to photos to help sort and manage them more easily.

RAW

An image file format. RAW files contain all of the image data that was captured by your digital camera's sensor. RAW files are not processed by your camera; instead, you must process RAW images using a photo editing program such as ACDSee Home.

Recursive

Program or task that can repeat itself indefinitely, such as a slideshow.

Red Eye

Red eye occurs when the light from your digital camera's flash reflects off the retinas in the subject's eyes. The subject's eyes look red instead of their normal color.

Relative Colorimetric

Rendering intent that maps the colors that fall exactly within the color gamuts of both the input and output devices. Best used for single- or limited-color images as colors outside of both gamuts may be mapped to a single color.

Render

Drawing images to your screen.

Rendering Intent

Approach used to map colors from one color gamut to another. There are four rendering intents available: [Perceptual](#), [Relative Colorimetric](#), [Saturation](#), and [Absolute Colorimetric](#).

Resolution

Quality and clarity of an image, measured in pixels, dots per inch, or pixels per inch.

RGB

Color model that uses red, green, and blue as its primary colors.

Ringing Artifacts

Distortion around the edges of image subjects, caused by compressing or resizing an image.

S

Saturation

Purity of a color. Higher color saturation results in more gray.

Saturation (rendering intent)

Rendering intent that maintains color saturation from one gamut to another. Best suited for images in which the actual color represented is less important than the color's vividness.

Selection

Portion of an image that you define with a selection tool. A marquee surrounds any selection made.

Sepia

Sepia-toned images are composed of shades of brown. Many old photographs have a sepia tone.

Sharpen

The sharpen tool is for sharpening images. The original image is blurred slightly. This blurred version of the image is subtracted from the original image, revealing the edges in the original image. These edges can then be sharpened by increasing contrast.

Sharpness

The sharpness in an image is determined, primarily, by your digital camera's lens and sensor. You can also create the illusion of sharpness by increasing the contrast between edges within an image.

Shortcut Menu

Menu that appears when you right-click within a program. Sometimes referred to as a context menu.

Slideshow

Automated sequential display of images. You can use slideshow software such as ACDSee Home to display slideshows of your images.

Soft Proofing

Using your computer's monitor as a proofing device. The monitor displays a simulation of how colors will appear when rendered by the printer.

T

Tagging

Tagging, like categories and ratings, is a great way to organize and group your photos without moving the files into different folders. You can tag a photo with one click. Similarly, you can display all tagged photos with one click.

Thumbnails

Small preview of a full-sized image.

Timestamp

Date and time associated with a file.

Transitions

Special effects used between images or video segments in slideshows, screensavers, and videos.

U

Underexposed

Images that are underexposed have too many shadows. Images typically become underexposed if you don't expose your digital camera's sensor to light long enough.

V

Vector Image

Image consisting of individual objects rather than pixels. Mathematical equations define the objects. You can adjust the size of a vector image and the image will retain its clarity and quality.

W

Watermark

Background text or graphics added to an image, usually to provide copyright protection.

White Balance

Removes color cast to create a photo that is correctly lit. You can use your camera settings to apply the correct white balance before taking an image, or correct the white balance in ACDSee.

Whitepoint

Lightest image area. You can control the intensity of the white in an image by adjusting its whitepoint.

X-Z

XML (Extensible Markup Language)

Standard language for Web documents.

Zoom

In ACDSee, zoom refers to the process of increasing or decreasing the display scale for an image. Increase the display scale to view a portion of an image or a specific image detail. Decrease the display scale to view more or all of the image.